

# [MS-ERREF]: Windows Error Codes

---

## Intellectual Property Rights Notice for Protocol Documentation

- This protocol documentation is covered by Microsoft copyrights. Regardless of any other terms that are contained in the terms of use for the Microsoft website that hosts this documentation, you may make copies of it in order to develop implementations of the protocols, and may distribute portions of it in your implementations of the protocols or your documentation as necessary to properly document the implementation. This permission also applies to any documents that are referenced in the protocol documentation.
- Microsoft does not claim any trade secret rights in this documentation.
- Microsoft has patents that may cover your implementations of the protocols. Neither this notice nor Microsoft's delivery of the documentation grants any licenses under those or any other Microsoft patents. If you are interested in obtaining a patent license, please contact [protocol@microsoft.com](mailto:protocol@microsoft.com).
- The names of companies and products contained in this documentation may be covered by trademarks or similar intellectual property rights. This notice does not grant any licenses under those rights.
- All other rights are reserved, and this notice does not grant any rights other than specifically described above, whether by implication, estoppel, or otherwise.

This protocol documentation is intended for use in conjunction with publicly available standard specifications, network programming art, and Microsoft Windows distributed systems concepts, and assumes that the reader either is familiar with the aforementioned material or has immediate access to it.

A protocol specification does not require the use of Microsoft programming tools or programming environments in order for you to develop an implementation. If you have access to Microsoft programming tools and environments you are free to take advantage of them.

## Revision Summary

Date	Revision History	Revision Class	Comments
02/14/2008	5.0.3	Editorial	Revised and edited the technical content.

# Table of Contents

<b>1</b>	<b>Introduction .....</b>	<b>3</b>
1.1	Glossary .....	3
1.2	References .....	3
1.2.1	Normative References .....	3
1.2.2	Informative References.....	3
1.3	Structure Overview .....	3
1.4	Relationship to Protocols and Other Structures .....	3
1.5	Applicability Statement .....	3
1.6	Versioning and Localization.....	3
1.7	Vendor Extensible Fields.....	3
<b>2</b>	<b>Structures.....</b>	<b>5</b>
2.1	HRESULT Values .....	5
2.2	Win32 Error Codes .....	220
2.3	NTSTATUS Values .....	374
<b>3</b>	<b>Structure Example .....</b>	<b>494</b>
<b>4</b>	<b>Security Considerations .....</b>	<b>495</b>
<b>5</b>	<b>Appendix A: Windows Behavior .....</b>	<b>496</b>
<b>6</b>	<b>Index.....</b>	<b>498</b>

# 1 Introduction

The Windows Error Codes document is a companion reference to the protocol specifications. It documents the details for the [HRESULT values](#), [Win32 error codes](#), and [NTSTATUS values](#).

The information in the Windows Error Codes was previously specified in "Windows System Overview" [MS-SYS] section 4.

## 1.1 Glossary

The following terms are defined in [\[MS-GLOS\]](#):

**HRESULT**  
**Message Identifier**  
**UUID**

## 1.2 References

### 1.2.1 Normative References

This specification relies upon no normative references.

### 1.2.2 Informative References

There are no informative references for this specification.

## 1.3 Structure Overview

If a protocol returns **HRESULTs**, the protocol uses HRESULTs, as specified in section [2.1](#).

If a protocol uses Win32 error codes, these values are taken from the Windows error number space, as specified in section [2.2](#).

If a protocol uses NTSTATUS values, these values are specified in section [2.3](#).

## 1.4 Relationship to Protocols and Other Structures

The structures documented in this specification do not depend on any other structures or protocols.

The structures in this document are returned by many protocols.

## 1.5 Applicability Statement

The data types specified in this document are applicable for use in any protocol that needs to include a discrete set of error codes.

## 1.6 Versioning and Localization

The structures in the Windows Error Codes require no versioning or localization information.

## 1.7 Vendor Extensible Fields

[HRESULTs](#): Vendors can choose their own values, as long as the **C** bit (0x20000000) is set, indicating it is a customer code. The structures documented in this specification have no vendor-extensible fields.

[Win32 Error Codes](#): Vendors should reuse those values with their indicated meanings. Choosing any other value runs the risk of a collision in the future.

[NTSTATUS](#): Vendors can choose their own values for this field, as long as the **C** bit (0x20000000) is set, indicating it is a customer code.

## 2 Structures

### 2.1 HRESULT Values

The HRESULT numbering space is vendor-extensible. Vendors can supply their own values for this field, as long as the **C** bit (0x20000000) is set, indicating it is a customer code.

The HRESULT numbering space has the following internal structure. The following diagram is independent of endianness (that is, the diagram is shown in host byte order); it merely shows the layout of the numbering space. Any protocol that uses NTSTATUS values on the wire is responsible for stating the order in which the bytes are placed on the wire.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
S	R	C	N	r	Facility											Code															

**S:** Severity. If set, indicates a failure result. If clear, indicates a success result.

**R:** Reserved. If the **N** bit is clear, this bit MUST be set to 0. If the **N** bit is set, the bit is defined by the NTSTATUS numbering space (as specified in section [2.3](#)).

**C:** Customer. This bit specifies if the value is customer-defined or Microsoft-defined. The bit is set for customer-defined values and clear for Microsoft-defined values.[<1>](#)

**N:** If set, indicates that the error code is an NTSTATUS value (as specified in section [2.3](#)) except that this bit is set.

**r:** If set, indicates the value MUST NOT be used as an error code, but instead can only be used as a **message identifier** for a display string.

**Facility:** The **facility** field indicates the system service that is responsible for the error. New facility codes as they become necessary. The following table lists the currently defined facility codes:

Value	Meaning
51	FACILITY_WINRM
36	FACILITY_WINDOWSUPDATE
80	FACILITY_WINDOWS_DEFENDER
24	FACILITY_WINDOWS_CE
8	FACILITY_WINDOWS
19	FACILITY_URT
22	FACILITY_UMI
41	FACILITY_TPM_SOFTWARE
40	FACILITY_TPM_SERVICES

Value	Meaning
23	FACILITY_SXS
3	FACILITY_STORAGE
34	FACILITY_STATE_MANAGEMENT
9	FACILITY_SSPI
16	FACILITY_SCARD
39	FACILITY_SHELL
15	FACILITY_SETUPAPI
9	FACILITY_SECURITY
1	FACILITY_RPC
48	FACILITY_PLA
7	FACILITY_WIN32
10	FACILITY_CONTROL
0	FACILITY_NULL
52	FACILITY_NDIS
35	FACILITY_METADIRECTORY
14	FACILITY_MSMQ
13	FACILITY_MEDIASERVER
12	FACILITY_INTERNET
4	FACILITY_ITF
53	FACILITY_USERMODE_HYPERVISOR
25	FACILITY_HTTP
38	FACILITY_GRAPHICS
50	FACILITY_FWP
49	FACILITY_FVE
31	FACILITY_USERMODE_FILTER_MANAGER
21	FACILITY_DPLAY
2	FACILITY_DISPATCH
37	FACILITY_DIRECTORYSERVICE
33	FACILITY_CONFIGURATION

Value	Meaning
17	FACILITY_COMPLUS
26	FACILITY_USERMODE_COMMONLOG
54	FACILITY_CMI
11	FACILITY_CERT
32	FACILITY_BACKGROUNDCOPY
20	FACILITY_ACS
18	FACILITY_AAF

**Code:** The remainder of the error code.

Combining the fields above into a single, 32-bit numbering space, the following HRESULT values are defined, in addition to those derived from NTSTATUS values (section 2.3) and [Win32 error codes \(section 2.2\)](#). Most values also have a default message defined, which can be used to map the value to a human-readable text message; when this is done, the HRESULT value is also known as a message identifier .

Note: In the following descriptions, a percentage sign (%) followed by one or more alphanumeric characters (for example, "%1" or "%hs") indicates a variable that is replaced by text at the time the value is returned.

Value	Meaning
STG_S_CONVERTED 0x00030200	The underlying file was converted to compound file format.
STG_S_BLOCK 0x00030201	The storage operation should block until more data is available.
STG_S_RETRYNOW 0x00030202	The storage operation should retry immediately.
STG_S_MONITORING 0x00030203	The notified event sink will not influence the storage operation.
STG_S_MULTIPLEOPENS 0x00030204	Multiple opens prevent consolidated (commit succeeded).
STG_S_CONSOLIDATIONFAILED 0x00030205	Consolidation of the storage file failed (commit succeeded).
STG_S_CANNOTCONSOLIDATE 0x00030206	Consolidation of the storage file is inappropriate (commit succeeded).
OLE_S_USEREG	Use the registry database to provide the requested

Value	Meaning
0x00040000	information.
OLE_S_STATIC 0x00040001	Success, but static.
OLE_S_MAC_CLIPFORMAT 0x00040002	Macintosh clipboard format.
DRAGDROP_S_DROP 0x00040100	Successful drop took place.
DRAGDROP_S_CANCEL 0x00040101	Drag-drop operation canceled.
DRAGDROP_S_USEDEFAULTCURSORS 0x00040102	Use the default cursor.
DATA_S_SAMEFORMATETC 0x00040130	Data has same FORMATETC.
VIEW_S_ALREADY_FROZEN 0x00040140	View is already frozen.
CACHE_S_FORMATETC_NOTSUPPORTED 0x00040170	FORMATETC not supported.
CACHE_S_SAMECACHE 0x00040171	Same cache.
CACHE_S_SOMECACHES_NOTUPDATED 0x00040172	Some caches are not updated.
OLEOBJ_S_INVALIDVERB 0x00040180	Invalid verb for OLE object.
OLEOBJ_S_CANNOT_DOVERB_NOW 0x00040181	Verb number is valid but verb cannot be done now.
OLEOBJ_S_INVALIDHWND 0x00040182	Invalid window handle passed.
INPLACE_S_TRUNCATED 0x000401A0	Message is too long; some of it had to be truncated before displaying.
CONVERT10_S_NO_PRESENTATION 0x000401C0	Unable to convert OLESTREAM to IStorage.
MK_S_REduced_TO_SELF 0x000401E2	Moniker reduced to itself.
MK_S_ME 0x000401E4	Common prefix is this moniker.



Value	Meaning
MK_S_HIM 0x000401E5	Common prefix is input moniker.
MK_S_US 0x000401E6	Common prefix is both monikers.
MK_S_MONIKERALREADYREGISTERED 0x000401E7	Moniker is already registered in running object table.
EVENT_S_SOME_SUBSCRIBERS_FAILED 0x00040200	An event was able to invoke some, but not all, of the subscribers.
EVENT_S_NOSUBSCRIBERS 0x00040202	An event was delivered, but there were no subscribers.
SCHED_S_TASK_READY 0x00041300	The task is ready to run at its next scheduled time.
SCHED_S_TASK_RUNNING 0x00041301	The task is currently running.
SCHED_S_TASK_DISABLED 0x00041302	The task will not run at the scheduled times because it has been disabled.
SCHED_S_TASK_HAS_NOT_RUN 0x00041303	The task has not yet run.
SCHED_S_TASK_NO_MORE_RUNS 0x00041304	There are no more runs scheduled for this task.
SCHED_S_TASK_NOT_SCHEDULED 0x00041305	One or more of the properties that are needed to run this task on a schedule have not been set.
SCHED_S_TASK_TERMINATED 0x00041306	The last run of the task was terminated by the user.
SCHED_S_TASK_NO_VALID_TRIGGERS 0x00041307	Either the task has no triggers, or the existing triggers are disabled or not set.
SCHED_S_EVENT_TRIGGER 0x00041308	Event triggers do not have set run times.
SCHED_S_SOME_TRIGGERS_FAILED 0x0004131B	The task is registered, but not all specified triggers will start the task.
SCHED_S_BATCH_LOGON_PROBLEM 0x0004131C	The task is registered, but it may fail to start. Batch logon privilege needs to be enabled

Value	Meaning
	for the task principal.
XACT_S_ASYNC 0x0004D000	An asynchronous operation was specified. The operation has begun, but its outcome is not known yet.
XACT_S_DEFECT 0x0004D001	XACT_S_DEFECT
XACT_S_READONLY 0x0004D002	The method call succeeded because the transaction was read-only.
XACT_S_SOMENORETAIN 0x0004D003	The transaction was successfully aborted. However, this is a coordinated transaction, and a number of enlisted resources were aborted outright because they could not support abort-retaining semantics.
XACT_S_OKINFORM 0x0004D004	No changes were made during this call, but the sink wants another chance to look if any other sinks make further changes.
XACT_S_MADECHANGESCONTENT 0x0004D005	The sink is content and wants the transaction to proceed. Changes were made to one or more resources during this call.
XACT_S_MADECHANGESINFORM 0x0004D006	The sink is for the moment and wants the transaction to proceed, but if other changes are made following this return by other event sinks, this sink wants another chance to look.
XACT_S_ALLNORETAIN 0x0004D007	The transaction was successfully aborted. However, the abort was nonretaining.
XACT_S_ABORTING 0x0004D008	An abort operation was already in progress.
XACT_S_SINGLEPHASE 0x0004D009	The resource manager has performed a single-phase commit of the transaction.
XACT_S_LOCALLY_OK 0x0004D00A	The local transaction has not aborted.

Value	Meaning
XACT_S_LASTRESOURCEMANAGER 0x0004D010	The resource manager has requested to be the coordinator (last resource manager) for the transaction.
CO_S_NOTALLINTERFACES 0x00080012	Not all the requested interfaces were available.
CO_S_MACHINENAMENOTFOUND 0x00080013	The specified machine name was not found in the cache.
SEC_I_CONTINUE_NEEDED 0x00090312	The function completed successfully, but it must be called again to complete the context.
SEC_I_COMPLETE_NEEDED 0x00090313	The function completed successfully, but CompleteToken must be called.
SEC_I_COMPLETE_AND_CONTINUE 0x00090314	The function completed successfully, but both CompleteToken and this function must be called to complete the context.
SEC_I_LOCAL_LOGON 0x00090315	The logon was completed, but no network authority was available. The logon was made using locally known information.
SEC_I_CONTEXT_EXPIRED 0x00090317	The context has expired and can no longer be used.
SEC_I_INCOMPLETE_CREDENTIALS 0x00090320	The credentials supplied were not complete and could not be verified. Additional information can be returned from the context.
SEC_I_RENEGOTIATE 0x00090321	The context data must be renegotiated with the peer.
SEC_I_NO_LSA_CONTEXT 0x00090323	There is no LSA mode context associated with this context.
SEC_I_SIGNATURE_NEEDED 0x0009035C	A signature operation must be performed before the user can authenticate.
CRYPT_I_NEW_PROTECTION_REQUIRED 0x00091012	The protected data needs to be reprotected.
NS_S_CALLPENDING	The requested operation is

Value	Meaning
0x000D0000L	pending completion.
NS_S_CALLABORTED 0x000D0001L	The requested operation was aborted by the client.
NS_S_STREAM_TRUNCATED 0x000D0002L	The stream was purposefully stopped before completion.
NS_S_REBUFFERING 0x000D0BC8L	The requested operation has caused the source to rebuffer.
NS_S_DEGRADING_QUALITY 0x000D0BC9L	The requested operation has caused the source to degrade codec quality.
NS_S_TRANSCRIPTOR_EOF 0x000D0BDBL	The transcriptor object has reached end of file.
NS_S_WMP_UI_VERSIONMISMATCH 0x000D0FE8L	An upgrade may be needed for the theme manager to correctly show this skin. Skin reports version: %.1f.
NS_S_WMP_EXCEPTION 0x000D0FE9L	An error occurred in one of the UI components.
NS_S_WMP_LOADED_GIF_IMAGE 0x000D1040L	Successfully loaded a GIF file.
NS_S_WMP_LOADED_PNG_IMAGE 0x000D1041L	Successfully loaded a PNG file.
NS_S_WMP_LOADED_BMP_IMAGE 0x000D1042L	Successfully loaded a BMP file.
NS_S_WMP_LOADED_JPG_IMAGE 0x000D1043L	Successfully loaded a JPG file.
NS_S_WMG_FORCE_DROP_FRAME 0x000D104FL	Drop this frame.
NS_S_WMR_ALREADYRENDERED 0x000D105FL	The specified stream has already been rendered.
NS_S_WMR_PINTYPEPARTIALMATCH 0x000D1060L	The specified type partially matches this pin type.
NS_S_WMR_PINTYPEFULLMATCH 0x000D1061L	The specified type fully matches this pin type.
NS_S_WMG_ADVISE_DROP_FRAME 0x000D1066L	The timestamp is late compared to the current render position. Advise dropping this frame.

Value	Meaning
NS_S_WMG_ADVISE_DROP_TO_KEYFRAME 0x000D1067L	The timestamp is severely late compared to the current render position. Advise dropping everything up to the next key frame.
NS_S_NEED_TO_BUY_BURN_RIGHTS 0x000D10DBL	No burn rights. You will be prompted to buy burn rights when you try to burn this file to an audio CD.
NS_S_WMPCORE_PLAYLISTCLEARABORT 0x000D10FEL	Failed to clear playlist because it was aborted by user.
NS_S_WMPCORE_PLAYLISTREMOVEITEMABORT 0x000D10FFL	Failed to remove item in the playlist since it was aborted by user.
NS_S_WMPCORE_PLAYLIST_CREATION_PENDING 0x000D1102L	Playlist is being generated asynchronously.
NS_S_WMPCORE_MEDIA_VALIDATION_PENDING 0x000D1103L	Validation of the media is pending...
NS_S_WMPCORE_PLAYLIST_REPEAT_SECONDARY_SEGMENTS_IGNORED 0x000D1104L	Encountered more than one Repeat block during ASX processing.
NS_S_WMPCORE_COMMAND_NOT_AVAILABLE 0x000D1105L	Current state of WMP disallows calling this method or property.
NS_S_WMPCORE_PLAYLIST_NAME_AUTO_GENERATED 0x000D1106L	Name for the playlist has been auto generated.
NS_S_WMPCORE_PLAYLIST_IMPORT_MISSING_ITEMS 0x000D1107L	The imported playlist does not contain all items from the original.
NS_S_WMPCORE_PLAYLIST_COLLAPSED_TO_SINGLE_MEDIA 0x000D1108L	The M3U playlist has been ignored because it only contains one item.
NS_S_WMPCORE_MEDIA_CHILD_PLAYLIST_OPEN_PENDING 0x000D1109L	The open for the child playlist associated with this media is pending.
NS_S_WMPCORE_MORE_NODES_AVAILABLE 0x000D110AL	More nodes support the interface requested, but the array for returning them is full.
NS_S_WMPBR_SUCCESS 0x000D1135L	Backup or Restore successful!.
NS_S_WMPBR_PARTIALSUCCESS	Transfer complete with

Value	Meaning
0x000D1136L	limitations.
NS_S_WMPEFFECT_TRANSPARENT 0x000D1144L	Request to the effects control to change transparency status to transparent.
NS_S_WMPEFFECT_OPAQUE 0x000D1145L	Request to the effects control to change transparency status to opaque.
NS_S_OPERATION_PENDING 0x000D114EL	The requested application pane is performing an operation and will not be released.
NS_S_TRACK_BUY_REQUIRES_ALBUM_PURCHASE 0x000D1359L	The file is only available for purchase when you buy the entire album.
NS_S_NAVIGATION_COMPLETE_WITH_ERRORS 0x000D135EL	There were problems completing the requested navigation. There are identifiers missing in the catalog.
NS_S_TRACK_ALREADY_DOWNLOADED 0x000D1361L	Track already downloaded.
NS_S_PUBLISHING_POINT_STARTED_WITH_FAILED_SINKS 0x000D1519L	The publishing point successfully started, but one or more of the requested data writer plug-ins failed.
NS_S_DRM_LICENSE_ACQUIRED 0x000D2726L	Status message: The license was acquired.
NS_S_DRM_INDIVIDUALIZED 0x000D2727L	Status message: The security upgrade has been completed.
NS_S_DRM_MONITOR_CANCELLED 0x000D2746L	Status message: License monitoring has been cancelled.
NS_S_DRM_ACQUIRE_CANCELLED 0x000D2747L	Status message: License acquisition has been cancelled.
NS_S_DRM_BURNABLE_TRACK 0x000D276EL	The track is burnable and had no playlist burn limit.
NS_S_DRM_BURNABLE_TRACK_WITH_PLAYLIST_RESTRICTION 0x000D276FL	The track is burnable but has a playlist burn limit.
NS_S_DRM_NEEDS_INDIVIDUALIZATION 0x000D27DEL	A security upgrade is required to perform the operation on this media file.

Value	Meaning
NS_S_REBOOT_RECOMMENDED 0x000D2AF8L	Installation was successful; however, some file cleanup is not complete. For best results, restart your computer.
NS_S_REBOOT_REQUIRED 0x000D2AF9L	Installation was successful; however, some file cleanup is not complete. To continue, you must restart your computer.
NS_S_EOSRECEDING 0x000D2F09L	EOS hit during rewinding.
NS_S_CHANGENOTICE 0x000D2F0DL	Internal.
ERROR_FLT_IO_COMPLETE 0x001F0001	The IO was completed by a filter.
ERROR_GRAPHICS_MODE_NOT_PINNED 0x00262307	No mode is pinned on the specified VidPN source or target.
ERROR_GRAPHICS_NO_PREFERRED_MODE 0x0026231E	Specified mode set does not specify preference for one of its modes.
ERROR_GRAPHICS_DATASET_IS_EMPTY 0x0026234B	Specified data set (for example, mode set, frequency range set, descriptor set, and topology) is empty.
ERROR_GRAPHICS_NO_MORE_ELEMENTS_IN_DATASET 0x0026234C	Specified data set (for example, mode set, frequency range set, descriptor set, and topology) does not contain any more elements.
ERROR_GRAPHICS_PATH_CONTENT_GEOMETRY_TRANSFORMATION_NOT_PINNED 0x00262351	Specified content transformation is not pinned on the specified VidPN present path.
PLA_S_PROPERTY_IGNORED 0x00300100	Property value will be ignored.
ERROR_NDIS_INDICATION_REQUIRED 0x00340001	The request will be completed later by a Network Driver Interface Specification (NDIS) status indication.
TRK_S_OUT_OF_SYNC 0x0DEAD100	The VolumeSequenceNumber of a MOVE_NOTIFICATION request is incorrect.

Value	Meaning
TRK_VOLUME_NOT_FOUND 0x0DEAD102	The VolumeID in a request was not found in the server's ServerVolumeTable.
TRK_VOLUME_NOT_OWNED 0x0DEAD103	A notification was sent to the LnkSvrMessage method, but the RequestMachine for the request was not the VolumeOwner for a VolumeID in the request.
TRK_S_NOTIFICATION_QUOTA_EXCEEDED 0x0DEAD107	The server received a MOVE_NOTIFICATION request, but the FileTable size limit has already been reached.
NS_I_TIGER_START 0x400D004FL	The Title Server %1 is running.
NS_I_CUB_START 0x400D0051L	Content Server %1 (%2) is starting.
NS_I_CUB_RUNNING 0x400D0052L	Content Server %1 (%2) is running.
NS_I_DISK_START 0x400D0054L	Disk %1 ( %2 ) on Content Server %3, is running.
NS_I_DISK_REBUILD_STARTED 0x400D0056L	Started rebuilding disk %1 ( %2 ) on Content Server %3.
NS_I_DISK_REBUILD_FINISHED 0x400D0057L	Finished rebuilding disk %1 ( %2 ) on Content Server %3.
NS_I_DISK_REBUILD_ABORTED 0x400D0058L	Aborted rebuilding disk %1 ( %2 ) on Content Server %3.
NS_I_LIMIT_FUNNELS 0x400D0059L	A NetShow administrator at network location %1 set the data stream limit to %2 streams.
NS_I_START_DISK 0x400D005AL	A NetShow administrator at network location %1 started disk %2.
NS_I_STOP_DISK 0x400D005BL	A NetShow administrator at network location %1 stopped disk %2.
NS_I_STOP_CUB 0x400D005CL	A NetShow administrator at network location %1 stopped Content Server %2.
NS_I_KILL_USERSESSION	A NetShow administrator at network location %1 aborted



Value	Meaning
0x400D005DL	user session %2 from the system.
NS_I_KILL_CONNECTION 0x400D005EL	A NetShow administrator at network location %1 aborted obsolete connection %2 from the system.
NS_I_REBUILD_DISK 0x400D005FL	A NetShow administrator at network location %1 started rebuilding disk %2.
MCMADM_I_NO_EVENTS 0x400D0069L	Event initialization failed, there will be no MCM events.
NS_I_LOGGING_FAILED 0x400D006EL	The logging operation failed.
NS_I_LIMIT_BANDWIDTH 0x400D0070L	A NetShow administrator at network location %1 set the maximum bandwidth limit to %2 bps.
NS_I_CUB_UNFAIL_LINK 0x400D0191L	Content Server %1 (%2) has established its link to Content Server %3.
NS_I_RESTRIPE_START 0x400D0193L	Restripe operation has started.
NS_I_RESTRIPE_DONE 0x400D0194L	Restripe operation has completed.
NS_I_RESTRIPE_DISK_OUT 0x400D0196L	Content disk %1 (%2) on Content Server %3 has been restriped out.
NS_I_RESTRIPE_CUB_OUT 0x400D0197L	Content server %1 (%2) has been restriped out.
NS_I_DISK_STOP 0x400D0198L	Disk %1 ( %2 ) on Content Server %3, has been offlined.
NS_I_PLAYLIST_CHANGE_RECEDING 0x400D14BEL	The playlist change occurred while receding.
NS_I_RECONNECTED 0x400D2EFFL	The client is reconnected.
NS_I_NOLOG_STOP 0x400D2F01L	Forcing a switch to a pending header on start.
NS_I_EXISTING_PACKETIZER 0x400D2F03L	There is already an existing packetizer plugin for the stream.

Value	Meaning
NS_I_MANUAL_PROXY 0x400D2F04L	The proxy setting is manual.
ERROR_GRAPHICS_DRIVER_MISMATCH 0x40262009	The kernel driver detected a version mismatch between it and the user mode driver.
ERROR_GRAPHICS_UNKNOWN_CHILD_STATUS 0x4026242F	Child device presence was not reliably detected.
ERROR_GRAPHICS_LEADLINK_START_DEFERRED 0x40262437	Starting the lead-link adapter has been deferred temporarily.
ERROR_GRAPHICS_POLLING_TOO_FREQUENTLY 0x40262439	The display adapter is being polled for children too frequently at the same polling level.
ERROR_GRAPHICS_START_DEFERRED 0x4026243A	Starting the adapter has been deferred temporarily.
E_NOTIMPL 0x80000001	Not implemented.
E_OUTOFMEMORY 0x80000002	Ran out of memory.
E_INVALIDARG 0x80000003	One or more arguments are invalid. This value is typically only returned by software when compiled for MacOS.
E_NOINTERFACE 0x80000004	No such interface supported.
E_POINTER 0x80000005	Invalid pointer.
E_HANDLE 0x80000006	Invalid handle.
E_ABORT 0x80000007	Operation aborted.
E_FAIL 0x80000008	Unspecified error.
E_ACCESSDENIED 0x80000009	General access denied error.
E_PENDING 0x8000000A	The data necessary to complete this operation is not yet available.

Value	Meaning
E_NOTIMPL 0x80004001	Not implemented.
E_NOINTERFACE 0x80004002	No such interface supported.
E_POINTER 0x80004003	Invalid pointer.
E_ABORT 0x80004004	Operation aborted.
E_FAIL 0x80004005	Unspecified error.
CO_E_INIT_TLS 0x80004006	Thread local storage failure.
CO_E_INIT_SHARED_ALLOCATOR 0x80004007	Get shared memory allocator failure.
CO_E_INIT_MEMORY_ALLOCATOR 0x80004008	Get memory allocator failure.
CO_E_INIT_CLASS_CACHE 0x80004009	Unable to initialize class cache.
CO_E_INIT_RPC_CHANNEL 0x8000400A	Unable to initialize remote procedure call (RPC) services.
CO_E_INIT_TLS_SET_CHANNEL_CONTROL 0x8000400B	Cannot set thread local storage channel control.
CO_E_INIT_TLS_CHANNEL_CONTROL 0x8000400C	Could not allocate thread local storage channel control.
CO_E_INIT_UNACCEPTED_USER_ALLOCATOR 0x8000400D	The user-supplied memory allocator is unacceptable.
CO_E_INIT_SCM_MUTEX_EXISTS 0x8000400E	The OLE service mutex already exists.
CO_E_INIT_SCM_FILE_MAPPING_EXISTS 0x8000400F	The OLE service file mapping already exists.
CO_E_INIT_SCM_MAP_VIEW_OF_FILE 0x80004010	Unable to map view of file for OLE service.
CO_E_INIT_SCM_EXEC_FAILURE 0x80004011	Failure attempting to launch OLE service.
CO_E_INIT_ONLY_SINGLE_THREADED	There was an attempt to call CoInitialize a second time

Value	Meaning
0x80004012	while single-threaded.
CO_E_CANT_REMOTE 0x80004013	A Remote activation was necessary but was not allowed.
CO_E_BAD_SERVER_NAME 0x80004014	A Remote activation was necessary, but the server name provided was invalid.
CO_E_WRONG_SERVER_IDENTITY 0x80004015	The class is configured to run as a security ID different from the caller.
CO_E_OLE1DDE_DISABLED 0x80004016	Use of OLE1 services requiring Dynamic Data Exchange (DDE) Windows is disabled.
CO_E_RUNAS_SYNTAX 0x80004017	A RunAs specification must be <domain name>\<user name> or simply <user name>.
CO_E_CREATEPROCESS_FAILURE 0x80004018	The server process could not be started. The path name may be incorrect.
CO_E_RUNAS_CREATEPROCESS_FAILURE 0x80004019	The server process could not be started as the configured identity. The path name may be incorrect or unavailable.
CO_E_RUNAS_LOGON_FAILURE 0x8000401A	The server process could not be started because the configured identity is incorrect. Check the user name and password.
CO_E_LAUNCH_PERMISSION_DENIED 0x8000401B	The client is not allowed to launch this server.
CO_E_START_SERVICE_FAILURE 0x8000401C	The service providing this server could not be started.
CO_E_REMOTE_COMMUNICATION_FAILURE 0x8000401D	This computer was unable to communicate with the computer providing the server.
CO_E_SERVER_START_TIMEOUT 0x8000401E	The server did not respond after being launched.
CO_E_CLSREG_INCONSISTENT 0x8000401F	The registration information for this server is inconsistent or incomplete.
CO_E_IIDREG_INCONSISTENT	The registration information

Value	Meaning
0x80004020	for this interface is inconsistent or incomplete.
CO_E_NOT_SUPPORTED 0x80004021	The operation attempted is not supported.
CO_E_RELOAD_DLL 0x80004022	A DLL must be loaded.
CO_E_MSI_ERROR 0x80004023	A Microsoft Software Installer error was encountered.
CO_E_ATTEMPT_TO_CREATE_OUTSIDE_CLIENT_CONTEXT 0x80004024	The specified activation could not occur in the client context as specified.
CO_E_SERVER_PAUSED 0x80004025	Activations on the server are paused.
CO_E_SERVER_NOT_PAUSED 0x80004026	Activations on the server are not paused.
CO_E_CLASS_DISABLED 0x80004027	The component or application containing the component has been disabled.
CO_E_CLRNOTAVAILABLE 0x80004028	The common language runtime is not available.
CO_E_ASYNC_WORK_REJECTED 0x80004029	The thread-pool rejected the submitted asynchronous work.
CO_E_SERVER_INIT_TIMEOUT 0x8000402A	The server started, but it did not finish initializing in a timely fashion.
CO_E_NO_SECCTX_IN_ACTIVATE 0x8000402B	Unable to complete the call because there is no COM+ security context inside IObjectControl.Activate.
CO_E_TRACKER_CONFIG 0x80004030	The provided tracker configuration is invalid.
CO_E_THREADPOOL_CONFIG 0x80004031	The provided thread pool configuration is invalid.
CO_E_SXS_CONFIG 0x80004032	The provided side-by-side configuration is invalid.
CO_E_MALFORMED_SPN 0x80004033	The server principal name (SPN) obtained during security negotiation is malformed.
E_UNEXPECTED	Catastrophic failure.

Value	Meaning
0x8000FFFF	
RPC_E_CALL_REJECTED 0x80010001	Call was rejected by callee.
RPC_E_CALL_CANCELED 0x80010002	Call was canceled by the message filter.
RPC_E_CANTPOST_INSENDCALL 0x80010003	The caller is dispatching an intertask SendMessage call and cannot call out via PostMessage.
RPC_E_CANTCALLOUT_INASYNCCALL 0x80010004	The caller is dispatching an asynchronous call and cannot make an outgoing call on behalf of this call.
RPC_E_CANTCALLOUT_INEXTERNALCALL 0x80010005	It is illegal to call out while inside message filter.
RPC_E_CONNECTION_TERMINATED 0x80010006	The connection terminated or is in a bogus state and can no longer be used. Other connections are still valid.
RPC_E_SERVER_DIED 0x80010007	The callee (the server, not the server application) is not available and disappeared; all connections are invalid. The call may have executed.
RPC_E_CLIENT_DIED 0x80010008	The caller (client) disappeared while the callee (server) was processing a call.
RPC_E_INVALID_DATAPACKET 0x80010009	The data packet with the marshaled parameter data is incorrect.
RPC_E_CANTTRANSMIT_CALL 0x8001000A	The call was not transmitted properly; the message queue was full and was not emptied after yielding.
RPC_E_CLIENT_CANTMARSHAL_DATA 0x8001000B	The client RPC caller cannot marshal the parameter data due to errors (such as low memory).
RPC_E_CLIENT_CANTUNMARSHAL_DATA 0x8001000C	The client RPC caller cannot unmarshal the return data due to errors (such as low memory).
RPC_E_SERVER_CANTMARSHAL_DATA 0x8001000D	The server RPC callee cannot marshal the return data due to

Value	Meaning
	errors (such as low memory).
RPC_E_SERVER_CANTUNMARSHAL_DATA 0x8001000E	The server RPC callee cannot unmarshal the parameter data due to errors (such as low memory).
RPC_E_INVALID_DATA 0x8001000F	Received data is invalid. The data may be server or client data.
RPC_E_INVALID_PARAMETER 0x80010010	A particular parameter is invalid and cannot be (un)marshaled.
RPC_E_CANTCALLOUT_AGAIN 0x80010011	There is no second outgoing call on same channel in DDE conversation.
RPC_E_SERVER_DIED_DNE 0x80010012	The callee (the server, not the server application) is not available and disappeared; all connections are invalid. The call did not execute.
RPC_E_SYS_CALL_FAILED 0x80010100	System call failed.
RPC_E_OUT_OF_RESOURCES 0x80010101	Could not allocate some required resource (such as memory or events)
RPC_E_ATTEMPTED_MULTITHREAD 0x80010102	Attempted to make calls on more than one thread in single-threaded mode.
RPC_E_NOT_REGISTERED 0x80010103	The requested interface is not registered on the server object.
RPC_E_FAULT 0x80010104	RPC could not call the server or could not return the results of calling the server.
RPC_E_SERVERFAULT 0x80010105	The server threw an exception.
RPC_E_CHANGED_MODE 0x80010106	Cannot change thread mode after it is set.
RPC_E_INVALIDMETHOD 0x80010107	The method called does not exist on the server.
RPC_E_DISCONNECTED 0x80010108	The object invoked has disconnected from its clients.

Value	Meaning
RPC_E_RETRY 0x80010109	The object invoked chose not to process the call now. Try again later.
RPC_E_SERVERCALL_RETRYLATER 0x8001010A	The message filter indicated that the application is busy.
RPC_E_SERVERCALL_REJECTED 0x8001010B	The message filter rejected the call.
RPC_E_INVALID_CALldata 0x8001010C	A call control interface was called with invalid data.
RPC_E_CANTCALLOUT_ININPUTSYNCCALL 0x8001010D	An outgoing call cannot be made because the application is dispatching an input-synchronous call.
RPC_E_WRONG_THREAD 0x8001010E	The application called an interface that was marshaled for a different thread.
RPC_E_THREAD_NOT_INIT 0x8001010F	CoInitialize has not been called on the current thread.
RPC_E_VERSION_MISMATCH 0x80010110	The version of OLE on the client and server machines does not match.
RPC_E_INVALID_HEADER 0x80010111	OLE received a packet with an invalid header.
RPC_E_INVALID_EXTENSION 0x80010112	OLE received a packet with an invalid extension.
RPC_E_INVALID_IPID 0x80010113	The requested object or interface does not exist.
RPC_E_INVALID_OBJECT 0x80010114	The requested object does not exist.
RPC_S_CALLPENDING 0x80010115	OLE has sent a request and is waiting for a reply.
RPC_S_WAITONTIMER 0x80010116	OLE is waiting before retrying a request.
RPC_E_CALL_COMPLETE 0x80010117	Call context cannot be accessed after call completed.
RPC_E_UNSECURE_CALL 0x80010118	Impersonate on unsecure calls is not supported.
RPC_E_TOO_LATE	Security must be initialized



Value	Meaning
0x80010119	before any interfaces are marshaled or unmarshaled. It cannot be changed after initialized.
RPC_E_NO_GOOD_SECURITY_PACKAGES 0x8001011A	No security packages are installed on this machine, the user is not logged on, or there are no compatible security packages between the client and server.
RPC_E_ACCESS_DENIED 0x8001011B	Access is denied.
RPC_E_REMOTE_DISABLED 0x8001011C	Remote calls are not allowed for this process.
RPC_E_INVALID_OBJREF 0x8001011D	The marshaled interface data packet (OBJREF) has an invalid or unknown format.
RPC_E_NO_CONTEXT 0x8001011E	No context is associated with this call. This happens for some custom marshaled calls and on the client side of the call.
RPC_E_TIMEOUT 0x8001011F	This operation returned because the time-out period expired.
RPC_E_NO_SYNC 0x80010120	There are no synchronize objects to wait on.
RPC_E_FULLSIC_REQUIRED 0x80010121	Full subject issuer chain Secure Sockets Layer (SSL) principal name expected from the server.
RPC_E_INVALID_STD_NAME 0x80010122	Principal name is not a valid Microsoft standard (msstd) name.
CO_E_FAILEDTOIMPERSONATE 0x80010123	Unable to impersonate DCOM client.
CO_E_FAILEDTOGETSECCTX 0x80010124	Unable to obtain server's security context.
CO_E_FAILEDTOOPENTHREADTOKEN 0x80010125	Unable to open the access token of the current thread.
CO_E_FAILEDTOGETTOKENINFO 0x80010126	Unable to obtain user information from an access token.

Value	Meaning
CO_E_TRUSTEEDOESNTMATCHCLIENT 0x80010127	The client who called IAccessControl::IsAccessPermitted was not the trustee provided to the method.
CO_E_FAILEDTOQUERYCLIENTBLANKET 0x80010128	Unable to obtain the client's security blanket.
CO_E_FAILEDTOSETDACL 0x80010129	Unable to set a discretionary access control list (ACL) into a security descriptor.
CO_E_ACCESSCHECKFAILED 0x8001012A	The system function AccessCheck returned false.
CO_E_NETACCESSAPIFAILED 0x8001012B	Either NetAccessDel or NetAccessAdd returned an error code.
CO_E_WRONGTRUSTEENAMESYNTAX 0x8001012C	One of the trustee strings provided by the user did not conform to the <Domain>\<Name> syntax and it was not the "*" string".
CO_E_INVALIDSID 0x8001012D	One of the security identifiers provided by the user was invalid.
CO_E_CONVERSIONFAILED 0x8001012E	Unable to convert a wide character trustee string to a multiple-byte trustee string.
CO_E_NOMATCHINGSIDFOUND 0x8001012F	Unable to find a security identifier that corresponds to a trustee string provided by the user.
CO_E_LOOKUPACCSIDFAILED 0x80010130	The system function LookupAccountSID failed.
CO_E_NOMATCHINGNAMEFOUND 0x80010131	Unable to find a trustee name that corresponds to a security identifier provided by the user.
CO_E_LOOKUPACCNAMEFAILED 0x80010132	The system function LookupAccountName failed.
CO_E_SETSERLHNDLFAILED 0x80010133	Unable to set or reset a serialization handle.
CO_E_FAILEDTOGETWINDIR 0x80010134	Unable to obtain the Windows directory.
CO_E_PATHTOOLONG	Path too long.

Value	Meaning
0x80010135	
CO_E_FAILEDTOGENUUID 0x80010136	Unable to generate a <b>UUID</b> .
CO_E_FAILEDTOCREATEFILE 0x80010137	Unable to create file.
CO_E_FAILEDTOCLOSEHANDLE 0x80010138	Unable to close a serialization handle or a file handle.
CO_E_EXCEEDSYSACLLIMIT 0x80010139	The number of access control entries (ACEs) in an ACL exceeds the system limit.
CO_E_ACESINWRONGORDER 0x8001013A	Not all the DENY_ACCESS ACEs are arranged in front of the GRANT_ACCESS ACEs in the stream.
CO_E_INCOMPATIBLESTREAMVERSION 0x8001013B	The version of ACL format in the stream is not supported by this implementation of IAccessControl.
CO_E_FAILEDTOOPENPROCESSTOKEN 0x8001013C	Unable to open the access token of the server process.
CO_E_DECODEFAILED 0x8001013D	Unable to decode the ACL in the stream provided by the user.
CO_E_ACNOTINITIALIZED 0x8001013F	The COM IAccessControl object is not initialized.
CO_E_CANCEL_DISABLED 0x80010140	Call Cancellation is disabled.
RPC_E_UNEXPECTED 0x8001FFFF	An internal error occurred.
DISP_E_UNKNOWNINTERFACE 0x80020001	Unknown interface.
DISP_E_MEMBERNOTFOUND 0x80020003	Member not found.
DISP_E_PARAMNOTFOUND 0x80020004	Parameter not found.
DISP_E_TYEMISMATCH 0x80020005	Type mismatch.
DISP_E_UNKNOWNNAME	Unknown name.

Value	Meaning
0x80020006	
DISP_E_NONAMEDARGS 0x80020007	No named arguments.
DISP_E_BADVARTYPE 0x80020008	Bad variable type.
DISP_E_EXCEPTION 0x80020009	Exception occurred.
DISP_E_OVERFLOW 0x8002000A	Out of present range.
DISP_E_BADINDEX 0x8002000B	Invalid index.
DISP_E_UNKNOWNLCID 0x8002000C	Unknown language.
DISP_E_ARRAYISLOCKED 0x8002000D	Memory is locked.
DISP_E_BADPARAMCOUNT 0x8002000E	Invalid number of parameters.
DISP_E_PARAMNOTOPTIONAL 0x8002000F	Parameter not optional.
DISP_E_BADCALLEE 0x80020010	Invalid callee.
DISP_E_NOTACOLLECTION 0x80020011	Does not support a collection.
DISP_E_DIVBYZERO 0x80020012	Division by zero.
DISP_E_BUFFERTOOSMALL 0x80020013	Buffer too small.
TYPE_E_BUFFERTOOSMALL 0x80028016	Buffer too small.
TYPE_E_FIELDNOTFOUND 0x80028017	Field name not defined in the record.
TYPE_E_INVDATAREAD 0x80028018	Old format or invalid type library.
TYPE_E_UNSUPFORMAT 0x80028019	Old format or invalid type library.

Value	Meaning
TYPE_E_REGISTRYACCESS 0x8002801C	Error accessing the OLE registry.
TYPE_E_LIBNOTREGISTERED 0x8002801D	Library not registered.
TYPE_E_UNDEFINEDTYPE 0x80028027	Bound to unknown type.
TYPE_E_QUALIFIEDNAMEDISALLOWED 0x80028028	Qualified name disallowed.
TYPE_E_INVALIDSTATE 0x80028029	Invalid forward reference, or reference to uncompiled type.
TYPE_E_WRONGTYPEKIND 0x8002802A	Type mismatch.
TYPE_E_ELEMENTNOTFOUND 0x8002802B	Element not found.
TYPE_E_AMBIGUOUSNAME 0x8002802C	Ambiguous name.
TYPE_E_NAMECONFLICT 0x8002802D	Name already exists in the library.
TYPE_E_UNKNOWNLCID 0x8002802E	Unknown language code identifier (LCID).
TYPE_E_DLLFUNCTIONNOTFOUND 0x8002802F	Function not defined in specified DLL.
TYPE_E_BADMODULEKIND 0x800288BD	Wrong module kind for the operation.
TYPE_E_SIZETOOBIG 0x800288C5	Size may not exceed 64 KB.
TYPE_E_DUPLICATEID 0x800288C6	Duplicate ID in inheritance hierarchy.
TYPE_E_INVALIDID 0x800288CF	Incorrect inheritance depth in standard OLE hmember.
TYPE_E_TYPEMISMATCH 0x80028CA0	Type mismatch.
TYPE_E_OUTOFBOUNDS 0x80028CA1	Invalid number of arguments.
TYPE_E_IOERROR	I/O error.

Value	Meaning
0x80028CA2	
TYPE_E_CANTCREATETMPFILE 0x80028CA3	Error creating unique .tmp file.
TYPE_E_CANTLOADLIBRARY 0x80029C4A	Error loading type library or DLL.
TYPE_E_INCONSISTENTPROPFUNCS 0x80029C83	Inconsistent property functions.
TYPE_E_CIRCULARTYPE 0x80029C84	Circular dependency between types and modules.
STG_E_INVALIDFUNCTION 0x80030001	Unable to perform requested operation.
STG_E_FILENOTFOUND 0x80030002	%1 could not be found.
STG_E_PATHNOTFOUND 0x80030003	The path %1 could not be found.
STG_E_TOOMANYOPENFILES 0x80030004	There are insufficient resources to open another file.
STG_E_ACCESSDENIED 0x80030005	Access denied.
STG_E_INVALIDHANDLE 0x80030006	Attempted an operation on an invalid object.
STG_E_INSUFFICIENTMEMORY 0x80030008	There is insufficient memory available to complete operation.
STG_E_INVALIDPOINTER 0x80030009	Invalid pointer error.
STG_E_NOMOREFILES 0x80030012	There are no more entries to return.
STG_E_DISKISWRITEPROTECTED 0x80030013	Disk is write-protected.
STG_E_SEEKERROR 0x80030019	An error occurred during a seek operation.
STG_E_WRITEFAULT 0x8003001D	A disk error occurred during a write operation.
STG_E_READFAULT 0x8003001E	A disk error occurred during a read operation.

Value	Meaning
STG_E_SHAREVIOLATION 0x80030020	A share violation has occurred.
STG_E_LOCKVIOLATION 0x80030021	A lock violation has occurred.
STG_E_FILEALREADYEXISTS 0x80030050	%1 already exists.
STG_E_INVALIDPARAMETER 0x80030057	Invalid parameter error.
STG_E_MEDIUMFULL 0x80030070	There is insufficient disk space to complete operation.
STG_E_PROPSETMISMATCHED 0x800300F0	Illegal write of non-simple property to simple property set.
STG_E_ABNORMALAPIEXIT 0x800300FA	An application programming interface (API) call exited abnormally.
STG_E_INVALIDHEADER 0x800300FB	The file %1 is not a valid compound file.
STG_E_INVALIDNAME 0x800300FC	The name %1 is not valid.
STG_E_UNKNOWN 0x800300FD	An unexpected error occurred.
STG_E_UNIMPLEMENTEDFUNCTION 0x800300FE	That function is not implemented.
STG_E_INVALIDFLAG 0x800300FF	Invalid flag error.
STG_E_INUSE 0x80030100	Attempted to use an object that is busy.
STG_E_NOTCURRENT 0x80030101	The storage has been changed since the last commit.
STG_E_REVERTED 0x80030102	Attempted to use an object that has ceased to exist.
STG_E_CANTSAVE 0x80030103	Cannot save.
STG_E_OLDFORMAT 0x80030104	The compound file %1 was produced with an incompatible version of storage.

Value	Meaning
STG_E_OLDDLL 0x80030105	The compound file %1 was produced with a newer version of storage.
STG_E_SHAREREQUIRED 0x80030106	Share.exe or equivalent is required for operation.
STG_E_NOTFILEBASEDSTORAGE 0x80030107	Illegal operation called on non-file based storage.
STG_E_EXTANTMARSHALLINGS 0x80030108	Illegal operation called on object with extant marshalings.
STG_E_DOCFILECORRUPT 0x80030109	The docfile has been corrupted.
STG_E_BADBASEADDRESS 0x80030110	OLE32.DLL has been loaded at the wrong address.
STG_E_DOCFILETOOLARGE 0x80030111	The compound file is too large for the current implementation.
STG_E_NOTSIMPLEFORMAT 0x80030112	The compound file was not created with the STGM_SIMPLE flag.
STG_E_INCOMPLETE 0x80030201	The file download was aborted abnormally. The file is incomplete.
STG_E_TERMINATED 0x80030202	The file download has been terminated.
STG_E_STATUS_COPY_PROTECTION_FAILURE 0x80030305	Generic Copy Protection Error.
STG_E_CSS_AUTHENTICATION_FAILURE 0x80030306	Copy Protection Error—DVD CSS Authentication failed.
STG_E_CSS_KEY_NOT_PRESENT 0x80030307	Copy Protection Error—The given sector does not have a valid CSS key.
STG_E_CSS_KEY_NOT_ESTABLISHED 0x80030308	Copy Protection Error—DVD session key not established.
STG_E_CSS_SCRAMBLED_SECTOR 0x80030309	Copy Protection Error—The read failed because the sector is encrypted.
STG_E_CSS_REGION_MISMATCH 0x8003030A	Copy Protection Error—The current DVD's region does not correspond to the region



Value	Meaning
	setting of the drive.
STG_E_RESETS_EXHAUSTED 0x8003030B	Copy Protection Error—The drive's region setting may be permanent or the number of user resets has been exhausted.
OLE_E_OLEVERB 0x80040000	Invalid OLEVERB structure.
OLE_E_ADVFLG 0x80040001	Invalid advise flags.
OLE_E_ENUM_NOMORE 0x80040002	Cannot enumerate any more because the associated data is missing.
OLE_E_ADVISENOTSUPPORTED 0x80040003	This implementation does not take advises.
OLE_E_NOCONNECTION 0x80040004	There is no connection for this connection ID.
OLE_E_NOTRUNNING 0x80040005	Need to run the object to perform this operation.
OLE_E_NOCACHE 0x80040006	There is no cache to operate on.
OLE_E_BLANK 0x80040007	Uninitialized object.
OLE_E_CLASSDIFF 0x80040008	Linked object's source class has changed.
OLE_E_CANT_GETMONIKER 0x80040009	Not able to get the moniker of the object.
OLE_E_CANT_BINDTOSOURCE 0x8004000A	Not able to bind to the source.
OLE_E_STATIC 0x8004000B	Object is static; operation not allowed.
OLE_E_PROMPTSAVECANCELLED 0x8004000C	User canceled out of the Save dialog box.
OLE_E_INVALIDRECT 0x8004000D	Invalid rectangle.
OLE_E_WRONGCOMPOBJ 0x8004000E	compobj.dll is too old for the ole2.dll initialized.

Value	Meaning
OLE_E_INVALIDHWND 0x8004000F	Invalid window handle.
OLE_E_NOT_INPLACEACTIVE 0x80040010	Object is not in any of the inplace active states.
OLE_E_CANTCONVERT 0x80040011	Not able to convert object.
OLE_E_NOSTORAGE 0x80040012	Not able to perform the operation because object is not given storage yet.
DV_E_FORMATETC 0x80040064	Invalid FORMATETC structure.
DV_E_DVTARGETDEVICE 0x80040065	Invalid DVTARGETDEVICE structure.
DV_E_STGMEDIUM 0x80040066	Invalid STDGMEDIUM structure.
DV_E_STATDATA 0x80040067	Invalid STATDATA structure.
DV_E_LINDEX 0x80040068	Invalid lindex.
DV_E_TYMED 0x80040069	Invalid TYMED structure.
DV_E_CLIPFORMAT 0x8004006A	Invalid clipboard format.
DV_E_DVASPECT 0x8004006B	Invalid aspects.
DV_E_DVTARGETDEVICE_SIZE 0x8004006C	The <i>tdSize</i> parameter of the DVTARGETDEVICE structure is invalid.
DV_E_NOVIEWOBJECT 0x8004006D	Object does not support IViewObject interface.
DRAGDROP_E_NOTREGISTERED 0x80040100	Trying to revoke a drop target that has not been registered.
DRAGDROP_E_ALREADYREGISTERED 0x80040101	This window has already been registered as a drop target.
DRAGDROP_E_INVALIDHWND 0x80040102	Invalid window handle.

Value	Meaning
CLASS_E_NOAGGREGATION 0x80040110	Class does not support aggregation (or class object is remote).
CLASS_E_CLASSNOTAVAILABLE 0x80040111	ClassFactory cannot supply requested class.
CLASS_E_NOTLICENSED 0x80040112	Class is not licensed for use.
VIEW_E_DRAW 0x80040140	Error drawing view.
REGDB_E_READREGDB 0x80040150	Could not read key from registry.
REGDB_E_WRITEREGDB 0x80040151	Could not write key to registry.
REGDB_E_KEYMISSING 0x80040152	Could not find the key in the registry.
REGDB_E_INVALIDVALUE 0x80040153	Invalid value for registry.
REGDB_E_CLASSNOTREG 0x80040154	Class not registered.
REGDB_E_IIDNOTREG 0x80040155	Interface not registered.
REGDB_E_BADTHREADINGMODEL 0x80040156	Threading model entry is not valid.
CAT_E_CATIDNOEXIST 0x80040160	CATID does not exist.
CAT_E_NODESCRIPTION 0x80040161	Description not found.
CS_E_PACKAGE_NOTFOUND 0x80040164	No package in the software installation data in Active Directory meets this criteria.
CS_E_NOT_DELETABLE 0x80040165	Deleting this will break the referential integrity of the software installation data in Active Directory.
CS_E_CLASS_NOTFOUND 0x80040166	The CLSID was not found in the software installation data in Active Directory.
CS_E_INVALID_VERSION	The software installation data

Value	Meaning
0x80040167	in Active Directory is corrupt.
CS_E_NO_CLASSSTORE 0x80040168	There is no software installation data in Active Directory.
CS_E_OBJECT_NOTFOUND 0x80040169	There is no software installation data object in Active Directory.
CS_E_OBJECT_ALREADY_EXISTS 0x8004016A	The software installation data object in Active Directory already exists.
CS_E_INVALID_PATH 0x8004016B	The path to the software installation data in Active Directory is not correct.
CS_E_NETWORK_ERROR 0x8004016C	A network error interrupted the operation.
CS_E_ADMIN_LIMIT_EXCEEDED 0x8004016D	The size of this object exceeds the maximum size set by the administrator.
CS_E_SCHEMA_MISMATCH 0x8004016E	The schema for the software installation data in Active Directory does not match the required schema.
CS_E_INTERNAL_ERROR 0x8004016F	An error occurred in the software installation data in Active Directory.
CACHE_E_NOCACHE_UPDATED 0x80040170	Cache not updated.
OLEOBJ_E_NOVERBS 0x80040180	No verbs for OLE object.
OLEOBJ_E_INVALIDVERB 0x80040181	Invalid verb for OLE object.
INPLACE_E_NOTUNDOABLE 0x800401A0	Undo is not available.
INPLACE_E_NOTOOLSPACE 0x800401A1	Space for tools is not available.
CONVERT10_E_OLESTREAM_GET 0x800401C0	OLESTREAM Get method failed.
CONVERT10_E_OLESTREAM_PUT 0x800401C1	OLESTREAM Put method failed.
CONVERT10_E_OLESTREAM_FMT	Contents of the OLESTREAM

Value	Meaning
0x800401C2	not in correct format.
CONVERT10_E_OLESTREAM_BITMAP_TO_DIB 0x800401C3	There was an error in a Windows GDI call while converting the bitmap to a device-independent bitmap (DIB).
CONVERT10_E_STG_FMT 0x800401C4	Contents of the IStorage not in correct format.
CONVERT10_E_STG_NO_STD_STREAM 0x800401C5	Contents of IStorage is missing one of the standard streams.
CONVERT10_E_STG_DIB_TO_BITMAP 0x800401C6	There was an error in a Windows Graphics Device Interface (GDI) call while converting the DIB to a bitmap.
CLIPBRD_E_CANT_OPEN 0x800401D0	OpenClipboard failed.
CLIPBRD_E_CANT_EMPTY 0x800401D1	EmptyClipboard failed.
CLIPBRD_E_CANT_SET 0x800401D2	SetClipboard failed.
CLIPBRD_E_BAD_DATA 0x800401D3	Data on clipboard is invalid.
CLIPBRD_E_CANT_CLOSE 0x800401D4	CloseClipboard failed.
MK_E_CONNECTMANUALLY 0x800401E0	Moniker needs to be connected manually.
MK_E_EXCEEDEDDEADLINE 0x800401E1	Operation exceeded deadline.
MK_E_NEEDGENERIC 0x800401E2	Moniker needs to be generic.
MK_E_UNAVAILABLE 0x800401E3	Operation unavailable.
MK_E_SYNTAX 0x800401E4	Invalid syntax.
MK_E_NOOBJECT 0x800401E5	No object for moniker.

Value	Meaning
MK_E_INVALIDEXTENSION 0x800401E6	Bad extension for file.
MK_E_INTERMEDIATEINTERFACENOTSUPPORTED 0x800401E7	Intermediate operation failed.
MK_E_NOTBINDABLE 0x800401E8	Moniker is not bindable.
MK_E_NOTBOUND 0x800401E9	Moniker is not bound.
MK_E_CANTOPENFILE 0x800401EA	Moniker cannot open file.
MK_E_MUSTBOTHERUSER 0x800401EB	User input required for operation to succeed.
MK_E_NOINVERSE 0x800401EC	Moniker class has no inverse.
MK_E_NOSTORAGE 0x800401ED	Moniker does not refer to storage.
MK_E_NOPREFIX 0x800401EE	No common prefix.
MK_E_ENUMERATION_FAILED 0x800401EF	Moniker could not be enumerated.
CO_E_NOTINITIALIZED 0x800401F0	CoInitialize has not been called.
CO_E_ALREADYINITIALIZED 0x800401F1	CoInitialize has already been called.
CO_E_CANTDETERMINECLASS 0x800401F2	Class of object cannot be determined.
CO_E_CLASSSTRING 0x800401F3	Invalid class string.
CO_E_IIDSTRING 0x800401F4	Invalid interface string.
CO_E_APPNOTFOUND 0x800401F5	Application not found.
CO_E_APPSINGLEUSE 0x800401F6	Application cannot be run more than once.
CO_E_ERRORINAPP	Some error in application.

Value	Meaning
0x800401F7	
CO_E_DLLNOTFOUND 0x800401F8	DLL for class not found.
CO_E_ERRORINDLL 0x800401F9	Error in the DLL.
CO_E_WRONGOSFORAPP 0x800401FA	Wrong operating system or operating system version for application.
CO_E_OBJNOTREG 0x800401FB	Object is not registered.
CO_E_OBJISREG 0x800401FC	Object is already registered.
CO_E_OBJNOTCONNECTED 0x800401FD	Object is not connected to server.
CO_E_APPDIDNTREG 0x800401FE	Application was launched, but it did not register a class factory.
CO_E_RELEASED 0x800401FF	Object has been released.
EVENT_E_ALL_SUBSCRIBERS_FAILED 0x80040201	An event was unable to invoke any of the subscribers.
EVENT_E_QUERYSYNTAX 0x80040203	A syntax error occurred trying to evaluate a query string.
EVENT_E_QUERYFIELD 0x80040204	An invalid field name was used in a query string.
EVENT_E_INTERNALEXCEPTION 0x80040205	An unexpected exception was raised.
EVENT_E_INTERNALERROR 0x80040206	An unexpected internal error was detected.
EVENT_E_INVALID_PER_USER_SID 0x80040207	The owner security identifier (SID) on a per-user subscription does not exist.
EVENT_E_USER_EXCEPTION 0x80040208	A user-supplied component or subscriber raised an exception.
EVENT_E_TOO_MANY_METHODS 0x80040209	An interface has too many methods to fire events from.

Value	Meaning
EVENT_E_MISSING_EVENTCLASS 0x8004020A	A subscription cannot be stored unless its event class already exists.
EVENT_E_NOT_ALL_REMOVED 0x8004020B	Not all the objects requested could be removed.
EVENT_E_COMPLUS_NOT_INSTALLED 0x8004020C	COM+ is required for this operation, but it is not installed.
EVENT_E_CANT_MODIFY_OR_DELETE_UNCONFIGURED_OBJECT 0x8004020D	Cannot modify or delete an object that was not added using the COM+ Administrative SDK.
EVENT_E_CANT_MODIFY_OR_DELETE_CONFIGURED_OBJECT 0x8004020E	Cannot modify or delete an object that was added using the COM+ Administrative SDK.
EVENT_E_INVALID_EVENT_CLASS_PARTITION 0x8004020F	The event class for this subscription is in an invalid partition.
EVENT_E_PER_USER_SID_NOT_LOGGED_ON 0x80040210	The owner of the PerUser subscription is not logged on to the system specified.
SCHED_E_TRIGGER_NOT_FOUND 0x80041309	Trigger not found.
SCHED_E_TASK_NOT_READY 0x8004130A	One or more of the properties that are needed to run this task have not been set.
SCHED_E_TASK_NOT_RUNNING 0x8004130B	There is no running instance of the task.
SCHED_E_SERVICE_NOT_INSTALLED 0x8004130C	The Task Scheduler service is not installed on this computer.
SCHED_E_CANNOT_OPEN_TASK 0x8004130D	The task object could not be opened.
SCHED_E_INVALID_TASK 0x8004130E	The object is either an invalid task object or is not a task object.
SCHED_E_ACCOUNT_INFORMATION_NOT_SET 0x8004130F	No account information could be found in the Task Scheduler security database for the task indicated.
SCHED_E_ACCOUNT_NAME_NOT_FOUND 0x80041310	Unable to establish existence of the account specified.



Value	Meaning
SCHED_E_ACCOUNT_DBASE_CORRUPT 0x80041311	Corruption was detected in the Task Scheduler security database; the database has been reset.
SCHED_E_NO_SECURITY_SERVICES 0x80041312	Task Scheduler security services are available only on Windows NT.
SCHED_E_UNKNOWN_OBJECT_VERSION 0x80041313	The task object version is either unsupported or invalid.
SCHED_E_UNSUPPORTED_ACCOUNT_OPTION 0x80041314	The task has been configured with an unsupported combination of account settings and run-time options.
SCHED_E_SERVICE_NOT_RUNNING 0x80041315	The Task Scheduler service is not running.
SCHED_E_UNEXPECTEDNODE 0x80041316	The task XML contains an unexpected node.
SCHED_E_NAMESPACE 0x80041317	The task XML contains an element or attribute from an unexpected namespace.
SCHED_E_INVALIDVALUE 0x80041318	The task XML contains a value that is incorrectly formatted or out of range.
SCHED_E_MISSINGNODE 0x80041319	The task XML is missing a required element or attribute.
SCHED_E_MALFORMEDXML 0x8004131A	The task XML is malformed.
SCHED_E_TOO_MANY_NODES 0x8004131D	The task XML contains too many nodes of the same type.
SCHED_E_PAST_END_BOUNDARY 0x8004131E	The task cannot be started after the trigger's end boundary.
SCHED_E_ALREADY_RUNNING 0x8004131F	An instance of this task is already running.
SCHED_E_USER_NOT_LOGGED_ON 0x80041320	The task will not run because the user is not logged on.
SCHED_E_INVALID_TASK_HASH 0x80041321	The task image is corrupt or has been tampered with.
SCHED_E_SERVICE_NOT_AVAILABLE 0x80041322	The Task Scheduler service is not available.

Value	Meaning
SCHED_E_SERVICE_TOO_BUSY 0x80041323	The Task Scheduler service is too busy to handle your request. Try again later.
SCHED_E_TASK_ATTEMPTED 0x80041324	The Task Scheduler service attempted to run the task, but the task did not run due to one of the constraints in the task definition.
XACT_E_ALREADYOTHERSINGLEPHASE 0x8004D000	Another single phase resource manager has already been enlisted in this transaction.
XACT_E_CANTRETAIN 0x8004D001	A retaining commit or abort is not supported.
XACT_E_COMMITFAILED 0x8004D002	The transaction failed to commit for an unknown reason. The transaction was aborted.
XACT_E_COMMITPREVENTED 0x8004D003	Cannot call commit on this transaction object because the calling application did not initiate the transaction.
XACT_E_HEURISTICABORT 0x8004D004	Instead of committing, the resource heuristically aborted.
XACT_E_HEURISTICCOMMIT 0x8004D005	Instead of aborting, the resource heuristically committed.
XACT_E_HEURISTICDAMAGE 0x8004D006	Some of the states of the resource were committed while others were aborted, likely because of heuristic decisions.
XACT_E_HEURISTICDANGER 0x8004D007	Some of the states of the resource may have been committed while others may have been aborted, likely because of heuristic decisions.
XACT_E_ISOLATIONLEVEL 0x8004D008	The requested isolation level is not valid or supported.
XACT_E_NOASYNC 0x8004D009	The transaction manager does not support an asynchronous operation for this method.
XACT_E_NOENLIST 0x8004D00A	Unable to enlist in the transaction.

Value	Meaning
XACT_E_NOISORETAIN 0x8004D00B	The requested semantics of retention of isolation across retaining commit and abort boundaries cannot be supported by this transaction implementation, or <b>isoFlags</b> was not equal to 0.
XACT_E_NORESOURCE 0x8004D00C	There is no resource presently associated with this enlistment.
XACT_E_NOTCURRENT 0x8004D00D	The transaction failed to commit due to the failure of optimistic concurrency control in at least one of the resource managers.
XACT_E_NOTTRANSACTION 0x8004D00E	The transaction has already been implicitly or explicitly committed or aborted.
XACT_E_NOTSUPPORTED 0x8004D00F	An invalid combination of flags was specified.
XACT_E_UNKNOWNRMGRID 0x8004D010	The resource manager ID is not associated with this transaction or the transaction manager.
XACT_E_WRONGSTATE 0x8004D011	This method was called in the wrong state.
XACT_E_WRONGUOW 0x8004D012	The indicated unit of work does not match the unit of work expected by the resource manager.
XACT_E_XTIONEXISTS 0x8004D013	An enlistment in a transaction already exists.
XACT_E_NOIMPORTOBJECT 0x8004D014	An import object for the transaction could not be found.
XACT_E_INVALIDCOOKIE 0x8004D015	The transaction cookie is invalid.
XACT_E_INDOUBT 0x8004D016	The transaction status is in doubt. A communication failure occurred, or a transaction manager or resource manager has failed.
XACT_E_NOTIMEOUT 0x8004D017	A time-out was specified, but time-outs are not supported.

Value	Meaning
XACT_E_ALREADYINPROGRESS 0x8004D018	The requested operation is already in progress for the transaction.
XACT_E_ABORTED 0x8004D019	The transaction has already been aborted.
XACT_E_LOGFULL 0x8004D01A	The Transaction Manager returned a log full error.
XACT_E_TMNOTAVAILABLE 0x8004D01B	The transaction manager is not available.
XACT_E_CONNECTION_DOWN 0x8004D01C	A connection with the transaction manager was lost.
XACT_E_CONNECTION_DENIED 0x8004D01D	A request to establish a connection with the transaction manager was denied.
XACT_E_REENLISTTIMEOUT 0x8004D01E	Resource manager reenlistment to determine transaction status timed out.
XACT_E_TIP_CONNECT_FAILED 0x8004D01F	The transaction manager failed to establish a connection with another Transaction Internet Protocol (TIP) transaction manager.
XACT_E_TIP_PROTOCOL_ERROR 0x8004D020	The transaction manager encountered a protocol error with another TIP transaction manager.
XACT_E_TIP_PULL_FAILED 0x8004D021	The transaction manager could not propagate a transaction from another TIP transaction manager.
XACT_E_DEST_TMNOTAVAILABLE 0x8004D022	The transaction manager on the destination machine is not available.
XACT_E_TIP_DISABLED 0x8004D023	The transaction manager has disabled its support for TIP.
XACT_E_NETWORK_TX_DISABLED 0x8004D024	The transaction manager has disabled its support for remote or network transactions.
XACT_E_PARTNER_NETWORK_TX_DISABLED 0x8004D025	The partner transaction manager has disabled its support for remote or network transactions.

Value	Meaning
XACT_E_XA_TX_DISABLED 0x8004D026	The transaction manager has disabled its support for XA transactions.
XACT_E_UNABLE_TO_READ_DTC_CONFIG 0x8004D027	Microsoft Distributed Transaction Coordinator (MSDTC) was unable to read its configuration information.
XACT_E_UNABLE_TO_LOAD_DTC_PROXY 0x8004D028	MSDTC was unable to load the DTC proxy DLL.
XACT_E_ABORTING 0x8004D029	The local transaction has aborted.
XACT_E_CLERKNOTFOUND 0x8004D080	XACT_E_CLERKNOTFOUND
XACT_E_CLERKEXISTS 0x8004D081	XACT_E_CLERKEXISTS
XACT_E_RECOVERYINPROGRESS 0x8004D082	XACT_E_RECOVERYINPROGRESS
XACT_E_TRANSACTIONCLOSED 0x8004D083	XACT_E_TRANSACTIONCLOSED
XACT_E_INVALIDLSN 0x8004D084	XACT_E_INVALIDLSN
XACT_E_REPLAYREQUEST 0x8004D085	XACT_E_REPLAYREQUEST
XACT_E_CONNECTION_REQUEST_DENIED 0x8004D100	The request to connect to the specified transaction coordinator was denied.
XACT_E_TOOMANY_ENLISTMENTS 0x8004D101	The maximum number of enlistments for the specified transaction has been reached.
XACT_E_DUPLICATE_GUID 0x8004D102	A resource manager with the same identifier is already registered with the specified transaction coordinator.
XACT_E_NOTSINGLEPHASE 0x8004D103	The prepare request given was not eligible for single-phase optimizations.
XACT_E_RECOVERYALREADYDONE 0x8004D104	RecoveryComplete has already been called for the given resource manager.
XACT_E_PROTOCOL	The interface call made was incorrect for the current state

Value	Meaning
0x8004D105	of the protocol.
XACT_E_RM_FAILURE 0x8004D106	The xa_open call failed for the XA resource.
XACT_E_RECOVERY_FAILED 0x8004D107	The xa_recover call failed for the XA resource.
XACT_E_LU_NOT_FOUND 0x8004D108	The logical unit of work specified cannot be found.
XACT_E_DUPLICATE_LU 0x8004D109	The specified logical unit of work already exists.
XACT_E_LU_NOT_CONNECTED 0x8004D10A	Subordinate creation failed. The specified logical unit of work was not connected.
XACT_E_DUPLICATE_TRANSID 0x8004D10B	A transaction with the given identifier already exists.
XACT_E_LU_BUSY 0x8004D10C	The resource is in use.
XACT_E_LU_NO_RECOVERY_PROCESS 0x8004D10D	The LU Recovery process is down.
XACT_E_LU_DOWN 0x8004D10E	The remote session was lost.
XACT_E_LU_RECOVERING 0x8004D10F	The resource is currently recovering.
XACT_E_LU_RECOVERY_MISMATCH 0x8004D110	There was a mismatch in driving recovery.
XACT_E_RM_UNAVAILABLE 0x8004D111	An error occurred with the XA resource.
CONTEXT_E_ABORTED 0x8004E002	The root transaction wanted to commit, but the transaction aborted.
CONTEXT_E_ABORTING 0x8004E003	The COM+ component on which the method call was made has a transaction that has already aborted or is in the process of aborting.
CONTEXT_E_NOCONTEXT 0x8004E004	There is no Microsoft Transaction Server (MTS) object context.
CONTEXT_E_WOULD_DEADLOCK	The component is configured to use synchronization, and

Value	Meaning
0x8004E005	this method call would cause a deadlock to occur.
CONTEXT_E_SYNCH_TIMEOUT 0x8004E006	The component is configured to use synchronization, and a thread has timed out waiting to enter the context.
CONTEXT_E_OLDREF 0x8004E007	You made a method call on a COM+ component that has a transaction that has already committed or aborted.
CONTEXT_E_ROLENOTFOUND 0x8004E00C	The specified role was not configured for the application.
CONTEXT_E_TMNOTAVAILABLE 0x8004E00F	COM+ was unable to talk to the MSDTC.
CO_E_ACTIVATIONFAILED 0x8004E021	An unexpected error occurred during COM+ activation.
CO_E_ACTIVATIONFAILED_EVENTLOGGED 0x8004E022	COM+ activation failed. Check the event log for more information.
CO_E_ACTIVATIONFAILED_CATALOGERROR 0x8004E023	COM+ activation failed due to a catalog or configuration error.
CO_E_ACTIVATIONFAILED_TIMEOUT 0x8004E024	COM+ activation failed because the activation could not be completed in the specified amount of time.
CO_E_INITIALIZATIONFAILED 0x8004E025	COM+ activation failed because an initialization function failed. Check the event log for more information.
CONTEXT_E_NOJIT 0x8004E026	The requested operation requires that just-in-time (JIT) be in the current context, and it is not.
CONTEXT_E_NOTTRANSACTION 0x8004E027	The requested operation requires that the current context have a transaction, and it does not.
CO_E_THREADINGMODEL_CHANGED 0x8004E028	The components threading model has changed after install into a COM+ application. Re-install component.

Value	Meaning
CO_E_NOIISINTRINSICS 0x8004E029	Internet Information Services (IIS) intrinsics not available. Start your work with IIS.
CO_E_NOCOOKIES 0x8004E02A	An attempt to write a cookie failed.
CO_E_DBERROR 0x8004E02B	An attempt to use a database generated a database-specific error.
CO_E_NOTPOOLED 0x8004E02C	The COM+ component you created must use object pooling to work.
CO_E_NOTCONSTRUCTED 0x8004E02D	The COM+ component you created must use object construction to work correctly.
CO_E_NOSYNCHRONIZATION 0x8004E02E	The COM+ component requires synchronization, and it is not configured for it.
CO_E_ISOLEVELMISMATCH 0x8004E02F	The TxIsolation Level property for the COM+ component being created is stronger than the TxIsolationLevel for the root.
CO_E_CALL_OUT_OF_TX_SCOPE_NOT_ALLOWED 0x8004E030	The component attempted to make a cross-context call between invocations of EnterTransactionScope and ExitTransactionScope. This is not allowed. Cross-context calls cannot be made while inside a transaction scope.
CO_E_EXIT_TRANSACTION_SCOPE_NOT_CALLED 0x8004E031	The component made a call to EnterTransactionScope, but did not make a corresponding call to ExitTransactionScope before returning.
E_INVALIDARG 0x80070057	One or more arguments are invalid.
CO_E_CLASS_CREATE_FAILED 0x80080001	Attempt to create a class object failed.
CO_E_SCM_ERROR 0x80080002	OLE service could not bind object.
CO_E_SCM_RPC_FAILURE 0x80080003	RPC communication failed with OLE service.



Value	Meaning
CO_E_BAD_PATH 0x80080004	Bad path to object.
CO_E_SERVER_EXEC_FAILURE 0x80080005	Server execution failed.
CO_E_OBJSRV_RPC_FAILURE 0x80080006	OLE service could not communicate with the object server.
MK_E_NO_NORMALIZED 0x80080007	Moniker path could not be normalized.
CO_E_SERVER_STOPPING 0x80080008	Object server is stopping when OLE service contacts it.
MEM_E_INVALID_ROOT 0x80080009	An invalid root block pointer was specified.
MEM_E_INVALID_LINK 0x80080010	An allocation chain contained an invalid link pointer.
MEM_E_INVALID_SIZE 0x80080011	The requested allocation size was too large.
CO_E_MISSING_DISPLAYNAME 0x80080015	The activation requires a display name to be present under the class identifier (CLSID) key.
CO_E_RUNAS_VALUE_MUST_BE_AAA 0x80080016	The activation requires that the RunAs value for the application is Activate As Activator.
CO_E_ELEVATION_DISABLED 0x80080017	The class is not configured to support elevated activation.
NTE_BAD_UID 0x80090001	Bad UID.
NTE_BAD_HASH 0x80090002	Bad hash.
NTE_BAD_KEY 0x80090003	Bad key.
NTE_BAD_LEN 0x80090004	Bad length.
NTE_BAD_DATA 0x80090005	Bad data.
NTE_BAD_SIGNATURE	Invalid signature.

Value	Meaning
0x80090006	
NTE_BAD_VER 0x80090007	Bad version of provider.
NTE_BAD_ALGID 0x80090008	Invalid algorithm specified.
NTE_BAD_FLAGS 0x80090009	Invalid flags specified.
NTE_BAD_TYPE 0x8009000A	Invalid type specified.
NTE_BAD_KEY_STATE 0x8009000B	Key not valid for use in specified state.
NTE_BAD_HASH_STATE 0x8009000C	Hash not valid for use in specified state.
NTE_NO_KEY 0x8009000D	Key does not exist.
NTE_NO_MEMORY 0x8009000E	Insufficient memory available for the operation.
NTE_EXISTS 0x8009000F	Object already exists.
NTE_PERM 0x80090010	Access denied.
NTE_NOT_FOUND 0x80090011	Object was not found.
NTE_DOUBLE_ENCRYPT 0x80090012	Data already encrypted.
NTE_BAD_PROVIDER 0x80090013	Invalid provider specified.
NTE_BAD_PROV_TYPE 0x80090014	Invalid provider type specified.
NTE_BAD_PUBLIC_KEY 0x80090015	Provider's public key is invalid.
NTE_BAD_KEYSET 0x80090016	Key set does not exist.
NTE_PROV_TYPE_NOT_DEF 0x80090017	Provider type not defined.

Value	Meaning
NTE_PROV_TYPE_ENTRY_BAD 0x80090018	The provider type, as registered, is invalid.
NTE_KEYSET_NOT_DEF 0x80090019	The key set is not defined.
NTE_KEYSET_ENTRY_BAD 0x8009001A	The key set, as registered, is invalid.
NTE_PROV_TYPE_NO_MATCH 0x8009001B	Provider type does not match registered value.
NTE_SIGNATURE_FILE_BAD 0x8009001C	The digital signature file is corrupt.
NTE_PROVIDER_DLL_FAIL 0x8009001D	Provider DLL failed to initialize correctly.
NTE_PROV_DLL_NOT_FOUND 0x8009001E	Provider DLL could not be found.
NTE_BAD_KEYSET_PARAM 0x8009001F	The <i>keyset</i> parameter is invalid.
NTE_FAIL 0x80090020	An internal error occurred.
NTE_SYS_ERR 0x80090021	A base error occurred.
NTE_SILENT_CONTEXT 0x80090022	Provider could not perform the action because the context was acquired as silent.
NTE_TOKEN_KEYSET_STORAGE_FULL 0x80090023	The security token does not have storage space available for an additional container.
NTE_TEMPORARY_PROFILE 0x80090024	The profile for the user is a temporary profile.
NTE_FIXEDPARAMETER 0x80090025	The key parameters could not be set because the configuration service provider (CSP) uses fixed parameters.
NTE_INVALID_HANDLE 0x80090026	The supplied handle is invalid.
NTE_INVALID_PARAMETER 0x80090027	The parameter is incorrect.
NTE_BUFFER_TOO_SMALL	The buffer supplied to a function was too small.

Value	Meaning
0x80090028	
NTE_NOT_SUPPORTED 0x80090029	The requested operation is not supported.
NTE_NO_MORE_ITEMS 0x8009002A	No more data is available.
NTE_BUFFERS_OVERLAP 0x8009002B	The supplied buffers overlap incorrectly.
NTE_DECRYPTION_FAILURE 0x8009002C	The specified data could not be decrypted.
NTE_INTERNAL_ERROR 0x8009002D	An internal consistency check failed.
NTE_UI_REQUIRED 0x8009002E	This operation requires input from the user.
NTE_HMAC_NOT_SUPPORTED 0x8009002F	The cryptographic provider does not support Hash Message Authentication Code (HMAC).
SEC_E_INSUFFICIENT_MEMORY 0x80090300	Not enough memory is available to complete this request.
SEC_E_INVALID_HANDLE 0x80090301	The handle specified is invalid.
SEC_E_UNSUPPORTED_FUNCTION 0x80090302	The function requested is not supported.
SEC_E_TARGET_UNKNOWN 0x80090303	The specified target is unknown or unreachable.
SEC_E_INTERNAL_ERROR 0x80090304	The Local Security Authority (LSA) cannot be contacted.
SEC_E_SECPKG_NOT_FOUND 0x80090305	The requested security package does not exist.
SEC_E_NOT_OWNER 0x80090306	The caller is not the owner of the desired credentials.
SEC_E_CANNOT_INSTALL 0x80090307	The security package failed to initialize and cannot be installed.
SEC_E_INVALID_TOKEN 0x80090308	The token supplied to the function is invalid.

Value	Meaning
SEC_E_CANNOT_PACK 0x80090309	The security package is not able to marshal the logon buffer, so the logon attempt has failed.
SEC_E_QOP_NOT_SUPPORTED 0x8009030A	The per-message quality of protection is not supported by the security package.
SEC_E_NO_IMPERSONATION 0x8009030B	The security context does not allow impersonation of the client.
SEC_E_LOGON_DENIED 0x8009030C	The logon attempt failed.
SEC_E_UNKNOWN_CREDENTIALS 0x8009030D	The credentials supplied to the package were not recognized.
SEC_E_NO_CREDENTIALS 0x8009030E	No credentials are available in the security package.
SEC_E_MESSAGE_ALTERED 0x8009030F	The message or signature supplied for verification has been altered.
SEC_E_OUT_OF_SEQUENCE 0x80090310	The message supplied for verification is out of sequence.
SEC_E_NO_AUTHENTICATING_AUTHORITY 0x80090311	No authority could be contacted for authentication.
SEC_E_BAD_PKGID 0x80090316	The requested security package does not exist.
SEC_E_CONTEXT_EXPIRED 0x80090317	The context has expired and can no longer be used.
SEC_E_INCOMPLETE_MESSAGE 0x80090318	The supplied message is incomplete. The signature was not verified.
SEC_E_INCOMPLETE_CREDENTIALS 0x80090320	The credentials supplied were not complete and could not be verified. The context could not be initialized.
SEC_E_BUFFER_TOO_SMALL 0x80090321	The buffers supplied to a function was too small.
SEC_E_WRONG_PRINCIPAL 0x80090322	The target principal name is incorrect.
SEC_E_TIME_SKEW 0x80090324	The clocks on the client and server machines are skewed.

Value	Meaning
SEC_E_UNTRUSTED_ROOT 0x80090325	The certificate chain was issued by an authority that is not trusted.
SEC_E_ILLEGAL_MESSAGE 0x80090326	The message received was unexpected or badly formatted.
SEC_E_CERT_UNKNOWN 0x80090327	An unknown error occurred while processing the certificate.
SEC_E_CERT_EXPIRED 0x80090328	The received certificate has expired.
SEC_E_ENCRYPT_FAILURE 0x80090329	The specified data could not be encrypted.
SEC_E_DECRYPT_FAILURE 0x80090330	The specified data could not be decrypted.
SEC_E_ALGORITHM_MISMATCH 0x80090331	The client and server cannot communicate because they do not possess a common algorithm.
SEC_E_SECURITY_QOS_FAILED 0x80090332	The security context could not be established due to a failure in the requested quality of service (for example, mutual authentication or delegation).
SEC_E_UNFINISHED_CONTEXT_DELETED 0x80090333	A security context was deleted before the context was completed. This is considered a logon failure.
SEC_E_NO_TGT_REPLY 0x80090334	The client is trying to negotiate a context and the server requires user-to-user but did not send a ticket granting ticket (TGT) reply.
SEC_E_NO_IP_ADDRESSES 0x80090335	Unable to accomplish the requested task because the local machine does not have an IP addresses.
SEC_E_WRONG_CREDENTIAL_HANDLE 0x80090336	The supplied credential handle does not match the credential associated with the security context.
SEC_E_CRYPTO_SYSTEM_INVALID 0x80090337	The cryptographic system or checksum function is invalid because a required function is unavailable.

Value	Meaning
SEC_E_MAX_REFERRALS_EXCEEDED 0x80090338	The number of maximum ticket referrals has been exceeded.
SEC_E_MUST_BE_KDC 0x80090339	The local machine must be a Kerberos domain controller (KDC), and it is not.
SEC_E_STRONG_CRYPTO_NOT_SUPPORTED 0x8009033A	The other end of the security negotiation requires strong cryptographics, but it is not supported on the local machine.
SEC_E_TOO_MANY_PRINCIPALS 0x8009033B	The KDC reply contained more than one principal name.
SEC_E_NO_PA_DATA 0x8009033C	Expected to find PA data for a hint of what etype to use, but it was not found.
SEC_E_PKINIT_NAME_MISMATCH 0x8009033D	The client certificate does not contain a valid user principal name (UPN), or does not match the client name in the logon request. Contact your administrator.
SEC_E_SMARTCARD_LOGON_REQUIRED 0x8009033E	Smart card logon is required and was not used.
SEC_E_SHUTDOWN_IN_PROGRESS 0x8009033F	A system shutdown is in progress.
SEC_E_KDC_INVALID_REQUEST 0x80090340	An invalid request was sent to the KDC.
SEC_E_KDC_UNABLE_TO_REFER 0x80090341	The KDC was unable to generate a referral for the service requested.
SEC_E_KDC_UNKNOWN_ETYPE 0x80090342	The encryption type requested is not supported by the KDC.
SEC_E_UNSUPPORTED_PREAUTH 0x80090343	An unsupported pre-authentication mechanism was presented to the Kerberos package.
SEC_E_DELEGATION_REQUIRED 0x80090345	The requested operation cannot be completed. The computer must be trusted for delegation, and the current user account must be configured to allow delegation.

Value	Meaning
SEC_E_BAD_BINDINGS 0x80090346	Client's supplied Security Support Provider Interface (SSPI) channel bindings were incorrect.
SEC_E_MULTIPLE_ACCOUNTS 0x80090347	The received certificate was mapped to multiple accounts.
SEC_E_NO_KERB_KEY 0x80090348	SEC_E_NO_KERB_KEY
SEC_E_CERT_WRONG_USAGE 0x80090349	The certificate is not valid for the requested usage.
SEC_E_DOWNGRADE_DETECTED 0x80090350	The system detected a possible attempt to compromise security. Ensure that you can contact the server that authenticated you.
SEC_E_SMARTCARD_CERT_REVOKED 0x80090351	The smart card certificate used for authentication has been revoked. Contact your system administrator. The event log may contain additional information.
SEC_E_ISSUING_CA_UNTRUSTED 0x80090352	An untrusted certification authority (CA) was detected while processing the smart card certificate used for authentication. Contact your system administrator.
SEC_E_REVOCATION_OFFLINE_C 0x80090353	The revocation status of the smart card certificate used for authentication could not be determined. Contact your system administrator.
SEC_E_PKINIT_CLIENT_FAILURE 0x80090354	The smart card certificate used for authentication was not trusted. Contact your system administrator.
SEC_E_SMARTCARD_CERT_EXPIRED 0x80090355	The smart card certificate used for authentication has expired. Contact your system administrator.
SEC_E_NO_S4U_PROT_SUPPORT 0x80090356	The Kerberos subsystem encountered an error. A service for user protocol requests was made against a domain controller that does not support services for users.



Value	Meaning
SEC_E_CROSSREALM_DELEGATION_FAILURE 0x80090357	An attempt was made by this server to make a Kerberos-constrained delegation request for a target outside the server's realm. This is not supported and indicates a misconfiguration on this server's allowed-to-delegate-to list. Contact your administrator.
SEC_E_REVOCATION_OFFLINE_KDC 0x80090358	The revocation status of the domain controller certificate used for smart card authentication could not be determined. The system event log contains additional information. Contact your system administrator.
SEC_E_ISSUING_CA_UNTRUSTED_KDC 0x80090359	An untrusted CA was detected while processing the domain controller certificate used for authentication. The system event log contains additional information. Contact your system administrator.
SEC_E_KDC_CERT_EXPIRED 0x8009035A	The domain controller certificate used for smart card logon has expired. Contact your system administrator with the contents of your system event log.
SEC_E_KDC_CERT_REVOKED 0x8009035B	The domain controller certificate used for smart card logon has been revoked. Contact your system administrator with the contents of your system event log.
SEC_E_INVALID_PARAMETER 0x8009035D	One or more of the parameters passed to the function were invalid.
SEC_E_DELEGATION_POLICY 0x8009035E	The client policy does not allow credential delegation to the target server.
SEC_E_POLICY_NLTM_ONLY 0x8009035F	The client policy does not allow credential delegation to the target server with NLTM only authentication.
CRYPT_E_MSG_ERROR	An error occurred while performing an operation on a

Value	Meaning
0x80091001	cryptographic message.
CRYPT_E_UNKNOWN_ALGO 0x80091002	Unknown cryptographic algorithm.
CRYPT_E_OID_FORMAT 0x80091003	The object identifier is poorly formatted.
CRYPT_E_INVALID_MSG_TYPE 0x80091004	Invalid cryptographic message type.
CRYPT_E_UNEXPECTED_ENCODING 0x80091005	Unexpected cryptographic message encoding.
CRYPT_E_AUTH_ATTR_MISSING 0x80091006	The cryptographic message does not contain an expected authenticated attribute.
CRYPT_E_HASH_VALUE 0x80091007	The hash value is not correct.
CRYPT_E_INVALID_INDEX 0x80091008	The index value is not valid.
CRYPT_E_ALREADY_DECRYPTED 0x80091009	The content of the cryptographic message has already been decrypted.
CRYPT_E_NOT_DECRYPTED 0x8009100A	The content of the cryptographic message has not been decrypted yet.
CRYPT_E_RECIPIENT_NOT_FOUND 0x8009100B	The enveloped-data message does not contain the specified recipient.
CRYPT_E_CONTROL_TYPE 0x8009100C	Invalid control type.
CRYPT_E_ISSUER_SERIALNUMBER 0x8009100D	Invalid issuer or serial number.
CRYPT_E_SIGNER_NOT_FOUND 0x8009100E	Cannot find the original signer.
CRYPT_E_ATTRIBUTES_MISSING 0x8009100F	The cryptographic message does not contain all of the requested attributes.
CRYPT_E_STREAM_MSG_NOT_READY 0x80091010	The streamed cryptographic message is not ready to return data.
CRYPT_E_STREAM_INSUFFICIENT_DATA 0x80091011	The streamed cryptographic message requires more data to complete the decode

Value	Meaning
	operation.
CRYPT_E_BAD_LEN 0x80092001	The length specified for the output data was insufficient.
CRYPT_E_BAD_ENCODE 0x80092002	An error occurred during the encode or decode operation.
CRYPT_E_FILE_ERROR 0x80092003	An error occurred while reading or writing to a file.
CRYPT_E_NOT_FOUND 0x80092004	Cannot find object or property.
CRYPT_E_EXISTS 0x80092005	The object or property already exists.
CRYPT_E_NO_PROVIDER 0x80092006	No provider was specified for the store or object.
CRYPT_E_SELF_SIGNED 0x80092007	The specified certificate is self-signed.
CRYPT_E_DELETED_PREV 0x80092008	The previous certificate or certificate revocation list (CRL) context was deleted.
CRYPT_E_NO_MATCH 0x80092009	Cannot find the requested object.
CRYPT_E_UNEXPECTED_MSG_TYPE 0x8009200A	The certificate does not have a property that references a private key.
CRYPT_E_NO_KEY_PROPERTY 0x8009200B	Cannot find the certificate and private key for decryption.
CRYPT_E_NO_DECRYPT_CERT 0x8009200C	Cannot find the certificate and private key to use for decryption.
CRYPT_E_BAD_MSG 0x8009200D	Not a cryptographic message or the cryptographic message is not formatted correctly.
CRYPT_E_NO_SIGNER 0x8009200E	The signed cryptographic message does not have a signer for the specified signer index.
CRYPT_E_PENDING_CLOSE 0x8009200F	Final closure is pending until additional frees or closes.
CRYPT_E_REVOKED 0x80092010	The certificate is revoked.

Value	Meaning
CRYPT_E_NO_REVOCATION_DLL 0x80092011	No DLL or exported function was found to verify revocation.
CRYPT_E_NO_REVOCATION_CHECK 0x80092012	The revocation function was unable to check revocation for the certificate.
CRYPT_E_REVOCATION_OFFLINE 0x80092013	The revocation function was unable to check revocation because the revocation server was offline.
CRYPT_E_NOT_IN_REVOCATION_DATABASE 0x80092014	The certificate is not in the revocation server's database.
CRYPT_E_INVALID_NUMERIC_STRING 0x80092020	The string contains a non-numeric character.
CRYPT_E_INVALID_PRINTABLE_STRING 0x80092021	The string contains a nonprintable character.
CRYPT_E_INVALID_IA5_STRING 0x80092022	The string contains a character not in the 7-bit ASCII character set.
CRYPT_E_INVALID_X500_STRING 0x80092023	The string contains an invalid X500 name attribute key, object identifier (OID), value, or delimiter.
CRYPT_E_NOT_CHAR_STRING 0x80092024	The dwValueType for the CERT_NAME_VALUE is not one of the character strings. Most likely it is either a CERT_RDN_ENCODED_BLOB or CERT_TDN_OCTED_STRING.
CRYPT_E_FILERESIZED 0x80092025	The Put operation cannot continue. The file needs to be resized. However, there is already a signature present. A complete signing operation must be done.
CRYPT_E_SECURITY_SETTINGS 0x80092026	The cryptographic operation failed due to a local security option setting.
CRYPT_E_NO_VERIFY_USAGE_DLL 0x80092027	No DLL or exported function was found to verify subject usage.
CRYPT_E_NO_VERIFY_USAGE_CHECK 0x80092028	The called function was unable to perform a usage check on the subject.

Value	Meaning
CRYPT_E_VERIFY_USAGE_OFFLINE 0x80092029	The called function was unable to complete the usage check because the server was offline.
CRYPT_E_NOT_IN_CTL 0x8009202A	The subject was not found in a certificate trust list (CTL).
CRYPT_E_NO_TRUSTED_SIGNER 0x8009202B	None of the signers of the cryptographic message or certificate trust list is trusted.
CRYPT_E_MISSING_PUBKEY_PARA 0x8009202C	The public key's algorithm parameters are missing.
CRYPT_E_OSS_ERROR 0x80093000	OSS Certificate encode/decode error code base.
OSS_MORE_BUF 0x80093001	OSS ASN.1 Error: Output Buffer is too small.
OSS_NEGATIVE_INTEGER 0x80093002	OSS ASN.1 Error: Signed integer is encoded as a unsigned integer.
OSS_PDU_RANGE 0x80093003	OSS ASN.1 Error: Unknown ASN.1 data type.
OSS_MORE_INPUT 0x80093004	OSS ASN.1 Error: Output buffer is too small; the decoded data has been truncated.
OSS_DATA_ERROR 0x80093005	OSS ASN.1 Error: Invalid data.
OSS_BAD_ARG 0x80093006	OSS ASN.1 Error: Invalid argument.
OSS_BAD_VERSION 0x80093007	OSS ASN.1 Error: Encode/Decode version mismatch.
OSS_OUT_MEMORY 0x80093008	OSS ASN.1 Error: Out of memory.
OSS_PDU_MISMATCH 0x80093009	OSS ASN.1 Error: Encode/Decode error.
OSS_LIMITED 0x8009300A	OSS ASN.1 Error: Internal error.
OSS_BAD_PTR 0x8009300B	OSS ASN.1 Error: Invalid data.

Value	Meaning
OSS_BAD_TIME 0x8009300C	OSS ASN.1 Error: Invalid data.
OSS_INDEFINITE_NOT_SUPPORTED 0x8009300D	OSS ASN.1 Error: Unsupported BER indefinite-length encoding.
OSS_MEM_ERROR 0x8009300E	OSS ASN.1 Error: Access violation.
OSS_BAD_TABLE 0x8009300F	OSS ASN.1 Error: Invalid data.
OSS_TOO_LONG 0x80093010	OSS ASN.1 Error: Invalid data.
OSS_CONSTRAINT_VIOLATED 0x80093011	OSS ASN.1 Error: Invalid data.
OSS_FATAL_ERROR 0x80093012	OSS ASN.1 Error: Internal error.
OSS_ACCESS_SERIALIZATION_ERROR 0x80093013	OSS ASN.1 Error: Multithreading conflict.
OSS_NULL_TBL 0x80093014	OSS ASN.1 Error: Invalid data.
OSS_NULL_FCN 0x80093015	OSS ASN.1 Error: Invalid data.
OSS_BAD_ENCRULES 0x80093016	OSS ASN.1 Error: Invalid data.
OSS_UNAVAIL_ENCRULES 0x80093017	OSS ASN.1 Error: Encode/Decode function not implemented.
OSS_CANT_OPEN_TRACE_WINDOW 0x80093018	OSS ASN.1 Error: Trace file error.
OSS_UNIMPLEMENTED 0x80093019	OSS ASN.1 Error: Function not implemented.
OSS_OID_DLL_NOT_LINKED 0x8009301A	OSS ASN.1 Error: Program link error.
OSS_CANT_OPEN_TRACE_FILE 0x8009301B	OSS ASN.1 Error: Trace file error.
OSS_TRACE_FILE_ALREADY_OPEN 0x8009301C	OSS ASN.1 Error: Trace file error.

Value	Meaning
OSS_TABLE_MISMATCH 0x8009301D	OSS ASN.1 Error: Invalid data.
OSS_TYPE_NOT_SUPPORTED 0x8009301E	OSS ASN.1 Error: Invalid data.
OSS_REAL_DLL_NOT_LINKED 0x8009301F	OSS ASN.1 Error: Program link error.
OSS_REAL_CODE_NOT_LINKED 0x80093020	OSS ASN.1 Error: Program link error.
OSS_OUT_OF_RANGE 0x80093021	OSS ASN.1 Error: Program link error.
OSS_COPIER_DLL_NOT_LINKED 0x80093022	OSS ASN.1 Error: Program link error.
OSS_CONSTRAINT_DLL_NOT_LINKED 0x80093023	OSS ASN.1 Error: Program link error.
OSS_COMPARATOR_DLL_NOT_LINKED 0x80093024	OSS ASN.1 Error: Program link error.
OSS_COMPARATOR_CODE_NOT_LINKED 0x80093025	OSS ASN.1 Error: Program link error.
OSS_MEM_MGR_DLL_NOT_LINKED 0x80093026	OSS ASN.1 Error: Program link error.
OSS_PDV_DLL_NOT_LINKED 0x80093027	OSS ASN.1 Error: Program link error.
OSS_PDV_CODE_NOT_LINKED 0x80093028	OSS ASN.1 Error: Program link error.
OSS_API_DLL_NOT_LINKED 0x80093029	OSS ASN.1 Error: Program link error.
OSS_BERDER_DLL_NOT_LINKED 0x8009302A	OSS ASN.1 Error: Program link error.
OSS_PER_DLL_NOT_LINKED 0x8009302B	OSS ASN.1 Error: Program link error.
OSS_OPEN_TYPE_ERROR 0x8009302C	OSS ASN.1 Error: Program link error.
OSS_MUTEX_NOT_CREATED 0x8009302D	OSS ASN.1 Error: System resource error.
OSS_CANT_CLOSE_TRACE_FILE	OSS ASN.1 Error: Trace file error.

Value	Meaning
0x8009302E	
CRYPT_E_ASN1_ERROR 0x80093100	ASN1 Certificate encode/decode error code base.
CRYPT_E_ASN1_INTERNAL 0x80093101	ASN1 internal encode or decode error.
CRYPT_E_ASN1_EOD 0x80093102	ASN1 unexpected end of data.
CRYPT_E_ASN1_CORRUPT 0x80093103	ASN1 corrupted data.
CRYPT_E_ASN1_LARGE 0x80093104	ASN1 value too large.
CRYPT_E_ASN1_CONSTRAINT 0x80093105	ASN1 constraint violated.
CRYPT_E_ASN1_MEMORY 0x80093106	ASN1 out of memory.
CRYPT_E_ASN1_OVERFLOW 0x80093107	ASN1 buffer overflow.
CRYPT_E_ASN1_BADPDU 0x80093108	ASN1 function not supported for this protocol data unit (PDU).
CRYPT_E_ASN1_BADARGS 0x80093109	ASN1 bad arguments to function call.
CRYPT_E_ASN1_BADREAL 0x8009310A	ASN1 bad real value.
CRYPT_E_ASN1_BADTAG 0x8009310B	ASN1 bad tag value met.
CRYPT_E_ASN1_CHOICE 0x8009310C	ASN1 bad choice value.
CRYPT_E_ASN1_RULE 0x8009310D	ASN1 bad encoding rule.
CRYPT_E_ASN1_UTF8 0x8009310E	ASN1 bad Unicode (UTF8).
CRYPT_E_ASN1_PDU_TYPE 0x80093133	ASN1 bad PDU type.
CRYPT_E_ASN1_NYI 0x80093134	ASN1 not yet implemented.



Value	Meaning
CRYPT_E_ASN1_EXTENDED 0x80093201	ASN1 skipped unknown extensions.
CRYPT_E_ASN1_NOEOD 0x80093202	ASN1 end of data expected.
CERTSRV_E_BAD_REQUESTSUBJECT 0x80094001	The request subject name is invalid or too long.
CERTSRV_E_NO_REQUEST 0x80094002	The request does not exist.
CERTSRV_E_BAD_REQUESTSTATUS 0x80094003	The request's current status does not allow this operation.
CERTSRV_E_PROPERTY_EMPTY 0x80094004	The requested property value is empty.
CERTSRV_E_INVALID_CA_CERTIFICATE 0x80094005	The CA's certificate contains invalid data.
CERTSRV_E_SERVER_SUSPENDED 0x80094006	Certificate service has been suspended for a database restore operation.
CERTSRV_E_ENCODING_LENGTH 0x80094007	The certificate contains an encoded length that is potentially incompatible with older enrollment software.
CERTSRV_E_ROLECONFLICT 0x80094008	The operation is denied. The user has multiple roles assigned, and the CA is configured to enforce role separation.
CERTSRV_E_RESTRICTEDOFFICER 0x80094009	The operation is denied. It can only be performed by a certificate manager that is allowed to manage certificates for the current requester.
CERTSRV_E_KEY_ARCHIVAL_NOT_CONFIGURED 0x8009400A	Cannot archive private key. The CA is not configured for key archival.
CERTSRV_E_NO_VALID_KRA 0x8009400B	Cannot archive private key. The CA could not verify one or more key recovery certificates.
CERTSRV_E_BAD_REQUEST_KEY_ARCHIVAL 0x8009400C	The request is incorrectly formatted. The encrypted private key must be in an unauthenticated attribute in

Value	Meaning
	an outermost signature.
CERTSRV_E_NO_CAADMIN_DEFINED 0x8009400D	At least one security principal must have the permission to manage this CA.
CERTSRV_E_BAD_RENEWAL_CERT_ATTRIBUTE 0x8009400E	The request contains an invalid renewal certificate attribute.
CERTSRV_E_NO_DB_SESSIONS 0x8009400F	An attempt was made to open a CA database session, but there are already too many active sessions. The server may need to be configured to allow additional sessions.
CERTSRV_E_ALIGNMENT_FAULT 0x80094010	A memory reference caused a data alignment fault.
CERTSRV_E_ENROLL_DENIED 0x80094011	The permissions on this CA do not allow the current user to enroll for certificates.
CERTSRV_E_TEMPLATE_DENIED 0x80094012	The permissions on the certificate template do not allow the current user to enroll for this type of certificate.
CERTSRV_E_DOWNLEVEL_DC_SSL_OR_UPGRADE 0x80094013	The contacted domain controller cannot support signed Lightweight Directory Access Protocol (LDAP) traffic. Update the domain controller or configure Certificate Services to use SSL for Active Directory access.
CERTSRV_E_UNSUPPORTED_CERT_TYPE 0x80094800	The requested certificate template is not supported by this CA.
CERTSRV_E_NO_CERT_TYPE 0x80094801	The request contains no certificate template information.
CERTSRV_E_TEMPLATE_CONFLICT 0x80094802	The request contains conflicting template information.
CERTSRV_E_SUBJECT_ALT_NAME_REQUIRED 0x80094803	The request is missing a required Subject Alternate name extension.
CERTSRV_E_ARCHIVED_KEY_REQUIRED 0x80094804	The request is missing a required private key for archival by the server.

Value	Meaning
CERTSRV_E_SMIME_REQUIRED 0x80094805	The request is missing a required SMIME capabilities extension.
CERTSRV_E_BAD_RENEWAL_SUBJECT 0x80094806	The request was made on behalf of a subject other than the caller. The certificate template must be configured to require at least one signature to authorize the request.
CERTSRV_E_BAD_TEMPLATE_VERSION 0x80094807	The request template version is newer than the supported template version.
CERTSRV_E_TEMPLATE_POLICY_REQUIRED 0x80094808	The template is missing a required signature policy attribute.
CERTSRV_E_SIGNATURE_POLICY_REQUIRED 0x80094809	The request is missing required signature policy information.
CERTSRV_E_SIGNATURE_COUNT 0x8009480A	The request is missing one or more required signatures.
CERTSRV_E_SIGNATURE_REJECTED 0x8009480B	One or more signatures did not include the required application or issuance policies. The request is missing one or more required valid signatures.
CERTSRV_E_ISSUANCE_POLICY_REQUIRED 0x8009480C	The request is missing one or more required signature issuance policies.
CERTSRV_E_SUBJECT_UPN_REQUIRED 0x8009480D	The UPN is unavailable and cannot be added to the Subject Alternate name.
CERTSRV_E_SUBJECT_DIRECTORY_GUID_REQUIRED 0x8009480E	The Active Directory GUID is unavailable and cannot be added to the Subject Alternate name.
CERTSRV_E_SUBJECT_DNS_REQUIRED 0x8009480F	The Domain Name System (DNS) name is unavailable and cannot be added to the Subject Alternate name.
CERTSRV_E_ARCHIVED_KEY_UNEXPECTED 0x80094810	The request includes a private key for archival by the server, but key archival is not enabled for the specified certificate template.

Value	Meaning
CERTSRV_E_KEY_LENGTH 0x80094811	The public key does not meet the minimum size required by the specified certificate template.
CERTSRV_E_SUBJECT_EMAIL_REQUIRED 0x80094812	The e-mail name is unavailable and cannot be added to the Subject or Subject Alternate name.
CERTSRV_E_UNKNOWN_CERT_TYPE 0x80094813	One or more certificate templates to be enabled on this CA could not be found.
CERTSRV_E_CERT_TYPE_OVERLAP 0x80094814	The certificate template renewal period is longer than the certificate validity period. The template should be reconfigured or the CA certificate renewed.
CERTSRV_E_TOO_MANY_SIGNATURES 0x80094815	The certificate template requires too many return authorization (RA) signatures. Only one RA signature is allowed.
XENROLL_E_KEY_NOT_EXPORTABLE 0x80095000	The key is not exportable.
XENROLL_E_CANNOT_ADD_ROOT_CERT 0x80095001	You cannot add the root CA certificate into your local store.
XENROLL_E_RESPONSE_KA_HASH_NOT_FOUND 0x80095002	The key archival hash attribute was not found in the response.
XENROLL_E_RESPONSE_UNEXPECTED_KA_HASH 0x80095003	An unexpected key archival hash attribute was found in the response.
XENROLL_E_RESPONSE_KA_HASH_MISMATCH 0x80095004	There is a key archival hash mismatch between the request and the response.
XENROLL_E_KEYSPEC_SMIME_MISMATCH 0x80095005	Signing certificate cannot include SMIME extension.
TRUST_E_SYSTEM_ERROR 0x80096001	A system-level error occurred while verifying trust.
TRUST_E_NO_SIGNER_CERT 0x80096002	The certificate for the signer of the message is invalid or not found.
TRUST_E_COUNTER_SIGNER	One of the counter signatures

Value	Meaning
0x80096003	was invalid.
TRUST_E_CERT_SIGNATURE 0x80096004	The signature of the certificate cannot be verified.
TRUST_E_TIME_STAMP 0x80096005	The time-stamp signature or certificate could not be verified or is malformed.
TRUST_E_BAD_DIGEST 0x80096010	The digital signature of the object did not verify.
TRUST_E_BASIC_CONSTRAINTS 0x80096019	A certificate's basic constraint extension has not been observed.
TRUST_E_FINANCIAL_CRITERIA 0x8009601E	The certificate does not meet or contain the Authenticode financial extensions.
MSSIPOTF_E_OUTOFMEMRANGE 0x80097001	Tried to reference a part of the file outside the proper range.
MSSIPOTF_E_CANTGETOBJECT 0x80097002	Could not retrieve an object from the file.
MSSIPOTF_E_NOHEADTABLE 0x80097003	Could not find the head table in the file.
MSSIPOTF_E_BAD_MAGICNUMBER 0x80097004	The magic number in the head table is incorrect.
MSSIPOTF_E_BAD_OFFSET_TABLE 0x80097005	The offset table has incorrect values.
MSSIPOTF_E_TABLE_TAGORDER 0x80097006	Duplicate table tags or the tags are out of alphabetical order.
MSSIPOTF_E_TABLE_LONGWORD 0x80097007	A table does not start on a long word boundary.
MSSIPOTF_E_BAD_FIRST_TABLE_PLACEMENT 0x80097008	First table does not appear after header information.
MSSIPOTF_E_TABLES_OVERLAP 0x80097009	Two or more tables overlap.
MSSIPOTF_E_TABLE_PADBYTES 0x8009700A	Too many pad bytes between tables, or pad bytes are not 0.
MSSIPOTF_E_FILETOOSMALL 0x8009700B	File is too small to contain the last table.

Value	Meaning
MSSIPOTF_E_TABLE_CHECKSUM 0x8009700C	A table checksum is incorrect.
MSSIPOTF_E_FILE_CHECKSUM 0x8009700D	The file checksum is incorrect.
MSSIPOTF_E_FAILED_POLICY 0x80097010	The signature does not have the correct attributes for the policy.
MSSIPOTF_E_FAILED_HINTS_CHECK 0x80097011	The file did not pass the hints check.
MSSIPOTF_E_NOT_OPENTYPE 0x80097012	The file is not an OpenType file.
MSSIPOTF_E_FILE 0x80097013	Failed on a file operation (such as open, map, read, or write).
MSSIPOTF_E_CRYPT 0x80097014	A call to a CryptoAPI function failed.
MSSIPOTF_E_BADVERSION 0x80097015	There is a bad version number in the file.
MSSIPOTF_E_DSIG_STRUCTURE 0x80097016	The structure of the DSIG table is incorrect.
MSSIPOTF_E_PCONST_CHECK 0x80097017	A check failed in a partially constant table.
MSSIPOTF_E_STRUCTURE 0x80097018	Some kind of structural error.
ERROR_CRED_REQUIRES_CONFIRMATION 0x80097019	The requested credential requires confirmation.
TRUST_E_PROVIDER_UNKNOWN 0x800B0001	Unknown trust provider.
TRUST_E_ACTION_UNKNOWN 0x800B0002	The trust verification action specified is not supported by the specified trust provider.
TRUST_E_SUBJECT_FORM_UNKNOWN 0x800B0003	The form specified for the subject is not one supported or known by the specified trust provider.
TRUST_E_SUBJECT_NOT_TRUSTED 0x800B0004	The subject is not trusted for the specified action.
DIGSIG_E_ENCODE	Error due to problem in ASN.1 encoding process.

Value	Meaning
0x800B0005	
DIGSIG_E_DECODE 0x800B0006	Error due to problem in ASN.1 decoding process.
DIGSIG_E_EXTENSIBILITY 0x800B0007	Reading/writing extensions where attributes are appropriate, and vice versa.
DIGSIG_E_CRYPT0 0x800B0008	Unspecified cryptographic failure.
PERSIST_E_SIZEDEFINITE 0x800B0009	The size of the data could not be determined.
PERSIST_E_SIZEINDEFINITE 0x800B000A	The size of the indefinite-sized data could not be determined.
PERSIST_E_NOTSELSIZING 0x800B000B	This object does not read and write self-sizing data.
TRUST_E_NOSIGNATURE 0x800B0100	No signature was present in the subject.
CERT_E_EXPIRED 0x800B0101	A required certificate is not within its validity period when verifying against the current system clock or the time stamp in the signed file.
CERT_E_VALIDITYPERIODNESTING 0x800B0102	The validity periods of the certification chain do not nest correctly.
CERT_E_ROLE 0x800B0103	A certificate that can only be used as an end entity is being used as a CA or vice versa.
CERT_E_PATHLENCONST 0x800B0104	A path length constraint in the certification chain has been violated.
CERT_E_CRITICAL 0x800B0105	A certificate contains an unknown extension that is marked "critical".
CERT_E_PURPOSE 0x800B0106	A certificate is being used for a purpose other than the ones specified by its CA.
CERT_E_ISSUERCHAINING 0x800B0107	A parent of a given certificate did not issue that child certificate.
CERT_E_MALFORMED 0x800B0108	A certificate is missing or has an empty value for an

Value	Meaning
	important field, such as a subject or issuer name.
CERT_E_UNTRUSTEDROOT 0x800B0109	A certificate chain processed, but terminated in a root certificate that is not trusted by the trust provider.
CERT_E_CHAINING 0x800B010A	A certificate chain could not be built to a trusted root authority.
TRUST_E_FAIL 0x800B010B	Generic trust failure.
CERT_E_REVOKED 0x800B010C	A certificate was explicitly revoked by its issuer.
CERT_E_UNTRUSTEDTESTROOT 0x800B010D	The certification path terminates with the test root that is not trusted with the current policy settings.
CERT_E_REVOCATION_FAILURE 0x800B010E	The revocation process could not continue—the certificates could not be checked.
CERT_E_CN_NO_MATCH 0x800B010F	The certificate's CN name does not match the passed value.
CERT_E_WRONG_USAGE 0x800B0110	The certificate is not valid for the requested usage.
TRUST_E_EXPLICIT_DISTRUST 0x800B0111	The certificate was explicitly marked as untrusted by the user.
CERT_E_UNTRUSTEDCA 0x800B0112	A certification chain processed correctly, but one of the CA certificates is not trusted by the policy provider.
CERT_E_INVALID_POLICY 0x800B0113	The certificate has invalid policy.
CERT_E_INVALID_NAME 0x800B0114	The certificate has an invalid name. The name is not included in the permitted list or is explicitly excluded.
NS_W_SERVER_BANDWIDTH_LIMIT 0x800D0003L	The maximum filebitrate value specified is greater than the server's configured maximum bandwidth.
NS_W_FILE_BANDWIDTH_LIMIT	The maximum bandwidth value specified is less than the



Value	Meaning
0x800D0004L	maximum filebitrate.
NS_W_UNKNOWN_EVENT 0x800D0060L	Unknown %1 event encountered.
NS_I_CATATONIC_FAILURE 0x800D0199L	Disk %1 ( %2 ) on Content Server %3, will be failed because it is catatonic.
NS_I_CATATONIC_AUTO_UNFAIL 0x800D019AL	Disk %1 ( %2 ) on Content Server %3, auto online from catatonic state.
SPAPI_E_EXPECTED_SECTION_NAME 0x800F0000	A non-empty line was encountered in the INF before the start of a section.
SPAPI_E_BAD_SECTION_NAME_LINE 0x800F0001	A section name marker in the information file (INF) is not complete or does not exist on a line by itself.
SPAPI_E_SECTION_NAME_TOO_LONG 0x800F0002	An INF section was encountered whose name exceeds the maximum section name length.
SPAPI_E_GENERAL_SYNTAX 0x800F0003	The syntax of the INF is invalid.
SPAPI_E_WRONG_INF_STYLE 0x800F0100	The style of the INF is different than what was requested.
SPAPI_E_SECTION_NOT_FOUND 0x800F0101	The required section was not found in the INF.
SPAPI_E_LINE_NOT_FOUND 0x800F0102	The required line was not found in the INF.
SPAPI_E_NO_BACKUP 0x800F0103	The files affected by the installation of this file queue have not been backed up for uninstall.
SPAPI_E_NO_ASSOCIATED_CLASS 0x800F0200	The INF or the device information set or element does not have an associated install class.
SPAPI_E_CLASS_MISMATCH 0x800F0201	The INF or the device information set or element does not match the specified install class.
SPAPI_E_DUPLICATE_FOUND	An existing device was found that is a duplicate of the

Value	Meaning
0x800F0202	device being manually installed.
SPAPI_E_NO_DRIVER_SELECTED 0x800F0203	There is no driver selected for the device information set or element.
SPAPI_E_KEY_DOES_NOT_EXIST 0x800F0204	The requested device registry key does not exist.
SPAPI_E_INVALID_DEVINST_NAME 0x800F0205	The device instance name is invalid.
SPAPI_E_INVALID_CLASS 0x800F0206	The install class is not present or is invalid.
SPAPI_E_DEVINST_ALREADY_EXISTS 0x800F0207	The device instance cannot be created because it already exists.
SPAPI_E_DEVINFO_NOT_REGISTERED 0x800F0208	The operation cannot be performed on a device information element that has not been registered.
SPAPI_E_INVALID_REG_PROPERTY 0x800F0209	The device property code is invalid.
SPAPI_E_NO_INF 0x800F020A	The INF from which a driver list is to be built does not exist.
SPAPI_E_NO_SUCH_DEVINST 0x800F020B	The device instance does not exist in the hardware tree.
SPAPI_E_CANT_LOAD_CLASS_ICON 0x800F020C	The icon representing this install class cannot be loaded.
SPAPI_E_INVALID_CLASS_INSTALLER 0x800F020D	The class installer registry entry is invalid.
SPAPI_E_DI_DO_DEFAULT 0x800F020E	The class installer has indicated that the default action should be performed for this installation request.
SPAPI_E_DI_NOFILECOPY 0x800F020F	The operation does not require any files to be copied.
SPAPI_E_INVALID_HWPROFILE 0x800F0210	The specified hardware profile does not exist.
SPAPI_E_NO_DEVICE_SELECTED 0x800F0211	There is no device information element currently selected for this device information set.

Value	Meaning
SPAPI_E_DEVINFO_LIST_LOCKED 0x800F0212	The operation cannot be performed because the device information set is locked.
SPAPI_E_DEVINFO_DATA_LOCKED 0x800F0213	The operation cannot be performed because the device information element is locked.
SPAPI_E_DI_BAD_PATH 0x800F0214	The specified path does not contain any applicable device INFs.
SPAPI_E_NO_CLASSINSTALL_PARAMS 0x800F0215	No class installer parameters have been set for the device information set or element.
SPAPI_E_FILEQUEUE_LOCKED 0x800F0216	The operation cannot be performed because the file queue is locked.
SPAPI_E_BAD_SERVICE_INSTALLSECT 0x800F0217	A service installation section in this INF is invalid.
SPAPI_E_NO_CLASS_DRIVER_LIST 0x800F0218	There is no class driver list for the device information element.
SPAPI_E_NO_ASSOCIATED_SERVICE 0x800F0219	The installation failed because a function driver was not specified for this device instance.
SPAPI_E_NO_DEFAULT_DEVICE_INTERFACE 0x800F021A	There is presently no default device interface designated for this interface class.
SPAPI_E_DEVICE_INTERFACE_ACTIVE 0x800F021B	The operation cannot be performed because the device interface is currently active.
SPAPI_E_DEVICE_INTERFACE_REMOVED 0x800F021C	The operation cannot be performed because the device interface has been removed from the system.
SPAPI_E_BAD_INTERFACE_INSTALLSECT 0x800F021D	An interface installation section in this INF is invalid.
SPAPI_E_NO_SUCH_INTERFACE_CLASS 0x800F021E	This interface class does not exist in the system.
SPAPI_E_INVALID_REFERENCE_STRING 0x800F021F	The reference string supplied for this interface device is invalid.
SPAPI_E_INVALID_MACHINENAME	The specified machine name does not conform to Universal

Value	Meaning
0x800F0220	Naming Convention (UNCs).
SPAPI_E_REMOTE_COMM_FAILURE 0x800F0221	A general remote communication error occurred.
SPAPI_E_MACHINE_UNAVAILABLE 0x800F0222	The machine selected for remote communication is not available at this time.
SPAPI_E_NO_CONFIGMGR_SERVICES 0x800F0223	The Plug and Play service is not available on the remote machine.
SPAPI_E_INVALID_PROPPAGE_PROVIDER 0x800F0224	The property page provider registry entry is invalid.
SPAPI_E_NO_SUCH_DEVICE_INTERFACE 0x800F0225	The requested device interface is not present in the system.
SPAPI_E_DI_POSTPROCESSING_REQUIRED 0x800F0226	The device's co-installer has additional work to perform after installation is complete.
SPAPI_E_INVALID_COINSTALLER 0x800F0227	The device's co-installer is invalid.
SPAPI_E_NO_COMPAT_DRIVERS 0x800F0228	There are no compatible drivers for this device.
SPAPI_E_NO_DEVICE_ICON 0x800F0229	There is no icon that represents this device or device type.
SPAPI_E_INVALID_INF_LOGCONFIG 0x800F022A	A logical configuration specified in this INF is invalid.
SPAPI_E_DI_DONT_INSTALL 0x800F022B	The class installer has denied the request to install or upgrade this device.
SPAPI_E_INVALID_FILTER_DRIVER 0x800F022C	One of the filter drivers installed for this device is invalid.
SPAPI_E_NON_WINDOWS_NT_DRIVER 0x800F022D	The driver selected for this device does not support Windows XP.
SPAPI_E_NON_WINDOWS_DRIVER 0x800F022E	The driver selected for this device does not support Windows.
SPAPI_E_NO_CATALOG_FOR_OEM_INF 0x800F022F	The third-party INF does not contain digital signature information.

Value	Meaning
SPAPI_E_DEVINSTALL_QUEUE_NONNATIVE 0x800F0230	An invalid attempt was made to use a device installation file queue for verification of digital signatures relative to other platforms.
SPAPI_E_NOT_DISABLEABLE 0x800F0231	The device cannot be disabled.
SPAPI_E_CANT_REMOVE_DEVINST 0x800F0232	The device could not be dynamically removed.
SPAPI_E_INVALID_TARGET 0x800F0233	Cannot copy to specified target.
SPAPI_E_DRIVER_NONNATIVE 0x800F0234	Driver is not intended for this platform.
SPAPI_E_IN_WOW64 0x800F0235	Operation not allowed in WOW64.
SPAPI_E_SET_SYSTEM_RESTORE_POINT 0x800F0236	The operation involving unsigned file copying was rolled back, so that a system restore point could be set.
SPAPI_E_INCORRECTLY_COPIED_INF 0x800F0237	An INF was copied into the Windows INF directory in an improper manner.
SPAPI_E_SCE_DISABLED 0x800F0238	The Security Configuration Editor (SCE) APIs have been disabled on this embedded product.
SPAPI_E_UNKNOWN_EXCEPTION 0x800F0239	An unknown exception was encountered.
SPAPI_E_PNP_REGISTRY_ERROR 0x800F023A	A problem was encountered when accessing the Plug and Play registry database.
SPAPI_E_REMOTE_REQUEST_UNSUPPORTED 0x800F023B	The requested operation is not supported for a remote machine.
SPAPI_E_NOT_AN_INSTALLED_OEM_INF 0x800F023C	The specified file is not an installed original equipment manufacturer (OEM) INF.
SPAPI_E_INF_IN_USE_BY_DEVICES 0x800F023D	One or more devices are presently installed using the specified INF.
SPAPI_E_DI_FUNCTION_OBSOLETE	The requested device install operation is obsolete.

Value	Meaning
0x800F023E	
SPAPI_E_NO_AUTHENTICODE_CATALOG 0x800F023F	A file could not be verified because it does not have an associated catalog signed via Authenticode.
SPAPI_E_AUTHENTICODE_DISALLOWED 0x800F0240	Authenticode signature verification is not supported for the specified INF.
SPAPI_E_AUTHENTICODE_TRUSTED_PUBLISHER 0x800F0241	The INF was signed with an Authenticode catalog from a trusted publisher.
SPAPI_E_AUTHENTICODE_TRUST_NOT_ESTABLISHED 0x800F0242	The publisher of an Authenticode-signed catalog has not yet been established as trusted.
SPAPI_E_AUTHENTICODE_PUBLISHER_NOT_TRUSTED 0x800F0243	The publisher of an Authenticode-signed catalog was not established as trusted.
SPAPI_E_SIGNATURE_OSATTRIBUTE_MISMATCH 0x800F0244	The software was tested for compliance with Windows logo requirements on a different version of Windows and may not be compatible with this version.
SPAPI_E_ONLY_VALIDATE_VIA_AUTHENTICODE 0x800F0245	The file may be validated only by a catalog signed via Authenticode.
SPAPI_E_DEVICE_INSTALLER_NOT_READY 0x800F0246	One of the installers for this device cannot perform the installation at this time.
SPAPI_E_DRIVER_STORE_ADD_FAILED 0x800F0247	A problem was encountered while attempting to add the driver to the store.
SPAPI_E_DEVICE_INSTALL_BLOCKED 0x800F0248	The installation of this device is forbidden by system policy. Contact your system administrator.
SPAPI_E_DRIVER_INSTALL_BLOCKED 0x800F0249	The installation of this driver is forbidden by system policy. Contact your system administrator.
SPAPI_E_WRONG_INF_TYPE 0x800F024A	The specified INF is the wrong type for this operation.
SPAPI_E_FILE_HASH_NOT_IN_CATALOG	The hash for the file is not

Value	Meaning
0x800F024B	present in the specified catalog file. The file is likely corrupt or the victim of tampering.
SPAPI_E_DRIVER_STORE_DELETE_FAILED 0x800F024C	A problem was encountered while attempting to delete the driver from the store.
SPAPI_E_UNRECOVERABLE_STACK_OVERFLOW 0x800F0300	An unrecoverable stack overflow was encountered.
SPAPI_E_ERROR_NOT_INSTALLED 0x800F1000	No installed components were detected.
SCARD_F_INTERNAL_ERROR 0x80100001	An internal consistency check failed.
SCARD_E_CANCELLED 0x80100002	The action was canceled by an SCardCancel request.
SCARD_E_INVALID_HANDLE 0x80100003	The supplied handle was invalid.
SCARD_E_INVALID_PARAMETER 0x80100004	One or more of the supplied parameters could not be properly interpreted.
SCARD_E_INVALID_TARGET 0x80100005	Registry startup information is missing or invalid.
SCARD_E_NO_MEMORY 0x80100006	Not enough memory available to complete this command.
SCARD_F_WAITED_TOO_LONG 0x80100007	An internal consistency timer has expired.
SCARD_E_INSUFFICIENT_BUFFER 0x80100008	The data buffer to receive returned data is too small for the returned data.
SCARD_E_UNKNOWN_READER 0x80100009	The specified reader name is not recognized.
SCARD_E_TIMEOUT 0x8010000A	The user-specified time-out value has expired.
SCARD_E_SHARING_VIOLATION 0x8010000B	The smart card cannot be accessed because of other connections outstanding.
SCARD_E_NO_SMARTCARD 0x8010000C	The operation requires a smart card, but no smart card is currently in the device.

Value	Meaning
SCARD_E_UNKNOWN_CARD 0x8010000D	The specified smart card name is not recognized.
SCARD_E_CANT_DISPOSE 0x8010000E	The system could not dispose of the media in the requested manner.
SCARD_E_PROTO_MISMATCH 0x8010000F	The requested protocols are incompatible with the protocol currently in use with the smart card.
SCARD_E_NOT_READY 0x80100010	The reader or smart card is not ready to accept commands.
SCARD_E_INVALID_VALUE 0x80100011	One or more of the supplied parameters values could not be properly interpreted.
SCARD_E_SYSTEM_CANCELLED 0x80100012	The action was canceled by the system, presumably to log off or shut down.
SCARD_F_COMM_ERROR 0x80100013	An internal communications error has been detected.
SCARD_F_UNKNOWN_ERROR 0x80100014	An internal error has been detected, but the source is unknown.
SCARD_E_INVALID_ATR 0x80100015	An automatic terminal recognition (ATR) obtained from the registry is not a valid ATR string.
SCARD_E_NOT_TRANSACTED 0x80100016	An attempt was made to end a nonexistent transaction.
SCARD_E_READER_UNAVAILABLE 0x80100017	The specified reader is not currently available for use.
SCARD_P_SHUTDOWN 0x80100018	The operation has been aborted to allow the server application to exit.
SCARD_E_PCI_TOO_SMALL 0x80100019	The peripheral component interconnect (PCI) Receive buffer was too small.
SCARD_E_READER_UNSUPPORTED 0x8010001A	The reader driver does not meet minimal requirements for support.
SCARD_E_DUPLICATE_READER 0x8010001B	The reader driver did not produce a unique reader



Value	Meaning
	name.
SCARD_E_CARD_UNSUPPORTED 0x8010001C	The smart card does not meet minimal requirements for support.
SCARD_E_NO_SERVICE 0x8010001D	The smart card resource manager is not running.
SCARD_E_SERVICE_STOPPED 0x8010001E	The smart card resource manager has shut down.
SCARD_E_UNEXPECTED 0x8010001F	An unexpected card error has occurred.
SCARD_E_ICC_INSTALLATION 0x80100020	No primary provider can be found for the smart card.
SCARD_E_ICC_CREATEORDER 0x80100021	The requested order of object creation is not supported.
SCARD_E_UNSUPPORTED_FEATURE 0x80100022	This smart card does not support the requested feature.
SCARD_E_DIR_NOT_FOUND 0x80100023	The identified directory does not exist in the smart card.
SCARD_E_FILE_NOT_FOUND 0x80100024	The identified file does not exist in the smart card.
SCARD_E_NO_DIR 0x80100025	The supplied path does not represent a smart card directory.
SCARD_E_NO_FILE 0x80100026	The supplied path does not represent a smart card file.
SCARD_E_NO_ACCESS 0x80100027	Access is denied to this file.
SCARD_E_WRITE_TOO_MANY 0x80100028	The smart card does not have enough memory to store the information.
SCARD_E_BAD_SEEK 0x80100029	There was an error trying to set the smart card file object pointer.
SCARD_E_INVALID_CHV 0x8010002A	The supplied PIN is incorrect.
SCARD_E_UNKNOWN_RES_MNG 0x8010002B	An unrecognized error code was returned from a layered component.

Value	Meaning
SCARD_E_NO_SUCH_CERTIFICATE 0x8010002C	The requested certificate does not exist.
SCARD_E_CERTIFICATE_UNAVAILABLE 0x8010002D	The requested certificate could not be obtained.
SCARD_E_NO_READERS_AVAILABLE 0x8010002E	Cannot find a smart card reader.
SCARD_E_COMM_DATA_LOST 0x8010002F	A communications error with the smart card has been detected. Retry the operation.
SCARD_E_NO_KEY_CONTAINER 0x80100030	The requested key container does not exist on the smart card.
SCARD_E_SERVER_TOO_BUSY 0x80100031	The smart card resource manager is too busy to complete this operation.
SCARD_W_UNSUPPORTED_CARD 0x80100065	The reader cannot communicate with the smart card, due to ATR configuration conflicts.
SCARD_W_UNRESPONSIVE_CARD 0x80100066	The smart card is not responding to a reset.
SCARD_W_UNPOWERED_CARD 0x80100067	Power has been removed from the smart card, so that further communication is not possible.
SCARD_W_RESET_CARD 0x80100068	The smart card has been reset, so any shared state information is invalid.
SCARD_W_REMOVED_CARD 0x80100069	The smart card has been removed, so that further communication is not possible.
SCARD_W_SECURITY_VIOLATION 0x8010006A	Access was denied because of a security violation.
SCARD_W_WRONG_CHV 0x8010006B	The card cannot be accessed because the wrong PIN was presented.
SCARD_W_CHV_BLOCKED 0x8010006C	The card cannot be accessed because the maximum number of PIN entry attempts has been reached.
SCARD_W_EOF 0x8010006D	The end of the smart card file has been reached.

Value	Meaning
SCARD_W_CANCELLED_BY_USER 0x8010006E	The action was canceled by the user.
SCARD_W_CARD_NOT_AUTHENTICATED 0x8010006F	No PIN was presented to the smart card.
COMADMIN_E_OBJECTERRORS 0x80110401	Errors occurred accessing one or more objects—the ErrorInfo collection may have more detail.
COMADMIN_E_OBJECTINVALID 0x80110402	One or more of the object's properties are missing or invalid.
COMADMIN_E_KEYMISSING 0x80110403	The object was not found in the catalog.
COMADMIN_E_ALREADYINSTALLED 0x80110404	The object is already registered.
COMADMIN_E_APP_FILE_WRITEFAIL 0x80110407	An error occurred writing to the application file.
COMADMIN_E_APP_FILE_READFAIL 0x80110408	An error occurred reading the application file.
COMADMIN_E_APP_FILE_VERSION 0x80110409	Invalid version number in application file.
COMADMIN_E_BADPATH 0x8011040A	The file path is invalid.
COMADMIN_E_APPLICATIONEXISTS 0x8011040B	The application is already installed.
COMADMIN_E_ROLEEXISTS 0x8011040C	The role already exists.
COMADMIN_E_CANTCOPYFILE 0x8011040D	An error occurred copying the file.
COMADMIN_E_NOUSER 0x8011040F	One or more users are not valid.
COMADMIN_E_INVALIDUSERIDS 0x80110410	One or more users in the application file are not valid.
COMADMIN_E_NOREGISTRYCLSID 0x80110411	The component's CLSID is missing or corrupt.
COMADMIN_E_BADREGISTRYPROGID 0x80110412	The component's programmatic ID is missing or

Value	Meaning
	corrupt.
COMADMIN_E_AUTHENTICATIONLEVEL 0x80110413	Unable to set required authentication level for update request.
COMADMIN_E_USERPASSWDNOTVALID 0x80110414	The identity or password set on the application is not valid.
COMADMIN_E_CLSIDORIIDMISMATCH 0x80110418	Application file CLSIDs or instance identifiers (IIDs) do not match corresponding DLLs.
COMADMIN_E_REMOTEINTERFACE 0x80110419	Interface information is either missing or changed.
COMADMIN_E_DLLREGISTERSERVER 0x8011041A	DllRegisterServer failed on component install.
COMADMIN_E_NOSERVERSHARE 0x8011041B	No server file share available.
COMADMIN_E_DLLLOADFAILED 0x8011041D	DLL could not be loaded.
COMADMIN_E_BADREGISTRYLIBID 0x8011041E	The registered TypeLib ID is not valid.
COMADMIN_E_APPDIRNOTFOUND 0x8011041F	Application install directory not found.
COMADMIN_E_REGISTRARFAILED 0x80110423	Errors occurred while in the component registrar.
COMADMIN_E_COMPFILE_DOESNOTEXIST 0x80110424	The file does not exist.
COMADMIN_E_COMPFILE_LOADDLLFAIL 0x80110425	The DLL could not be loaded.
COMADMIN_E_COMPFILE_GETCLASSOBJ 0x80110426	GetClassObject failed in the DLL.
COMADMIN_E_COMPFILE_CLASSNOTAVAIL 0x80110427	The DLL does not support the components listed in the TypeLib.
COMADMIN_E_COMPFILE_BADTLB 0x80110428	The TypeLib could not be loaded.
COMADMIN_E_COMPFILE_NOTINSTALLABLE 0x80110429	The file does not contain components or component information.

Value	Meaning
COMADMIN_E_NOTCHANGEABLE 0x8011042A	Changes to this object and its subobjects have been disabled.
COMADMIN_E_NOTDELETEABLE 0x8011042B	The delete function has been disabled for this object.
COMADMIN_E_SESSION 0x8011042C	The server catalog version is not supported.
COMADMIN_E_COMP_MOVE_LOCKED 0x8011042D	The component move was disallowed because the source or destination application is either a system application or currently locked against changes.
COMADMIN_E_COMP_MOVE_BAD_DEST 0x8011042E	The component move failed because the destination application no longer exists.
COMADMIN_E_REGISTERTLB 0x80110430	The system was unable to register the TypeLib.
COMADMIN_E_SYSTEMAPP 0x80110433	This operation cannot be performed on the system application.
COMADMIN_E_COMPFILE_NOREGISTRAR 0x80110434	The component registrar referenced in this file is not available.
COMADMIN_E_COREQCOMPINSTALLED 0x80110435	A component in the same DLL is already installed.
COMADMIN_E_SERVICENOTINSTALLED 0x80110436	The service is not installed.
COMADMIN_E_PROPERTYSAVEFAILED 0x80110437	One or more property settings are either invalid or in conflict with each other.
COMADMIN_E_OBJECTEXISTS 0x80110438	The object you are attempting to add or rename already exists.
COMADMIN_E_COMPONENTEXISTS 0x80110439	The component already exists.
COMADMIN_E_REGFILE_CORRUPT 0x8011043B	The registration file is corrupt.
COMADMIN_E_PROPERTY_OVERFLOW 0x8011043C	The property value is too large.

Value	Meaning
COMADMIN_E_NOTINREGISTRY 0x8011043E	Object was not found in registry.
COMADMIN_E_OBJECTNOTPOOLABLE 0x8011043F	This object cannot be pooled.
COMADMIN_E_APPLID_MATCHES_CLSID 0x80110446	A CLSID with the same GUID as the new application ID is already installed on this machine.
COMADMIN_E_ROLE_DOES_NOT_EXIST 0x80110447	A role assigned to a component, interface, or method did not exist in the application.
COMADMIN_E_START_APP_NEEDS_COMPONENTS 0x80110448	You must have components in an application to start the application.
COMADMIN_E_REQUIRES_DIFFERENT_PLATFORM 0x80110449	This operation is not enabled on this platform.
COMADMIN_E_CAN_NOT_EXPORT_APP_PROXY 0x8011044A	Application proxy is not exportable.
COMADMIN_E_CAN_NOT_START_APP 0x8011044B	Failed to start application because it is either a library application or an application proxy.
COMADMIN_E_CAN_NOT_EXPORT_SYS_APP 0x8011044C	System application is not exportable.
COMADMIN_E_CANT_SUBSCRIBE_TO_COMPONENT 0x8011044D	Cannot subscribe to this component (the component may have been imported).
COMADMIN_E_EVENTCLASS_CANT_BE_SUBSCRIBER 0x8011044E	An event class cannot also be a subscriber component.
COMADMIN_E_LIB_APP_PROXY_INCOMPATIBLE 0x8011044F	Library applications and application proxies are incompatible.
COMADMIN_E_BASE_PARTITION_ONLY 0x80110450	This function is valid for the base partition only.
COMADMIN_E_START_APP_DISABLED 0x80110451	You cannot start an application that has been disabled.
COMADMIN_E_CAT_DUPLICATE_PARTITION_NAME 0x80110457	The specified partition name is already in use on this computer.

Value	Meaning
COMADMIN_E_CAT_INVALID_PARTITION_NAME 0x80110458	The specified partition name is invalid. Check that the name contains at least one visible character.
COMADMIN_E_CAT_PARTITION_IN_USE 0x80110459	The partition cannot be deleted because it is the default partition for one or more users.
COMADMIN_E_FILE_PARTITION_DUPLICATE_FILES 0x8011045A	The partition cannot be exported because one or more components in the partition have the same file name.
COMADMIN_E_CAT_IMPORTED_COMPONENTS_NOT_ALLOWED 0x8011045B	Applications that contain one or more imported components cannot be installed into a nonbase partition.
COMADMIN_E_AMBIGUOUS_APPLICATION_NAME 0x8011045C	The application name is not unique and cannot be resolved to an application ID.
COMADMIN_E_AMBIGUOUS_PARTITION_NAME 0x8011045D	The partition name is not unique and cannot be resolved to a partition ID.
COMADMIN_E_REGDB_NOTINITIALIZED 0x80110472	The COM+ registry database has not been initialized.
COMADMIN_E_REGDB_NOTOPEN 0x80110473	The COM+ registry database is not open.
COMADMIN_E_REGDB_SYSTEMERR 0x80110474	The COM+ registry database detected a system error.
COMADMIN_E_REGDB_ALREADYRUNNING 0x80110475	The COM+ registry database is already running.
COMADMIN_E_MIG_VERSIONNOTSUPPORTED 0x80110480	This version of the COM+ registry database cannot be migrated.
COMADMIN_E_MIG_SCHEMANOTFOUND 0x80110481	The schema version to be migrated could not be found in the COM+ registry database.
COMADMIN_E_CAT_BITNESSMISMATCH 0x80110482	There was a type mismatch between binaries.
COMADMIN_E_CAT_UNACCEPTABLEBITNESS 0x80110483	A binary of unknown or invalid type was provided.
COMADMIN_E_CAT_WRONGAPPBITNESS	There was a type mismatch between a binary and an

Value	Meaning
0x80110484	application.
COMADMIN_E_CAT_PAUSE_RESUME_NOT_SUPPORTED 0x80110485	The application cannot be paused or resumed.
COMADMIN_E_CAT_SERVERFAULT 0x80110486	The COM+ catalog server threw an exception during execution.
COMQC_E_APPLICATION_NOT_QUEUED 0x80110600	Only COM+ applications marked "queued" can be invoked using the "queue" moniker.
COMQC_E_NO_QUEUEABLE_INTERFACES 0x80110601	At least one interface must be marked "queued" to create a queued component instance with the "queue" moniker.
COMQC_E_QUEUEING_SERVICE_NOT_AVAILABLE 0x80110602	Message Queuing is required for the requested operation and is not installed.
COMQC_E_NO_IPERSISTSTREAM 0x80110603	Unable to marshal an interface that does not support IPersistStream.
COMQC_E_BAD_MESSAGE 0x80110604	The message is improperly formatted or was damaged in transit.
COMQC_E_UNAUTHENTICATED 0x80110605	An unauthenticated message was received by an application that accepts only authenticated messages.
COMQC_E_UNTRUSTED_ENQUEUER 0x80110606	The message was requeued or moved by a user not in the QC Trusted User "role".
MSDTC_E_DUPLICATE_RESOURCE 0x80110701	Cannot create a duplicate resource of type Distributed Transaction Coordinator.
COMADMIN_E_OBJECT_PARENT_MISSING 0x80110808	One of the objects being inserted or updated does not belong to a valid parent collection.
COMADMIN_E_OBJECT_DOES_NOT_EXIST 0x80110809	One of the specified objects cannot be found.
COMADMIN_E_APP_NOT_RUNNING 0x8011080A	The specified application is not currently running.
COMADMIN_E_INVALID_PARTITION 0x8011080B	The partitions specified are not valid.



Value	Meaning
COMADMIN_E_SVCAPP_NOT_POOLABLE_OR_RECYCLABLE 0x8011080D	COM+ applications that run as Windows NT service may not be pooled or recycled.
COMADMIN_E_USER_IN_SET 0x8011080E	One or more users are already assigned to a local partition set.
COMADMIN_E_CANTRECYCLELIBRARYAPPS 0x8011080F	Library applications may not be recycled.
COMADMIN_E_CANTRECYCLESERVICEAPPS 0x80110811	Applications running as Windows NT services may not be recycled.
COMADMIN_E_PROCESSALREADYRECYCLED 0x80110812	The process has already been recycled.
COMADMIN_E_PAUSEDPROCESSMAYNOTBERECYCLED 0x80110813	A paused process may not be recycled.
COMADMIN_E_CANTMAKEINPROCSERVICE 0x80110814	Library applications may not be Windows NT services.
COMADMIN_E_PROGIDINUSEBYCLSID 0x80110815	The ProgID provided to the copy operation is invalid. The ProgID is in use by another registered CLSID.
COMADMIN_E_DEFAULT_PARTITION_NOT_IN_SET 0x80110816	The partition specified as the default is not a member of the partition set.
COMADMIN_E_RECYCLEDPROCESSMAYNOTBEPAUSED 0x80110817	A recycled process may not be paused.
COMADMIN_E_PARTITION_ACCESSDENIED 0x80110818	Access to the specified partition is denied.
COMADMIN_E_PARTITION_MSI_ONLY 0x80110819	Only application files (*.msi files) can be installed into partitions.
COMADMIN_E_LEGACYCOMPS_NOT_ALLOWED_IN_1_0_FORMAT 0x8011081A	Applications containing one or more legacy components may not be exported to 1.0 format.
COMADMIN_E_LEGACYCOMPS_NOT_ALLOWED_IN_NONBASE_PARTITIONS 0x8011081B	Legacy components may not exist in nonbase partitions.
COMADMIN_E_COMP_MOVE_SOURCE 0x8011081C	A component cannot be moved (or copied) from the System Application, an application proxy, or a nonchangeable application.

Value	Meaning
COMADMIN_E_COMP_MOVE_DEST 0x8011081D	A component cannot be moved (or copied) to the System Application, an application proxy or a nonchangeable application.
COMADMIN_E_COMP_MOVE_PRIVATE 0x8011081E	A private component cannot be moved (or copied) to a library application or to the base partition.
COMADMIN_E_BASEPARTITION_REQUIRED_IN_SET 0x8011081F	The Base Application Partition exists in all partition sets and cannot be removed.
COMADMIN_E_CANNOT_ALIAS_EVENTCLASS 0x80110820	Alas, Event Class components cannot be aliased.
COMADMIN_E_PRIVATE_ACCESSDENIED 0x80110821	Access is denied because the component is private.
COMADMIN_E_SAFERINVALID 0x80110822	The specified SAFER level is invalid.
COMADMIN_E_REGISTRY_ACCESSDENIED 0x80110823	The specified user cannot write to the system registry.
COMADMIN_E_PARTITIONS_DISABLED 0x80110824	COM+ partitions are currently disabled.
ERROR_FLT_NO_HANDLER_DEFINED 0x801F0001	A handler was not defined by the filter for this operation.
ERROR_FLT_CONTEXT_ALREADY_DEFINED 0x801F0002	A context is already defined for this object.
ERROR_FLT_INVALID_ASYNCHRONOUS_REQUEST 0x801F0003	Asynchronous requests are not valid for this operation.
ERROR_FLT_DISALLOW_FAST_IO 0x801F0004	Disallow the Fast IO path for this operation.
ERROR_FLT_INVALID_NAME_REQUEST 0x801F0005	An invalid name request was made. The name requested cannot be retrieved at this time.
ERROR_FLT_NOT_SAFE_TO_POST_OPERATION 0x801F0006	Posting this operation to a worker thread for further processing is not safe at this time because it could lead to a system deadlock.
ERROR_FLT_NOT_INITIALIZED 0x801F0007	The Filter Manager was not initialized when a filter tried to

Value	Meaning
	register. Be sure that the Filter Manager is being loaded as a driver.
ERROR_FLT_FILTER_NOT_READY 0x801F0008	The filter is not ready for attachment to volumes because it has not finished initializing (FltStartFiltering has not been called).
ERROR_FLT_POST_OPERATION_CLEANUP 0x801F0009	The filter must clean up any operation-specific context at this time because it is being removed from the system before the operation is completed by the lower drivers.
ERROR_FLT_INTERNAL_ERROR 0x801F000A	The Filter Manager had an internal error from which it cannot recover; therefore, the operation has been failed. This is usually the result of a filter returning an invalid value from a preoperation callback.
ERROR_FLT_DELETING_OBJECT 0x801F000B	The object specified for this action is in the process of being deleted; therefore, the action requested cannot be completed at this time.
ERROR_FLT_MUST_BE_NONPAGED_POOL 0x801F000C	Nonpaged pool must be used for this type of context.
ERROR_FLT_DUPLICATE_ENTRY 0x801F000D	A duplicate handler definition has been provided for an operation.
ERROR_FLT_CBDQ_DISABLED 0x801F000E	The callback data queue has been disabled.
ERROR_FLT_DO_NOT_ATTACH 0x801F000F	Do not attach the filter to the volume at this time.
ERROR_FLT_DO_NOT_DETACH 0x801F0010	Do not detach the filter from the volume at this time.
ERROR_FLT_INSTANCE_ALTITUDE_COLLISION 0x801F0011	An instance already exists at this altitude on the volume specified.
ERROR_FLT_INSTANCE_NAME_COLLISION 0x801F0012	An instance already exists with this name on the volume specified.
ERROR_FLT_FILTER_NOT_FOUND	The system could not find the

Value	Meaning
0x801F0013	filter specified.
ERROR_FLT_VOLUME_NOT_FOUND 0x801F0014	The system could not find the volume specified.
ERROR_FLT_INSTANCE_NOT_FOUND 0x801F0015	The system could not find the instance specified.
ERROR_FLT_CONTEXT_ALLOCATION_NOT_FOUND 0x801F0016	No registered context allocation definition was found for the given request.
ERROR_FLT_INVALID_CONTEXT_REGISTRATION 0x801F0017	An invalid parameter was specified during context registration.
ERROR_FLT_NAME_CACHE_MISS 0x801F0018	The name requested was not found in the Filter Manager name cache and could not be retrieved from the file system.
ERROR_FLT_NO_DEVICE_OBJECT 0x801F0019	The requested device object does not exist for the given volume.
ERROR_FLT_VOLUME_ALREADY_MOUNTED 0x801F001A	The specified volume is already mounted.
ERROR_FLT_ALREADY_ENLISTED 0x801F001B	The specified Transaction Context is already enlisted in a transaction.
ERROR_FLT_CONTEXT_ALREADY_LINKED 0x801F001C	The specified context is already attached to another object.
ERROR_FLT_NO_WAITER_FOR_REPLY 0x801F0020	No waiter is present for the filter's reply to this message.
ERROR_HUNG_DISPLAY_DRIVER_THREAD 0x80260001	{Display Driver Stopped Responding} The %hs display driver has stopped working normally. Save your work and reboot the system to restore full display functionality. The next time you reboot the machine a dialog will be displayed giving you a chance to report this failure to Microsoft.
ERROR_MONITOR_NO_DESCRIPTOR 0x80261001	Monitor descriptor could not be obtained.
ERROR_MONITOR_UNKNOWN_DESCRIPTOR_FORMAT 0x80261002	Format of the obtained monitor descriptor is not

Value	Meaning
	supported by this release.
DWM_E_COMPOSITIONDISABLED 0x80263001	{Desktop Composition is Disabled} The operation could not be completed because desktop composition is disabled.
DWM_E_REMOTING_NOT_SUPPORTED 0x80263002	{Some Desktop Composition APIs Are Not Supported While Remoting} Some desktop composition APIs are not supported while remoting. The operation is not supported while running in a remote session.
DWM_E_NO_REDIRECTION_SURFACE_AVAILABLE 0x80263003	{No DWM Redirection Surface is Available} The Desktop Window Manager (DWM) was unable to provide a redirection surface to complete the DirectX present.
DWM_E_NOT_QUEUEING_PRESENTS 0x80263004	{DWM Is Not Queuing Presents for the Specified Window} The window specified is not currently using queued presents.
TPM_E_ERROR_MASK 0x80280000	This is an error mask to convert Trusted Platform Module (TPM) hardware errors to Win32 errors.
TPM_E_AUTHFAIL 0x80280001	Authentication failed.
TPM_E_BADINDEX 0x80280002	The index to a Platform Configuration Register (PCR), DIR, or other register is incorrect.
TPM_E_BAD_PARAMETER 0x80280003	One or more parameters are bad.
TPM_E_AUDITFAILURE 0x80280004	An operation completed successfully but the auditing of that operation failed.
TPM_E_CLEAR_DISABLED 0x80280005	The clear disable flag is set and all clear operations now require physical access.
TPM_E_DEACTIVATED 0x80280006	The TPM is deactivated.

Value	Meaning
TPM_E_DISABLED 0x80280007	The TPM is disabled.
TPM_E_DISABLED_CMD 0x80280008	The target command has been disabled.
TPM_E_FAIL 0x80280009	The operation failed.
TPM_E_BAD_ORDINAL 0x8028000A	The ordinal was unknown or inconsistent.
TPM_E_INSTALL_DISABLED 0x8028000B	The ability to install an owner is disabled.
TPM_E_INVALID_KEYHANDLE 0x8028000C	The key handle cannot be interpreted.
TPM_E_KEYNOTFOUND 0x8028000D	The key handle points to an invalid key.
TPM_E_INAPPROPRIATE_ENC 0x8028000E	Unacceptable encryption scheme.
TPM_E_MIGRATEFAIL 0x8028000F	Migration authorization failed.
TPM_E_INVALID_PCR_INFO 0x80280010	PCR information could not be interpreted.
TPM_E_NOSPACE 0x80280011	No room to load key.
TPM_E_NOSRK 0x80280012	There is no storage root key (SRK) set.
TPM_E_NOTSEALED_BLOB 0x80280013	An encrypted blob is invalid or was not created by this TPM.
TPM_E_OWNER_SET 0x80280014	There is already an owner.
TPM_E_RESOURCES 0x80280015	The TPM has insufficient internal resources to perform the requested action.
TPM_E_SHORTRANDOM 0x80280016	A random string was too short.
TPM_E_SIZE 0x80280017	The TPM does not have the space to perform the operation.

Value	Meaning
TPM_E_WRONGPCRVAL 0x80280018	The named PCR value does not match the current PCR value.
TPM_E_BAD_PARAM_SIZE 0x80280019	The <i>paramSize</i> argument to the command has the incorrect value.
TPM_E_SHA_THREAD 0x8028001A	There is no existing SHA-1 thread.
TPM_E_SHA_ERROR 0x8028001B	The calculation is unable to proceed because the existing SHA-1 thread has already encountered an error.
TPM_E_FAILEDSELFTEST 0x8028001C	Self-test has failed and the TPM has shut down.
TPM_E_AUTH2FAIL 0x8028001D	The authorization for the second key in a two-key function failed authorization.
TPM_E_BADTAG 0x8028001E	The tag value sent to for a command is invalid.
TPM_E_IOERROR 0x8028001F	An I/O error occurred transmitting information to the TPM.
TPM_E_ENCRYPT_ERROR 0x80280020	The encryption process had a problem.
TPM_E_DECRYPT_ERROR 0x80280021	The decryption process did not complete.
TPM_E_INVALID_AUTHHANDLE 0x80280022	An invalid handle was used.
TPM_E_NO_ENDORSEMENT 0x80280023	The TPM does not have an endorsement key (EK) installed.
TPM_E_INVALID_KEYUSAGE 0x80280024	The usage of a key is not allowed.
TPM_E_WRONG_ENTITYTYPE 0x80280025	The submitted entity type is not allowed.
TPM_E_INVALID_POSTINIT 0x80280026	The command was received in the wrong sequence relative to TPM_Init and a subsequent TPM_Startup.
TPM_E_INAPPROPRIATE_SIG	Signed data cannot include

Value	Meaning
0x80280027	additional DER information.
TPM_E_BAD_KEY_PROPERTY 0x80280028	The key properties in TPM_KEY_PARMs are not supported by this TPM.
TPM_E_BAD_MIGRATION 0x80280029	The migration properties of this key are incorrect.
TPM_E_BAD_SCHEME 0x8028002A	The signature or encryption scheme for this key is incorrect or not permitted in this situation.
TPM_E_BAD_DATASIZE 0x8028002B	The size of the data (or blob) parameter is bad or inconsistent with the referenced key.
TPM_E_BAD_MODE 0x8028002C	A mode parameter is bad, such as capArea or subCapArea for TPM_GetCapability, physicalPresence parameter for TPM_PhysicalPresence, or migrationType for TPM_CreateMigrationBlob.
TPM_E_BAD_PRESENCE 0x8028002D	Either the physicalPresence or physicalPresenceLock bits have the wrong value.
TPM_E_BAD_VERSION 0x8028002E	The TPM cannot perform this version of the capability.
TPM_E_NO_WRAP_TRANSPORT 0x8028002F	The TPM does not allow for wrapped transport sessions.
TPM_E_AUDITFAIL_UNSUCCESSFUL 0x80280030	TPM audit construction failed and the underlying command was returning a failure code also.
TPM_E_AUDITFAIL_SUCCESSFUL 0x80280031	TPM audit construction failed and the underlying command was returning success.
TPM_E_NOTRESETABLE 0x80280032	Attempt to reset a PCR that does not have the resettable attribute.
TPM_E_NOTLOCAL 0x80280033	Attempt to reset a PCR register that requires locality and the locality modifier not part of command transport.
TPM_E_BAD_TYPE	Make identity blob not



Value	Meaning
0x80280034	properly typed.
TPM_E_INVALID_RESOURCE 0x80280035	When saving context identified resource type does not match actual resource.
TPM_E_NOTFIPS 0x80280036	The TPM is attempting to execute a command only available when in Federal Information Processing Standards (FIPS) mode.
TPM_E_INVALID_FAMILY 0x80280037	The command is attempting to use an invalid family ID.
TPM_E_NO_NV_PERMISSION 0x80280038	The permission to manipulate the NV storage is not available.
TPM_E_REQUIRES_SIGN 0x80280039	The operation requires a signed command.
TPM_E_KEY_NOTSUPPORTED 0x8028003A	Wrong operation to load an NV key.
TPM_E_AUTH_CONFLICT 0x8028003B	NV_LoadKey blob requires both owner and blob authorization.
TPM_E_AREA_LOCKED 0x8028003C	The NV area is locked and not writable.
TPM_E_BAD_LOCALITY 0x8028003D	The locality is incorrect for the attempted operation.
TPM_E_READ_ONLY 0x8028003E	The NV area is read-only and cannot be written to.
TPM_E_PER_NOWRITE 0x8028003F	There is no protection on the write to the NV area.
TPM_E_FAMILYCOUNT 0x80280040	The family count value does not match.
TPM_E_WRITE_LOCKED 0x80280041	The NV area has already been written to.
TPM_E_BAD_ATTRIBUTES 0x80280042	The NV area attributes conflict.
TPM_E_INVALID_STRUCTURE 0x80280043	The structure tag and version are invalid or inconsistent.
TPM_E_KEY_OWNER_CONTROL	The key is under control of the TPM owner and can only be

Value	Meaning
0x80280044	evicted by the TPM owner.
TPM_E_BAD_COUNTER 0x80280045	The counter handle is incorrect.
TPM_E_NOT_FULLWRITE 0x80280046	The write is not a complete write of the area.
TPM_E_CONTEXT_GAP 0x80280047	The gap between saved context counts is too large.
TPM_E_MAXNVWRITES 0x80280048	The maximum number of NV writes without an owner has been exceeded.
TPM_E_NOOPERATOR 0x80280049	No operator AuthData value is set.
TPM_E_RESOURCEMISSING 0x8028004A	The resource pointed to by context is not loaded.
TPM_E_DELEGATE_LOCK 0x8028004B	The delegate administration is locked.
TPM_E_DELEGATE_FAMILY 0x8028004C	Attempt to manage a family other than the delegated family.
TPM_E_DELEGATE_ADMIN 0x8028004D	Delegation table management not enabled.
TPM_E_TRANSPORT_NOTEXCLUSIVE 0x8028004E	There was a command executed outside an exclusive transport session.
TPM_E_OWNER_CONTROL 0x8028004F	Attempt to context save an owner evict controlled key.
TPM_E_DAA_RESOURCES 0x80280050	The DAA command has no resources available to execute the command.
TPM_E_DAA_INPUT_DATA0 0x80280051	The consistency check on DAA parameter inputData0 has failed.
TPM_E_DAA_INPUT_DATA1 0x80280052	The consistency check on DAA parameter inputData1 has failed.
TPM_E_DAA_ISSUER_SETTINGS 0x80280053	The consistency check on DAA_issuerSettings has failed.
TPM_E_DAA_TPM_SETTINGS 0x80280054	The consistency check on DAA_tpmSpecific has failed.

Value	Meaning
TPM_E_DAA_STAGE 0x80280055	The atomic process indicated by the submitted DAA command is not the expected process.
TPM_E_DAA_ISSUER_VALIDITY 0x80280056	The issuer's validity check has detected an inconsistency.
TPM_E_DAA_WRONG_W 0x80280057	The consistency check on w has failed.
TPM_E_BAD_HANDLE 0x80280058	The handle is incorrect.
TPM_E_BAD_DELEGATE 0x80280059	Delegation is not correct.
TPM_E_BADCONTEXT 0x8028005A	The context blob is invalid.
TPM_E_TOOMANYCONTEXTS 0x8028005B	Too many contexts held by the TPM.
TPM_E_MA_TICKET_SIGNATURE 0x8028005C	Migration authority signature validation failure.
TPM_E_MA_DESTINATION 0x8028005D	Migration destination not authenticated.
TPM_E_MA_SOURCE 0x8028005E	Migration source incorrect.
TPM_E_MA_AUTHORITY 0x8028005F	Incorrect migration authority.
TPM_E_PERMANENTEK 0x80280061	Attempt to revoke the EK and the EK is not revocable.
TPM_E_BAD_SIGNATURE 0x80280062	Bad signature of CMK ticket.
TPM_E_NOCONTEXTSPACE 0x80280063	There is no room in the context list for additional contexts.
TPM_E_COMMAND_BLOCKED 0x80280400	The command was blocked.
TPM_E_INVALID_HANDLE 0x80280401	The specified handle was not found.
TPM_E_DUPLICATE_VHANDLE 0x80280402	The TPM returned a duplicate handle and the command

Value	Meaning
	needs to be resubmitted.
TPM_E_EMBEDDED_COMMAND_BLOCKED 0x80280403	The command within the transport was blocked.
TPM_E_EMBEDDED_COMMAND_UNSUPPORTED 0x80280404	The command within the transport is not supported.
TPM_E_RETRY 0x80280800	The TPM is too busy to respond to the command immediately, but the command could be resubmitted at a later time.
TPM_E_NEEDS_SELFTEST 0x80280801	SelfTestFull has not been run.
TPM_E_DOING_SELFTEST 0x80280802	The TPM is currently executing a full self-test.
TPM_E_DEFEND_LOCK_RUNNING 0x80280803	The TPM is defending against dictionary attacks and is in a time-out period.
TBS_E_INTERNAL_ERROR 0x80284001	An internal software error has been detected.
TBS_E_BAD_PARAMETER 0x80284002	One or more input parameters are bad.
TBS_E_INVALID_OUTPUT_POINTER 0x80284003	A specified output pointer is bad.
TBS_E_INVALID_CONTEXT 0x80284004	The specified context handle does not refer to a valid context.
TBS_E_INSUFFICIENT_BUFFER 0x80284005	A specified output buffer is too small.
TBS_E_IOERROR 0x80284006	An error occurred while communicating with the TPM.
TBS_E_INVALID_CONTEXT_PARAM 0x80284007	One or more context parameters are invalid.
TBS_E_SERVICE_NOT_RUNNING 0x80284008	The TPM Base Services (TBS) is not running and could not be started.
TBS_E_TOO_MANY_TBS_CONTEXTS 0x80284009	A new context could not be created because there are too many open contexts.
TBS_E_TOO_MANY_RESOURCES	A new virtual resource could

Value	Meaning
0x8028400A	not be created because there are too many open virtual resources.
TBS_E_SERVICE_START_PENDING 0x8028400B	The TBS service has been started but is not yet running.
TBS_E_PPI_NOT_SUPPORTED 0x8028400C	The physical presence interface is not supported.
TBS_E_COMMAND_CANCELED 0x8028400D	The command was canceled.
TBS_E_BUFFER_TOO_LARGE 0x8028400E	The input or output buffer is too large.
TPMAPI_E_INVALID_STATE 0x80290100	The command buffer is not in the correct state.
TPMAPI_E_NOT_ENOUGH_DATA 0x80290101	The command buffer does not contain enough data to satisfy the request.
TPMAPI_E_TOO_MUCH_DATA 0x80290102	The command buffer cannot contain any more data.
TPMAPI_E_INVALID_OUTPUT_POINTER 0x80290103	One or more output parameters was null or invalid.
TPMAPI_E_INVALID_PARAMETER 0x80290104	One or more input parameters are invalid.
TPMAPI_E_OUT_OF_MEMORY 0x80290105	Not enough memory was available to satisfy the request.
TPMAPI_E_BUFFER_TOO_SMALL 0x80290106	The specified buffer was too small.
TPMAPI_E_INTERNAL_ERROR 0x80290107	An internal error was detected.
TPMAPI_E_ACCESS_DENIED 0x80290108	The caller does not have the appropriate rights to perform the requested operation.
TPMAPI_E_AUTHORIZATION_FAILED 0x80290109	The specified authorization information was invalid.
TPMAPI_E_INVALID_CONTEXT_HANDLE 0x8029010A	The specified context handle was not valid.
TPMAPI_E_TBS_COMMUNICATION_ERROR 0x8029010B	An error occurred while communicating with the TBS.

Value	Meaning
TPMAPI_E_TPM_COMMAND_ERROR 0x8029010C	The TPM returned an unexpected result.
TPMAPI_E_MESSAGE_TOO_LARGE 0x8029010D	The message was too large for the encoding scheme.
TPMAPI_E_INVALID_ENCODING 0x8029010E	The encoding in the binary large object (BLOB) was not recognized.
TPMAPI_E_INVALID_KEY_SIZE 0x8029010F	The key size is not valid.
TPMAPI_E_ENCRYPTION_FAILED 0x80290110	The encryption operation failed.
TPMAPI_E_INVALID_KEY_PARAMS 0x80290111	The key parameters structure was not valid.
TPMAPI_E_INVALID_MIGRATION_AUTHORIZATION_BLOB 0x80290112	The requested supplied data does not appear to be a valid migration authorization BLOB.
TPMAPI_E_INVALID_PCR_INDEX 0x80290113	The specified PCR index was invalid
TPMAPI_E_INVALID_DELEGATE_BLOB 0x80290114	The data given does not appear to be a valid delegate BLOB.
TPMAPI_E_INVALID_CONTEXT_PARAMS 0x80290115	One or more of the specified context parameters was not valid.
TPMAPI_E_INVALID_KEY_BLOB 0x80290116	The data given does not appear to be a valid key BLOB.
TPMAPI_E_INVALID_PCR_DATA 0x80290117	The specified PCR data was invalid.
TPMAPI_E_INVALID_OWNER_AUTH 0x80290118	The format of the owner authorization data was invalid.
TBSIMP_E_BUFFER_TOO_SMALL 0x80290200	The specified buffer was too small.
TBSIMP_E_CLEANUP_FAILED 0x80290201	The context could not be cleaned up.
TBSIMP_E_INVALID_CONTEXT_HANDLE 0x80290202	The specified context handle is invalid.
TBSIMP_E_INVALID_CONTEXT_PARAM	An invalid context parameter

Value	Meaning
0x80290203	was specified.
TBSIMP_E_TPM_ERROR 0x80290204	An error occurred while communicating with the TPM.
TBSIMP_E_HASH_BAD_KEY 0x80290205	No entry with the specified key was found.
TBSIMP_E_DUPLICATE_VHANDLE 0x80290206	The specified virtual handle matches a virtual handle already in use.
TBSIMP_E_INVALID_OUTPUT_POINTER 0x80290207	The pointer to the returned handle location was null or invalid.
TBSIMP_E_INVALID_PARAMETER 0x80290208	One or more parameters are invalid.
TBSIMP_E_RPC_INIT_FAILED 0x80290209	The RPC subsystem could not be initialized.
TBSIMP_E_SCHEDULER_NOT_RUNNING 0x8029020A	The TBS scheduler is not running.
TBSIMP_E_COMMAND_CANCELED 0x8029020B	The command was canceled.
TBSIMP_E_OUT_OF_MEMORY 0x8029020C	There was not enough memory to fulfill the request.
TBSIMP_E_LIST_NO_MORE_ITEMS 0x8029020D	The specified list is empty, or the iteration has reached the end of the list.
TBSIMP_E_LIST_NOT_FOUND 0x8029020E	The specified item was not found in the list.
TBSIMP_E_NOT_ENOUGH_SPACE 0x8029020F	The TPM does not have enough space to load the requested resource.
TBSIMP_E_NOT_ENOUGH_TPM_CONTEXTS 0x80290210	There are too many TPM contexts in use.
TBSIMP_E_COMMAND_FAILED 0x80290211	The TPM command failed.
TBSIMP_E_UNKNOWN_ORDINAL 0x80290212	The TBS does not recognize the specified ordinal.
TBSIMP_E_RESOURCE_EXPIRED 0x80290213	The requested resource is no longer available.

Value	Meaning
TBSIMP_E_INVALID_RESOURCE 0x80290214	The resource type did not match.
TBSIMP_E_NOTHING_TO_UNLOAD 0x80290215	No resources can be unloaded.
TBSIMP_E_HASH_TABLE_FULL 0x80290216	No new entries can be added to the hash table.
TBSIMP_E_TOO_MANY_TBS_CONTEXTS 0x80290217	A new TBS context could not be created because there are too many open contexts.
TBSIMP_E_TOO_MANY_RESOURCES 0x80290218	A new virtual resource could not be created because there are too many open virtual resources.
TBSIMP_E_PPI_NOT_SUPPORTED 0x80290219	The physical presence interface is not supported.
TBSIMP_E_TPM_INCOMPATIBLE 0x8029021A	TBS is not compatible with the version of TPM found on the system.
TPM_E_PPI_ACPI_FAILURE 0x80290300	A general error was detected when attempting to acquire the BIOS response to a physical presence command.
TPM_E_PPI_USER_ABORT 0x80290301	The user failed to confirm the TPM operation request.
TPM_E_PPI_BIOS_FAILURE 0x80290302	The BIOS failure prevented the successful execution of the requested TPM operation (for example, invalid TPM operation request, BIOS communication error with the TPM).
TPM_E_PPI_NOT_SUPPORTED 0x80290303	The BIOS does not support the physical presence interface.
PLA_E_DCS_NOT_FOUND 0x80300002	A Data Collector Set was not found.
PLA_E_TOO_MANY_FOLDERS 0x80300045	Unable to start Data Collector Set because there are too many folders.
PLA_E_NO_MIN_DISK 0x80300070	Not enough free disk space to start Data Collector Set.
PLA_E_DCS_IN_USE	Data Collector Set is in use.



Value	Meaning
0x803000AA	
PLA_E_DCS_ALREADY_EXISTS 0x803000B7	Data Collector Set already exists.
PLA_E_PROPERTY_CONFLICT 0x80300101	Property value conflict.
PLA_E_DCS_SINGLETON_REQUIRED 0x80300102	The current configuration for this Data Collector Set requires that it contain exactly one Data Collector.
PLA_E_CREDENTIALS_REQUIRED 0x80300103	A user account is required to commit the current Data Collector Set properties.
PLA_E_DCS_NOT_RUNNING 0x80300104	Data Collector Set is not running.
PLA_E_CONFLICT_INCL_EXCL_API 0x80300105	A conflict was detected in the list of include and exclude APIs. Do not specify the same API in both the include list and the exclude list.
PLA_E_NETWORK_EXE_NOT_VALID 0x80300106	The executable path specified refers to a network share or UNC path.
PLA_E_EXE_ALREADY_CONFIGURED 0x80300107	The executable path specified is already configured for API tracing.
PLA_E_EXE_PATH_NOT_VALID 0x80300108	The executable path specified does not exist. Verify that the specified path is correct.
PLA_E_DC_ALREADY_EXISTS 0x80300109	Data Collector already exists.
PLA_E_DCS_START_WAIT_TIMEOUT 0x8030010A	The wait for the Data Collector Set start notification has timed out.
PLA_E_DC_START_WAIT_TIMEOUT 0x8030010B	The wait for the Data Collector to start has timed out.
PLA_E_REPORT_WAIT_TIMEOUT 0x8030010C	The wait for the report generation tool to finish has timed out.
PLA_E_NO_DUPLICATES 0x8030010D	Duplicate items are not allowed.
PLA_E_EXE_FULL_PATH_REQUIRED	When specifying the

Value	Meaning
0x8030010E	executable to trace, you must specify a full path to the executable and not just a file name.
PLA_E_INVALID_SESSION_NAME 0x8030010F	The session name provided is invalid.
PLA_E_PLA_CHANNEL_NOT_ENABLED 0x80300110	The Event Log channel Microsoft-Windows-Diagnosis-PLA/Operational must be enabled to perform this operation.
PLA_E_TASKSCHED_CHANNEL_NOT_ENABLED 0x80300111	The Event Log channel Microsoft-Windows-TaskScheduler must be enabled to perform this operation.
FVE_E_LOCKED_VOLUME 0x80310000	The volume must be unlocked before it can be used.
FVE_E_NOT_ENCRYPTED 0x80310001	The volume is fully decrypted and no key is available.
FVE_E_NO_TPM_BIOS 0x80310002	The firmware does not support using a TPM during boot.
FVE_E_NO_MBR_METRIC 0x80310003	The firmware does not use a TPM to perform initial program load (IPL) measurement.
FVE_E_NO_BOOTSECTOR_METRIC 0x80310004	The master boot record (MBR) is not TPM-aware.
FVE_E_NO_BOOTMGR_METRIC 0x80310005	The BOOTMGR is not being measured by the TPM.
FVE_E_WRONG_BOOTMGR 0x80310006	The BOOTMGR component does not perform expected TPM measurements.
FVE_E_SECURE_KEY_REQUIRED 0x80310007	No secure key protection mechanism has been defined.
FVE_E_NOT_ACTIVATED 0x80310008	This volume has not been provisioned for encryption.
FVE_E_ACTION_NOT_ALLOWED 0x80310009	Requested action was denied by the full-volume encryption (FVE) control engine.
FVE_E_AD_SCHEMA_NOT_INSTALLED 0x8031000A	The Active Directory forest does not contain the required attributes and classes to host

Value	Meaning
	FVE or TPM information.
FVE_E_AD_INVALID_DATATYPE 0x8031000B	The type of data obtained from Active Directory was not expected.
FVE_E_AD_INVALID_DATASIZE 0x8031000C	The size of the data obtained from Active Directory was not expected.
FVE_E_AD_NO_VALUES 0x8031000D	The attribute read from Active Directory has no (zero) values.
FVE_E_AD_ATTR_NOT_SET 0x8031000E	The attribute was not set.
FVE_E_AD_GUID_NOT_FOUND 0x8031000F	The specified GUID could not be found.
FVE_E_BAD_INFORMATION 0x80310010	The control block for the encrypted volume is not valid.
FVE_E_TOO_SMALL 0x80310011	Not enough free space remaining on volume to allow encryption.
FVE_E_SYSTEM_VOLUME 0x80310012	The volume cannot be encrypted because it is required to boot the operating system.
FVE_E_FAILED_WRONG_FS 0x80310013	The volume cannot be encrypted because the file system is not supported.
FVE_E_FAILED_BAD_FS 0x80310014	The file system is inconsistent. Run CHKDSK.
FVE_E_NOT_SUPPORTED 0x80310015	This volume cannot be encrypted.
FVE_E_BAD_DATA 0x80310016	Data supplied is malformed.
FVE_E_VOLUME_NOT_BOUND 0x80310017	Volume is not bound to the system.
FVE_E_TPM_NOT_OWNED 0x80310018	TPM must be owned before a volume can be bound to it.
FVE_E_NOT_DATA_VOLUME 0x80310019	The volume specified is not a data volume.
FVE_E_AD_INSUFFICIENT_BUFFER	The buffer supplied to a function was insufficient to

Value	Meaning
0x8031001A	contain the returned data.
FVE_E_CONV_READ 0x8031001B	A read operation failed while converting the volume.
FVE_E_CONV_WRITE 0x8031001C	A write operation failed while converting the volume.
FVE_E_KEY_REQUIRED 0x8031001D	One or more key protection mechanisms are required for this volume.
FVE_E_CLUSTERING_NOT_SUPPORTED 0x8031001E	Cluster configurations are not supported.
FVE_E_VOLUME_BOUND_ALREADY 0x8031001F	The volume is already bound to the system.
FVE_E_OS_NOT_PROTECTED 0x80310020	The boot OS volume is not being protected via FVE.
FVE_E_PROTECTION_DISABLED 0x80310021	All protection mechanisms are effectively disabled (clear key exists).
FVE_E_RECOVERY_KEY_REQUIRED 0x80310022	A recovery key protection mechanism is required.
FVE_E_FOREIGN_VOLUME 0x80310023	This volume cannot be bound to a TPM.
FVE_E_OVERLAPPED_UPDATE 0x80310024	The control block for the encrypted volume was updated by another thread. Try again.
FVE_E_TPM_SRK_AUTH_NOT_ZERO 0x80310025	The SRK authentication of the TPM is not zero and, therefore, is not compatible.
FVE_E_FAILED_SECTOR_SIZE 0x80310026	The volume encryption algorithm cannot be used on this sector size.
FVE_E_FAILED_AUTHENTICATION 0x80310027	BitLocker recovery authentication failed.
FVE_E_NOT_OS_VOLUME 0x80310028	The volume specified is not the boot OS volume.
FVE_E_AUTOUNLOCK_ENABLED 0x80310029	Auto-unlock information for data volumes is present on the boot OS volume.
FVE_E_WRONG_BOOTSECTOR	The system partition boot sector does not perform TPM

Value	Meaning
0x8031002A	measurements.
FVE_E_WRONG_SYSTEM_FS 0x8031002B	The system partition file system must be NTFS.
FVE_E_POLICY_PASSWORD_REQUIRED 0x8031002C	Group policy requires a recovery password before encryption may begin.
FVE_E_CANNOT_SET_FVEK_ENCRYPTED 0x8031002D	The volume encryption algorithm and key cannot be set on an encrypted volume.
FVE_E_CANNOT_ENCRYPT_NO_KEY 0x8031002E	A key must be specified before encryption may begin.
FVE_E_BOOTABLE_CDDVD 0x80310030	A bootable CD/DVD is in the system. Remove the CD/DVD and reboot the system.
FVE_E_PROTECTOR_EXISTS 0x80310031	An instance of this key protector already exists on the volume.
FVE_E_RELATIVE_PATH 0x80310032	The file cannot be saved to a relative path.
FWP_E_CALLOUT_NOT_FOUND 0x80320001	The callout does not exist.
FWP_E_CONDITION_NOT_FOUND 0x80320002	The filter condition does not exist.
FWP_E_FILTER_NOT_FOUND 0x80320003	The filter does not exist.
FWP_E_LAYER_NOT_FOUND 0x80320004	The layer does not exist.
FWP_E_PROVIDER_NOT_FOUND 0x80320005	The provider does not exist.
FWP_E_PROVIDER_CONTEXT_NOT_FOUND 0x80320006	The provider context does not exist.
FWP_E_SUBLAYER_NOT_FOUND 0x80320007	The sublayer does not exist.
FWP_E_NOT_FOUND 0x80320008	The object does not exist.
FWP_E_ALREADY_EXISTS 0x80320009	An object with that GUID or LUID already exists.

Value	Meaning
FWP_E_IN_USE 0x8032000A	The object is referenced by other objects and, therefore, cannot be deleted.
FWP_E_DYNAMIC_SESSION_IN_PROGRESS 0x8032000B	The call is not allowed from within a dynamic session.
FWP_E_WRONG_SESSION 0x8032000C	The call was made from the wrong session and, therefore, cannot be completed.
FWP_E_NO_TXN_IN_PROGRESS 0x8032000D	The call must be made from within an explicit transaction.
FWP_E_TXN_IN_PROGRESS 0x8032000E	The call is not allowed from within an explicit transaction.
FWP_E_TXN_ABORTED 0x8032000F	The explicit transaction has been forcibly canceled.
FWP_E_SESSION_ABORTED 0x80320010	The session has been canceled.
FWP_E_INCOMPATIBLE_TXN 0x80320011	The call is not allowed from within a read-only transaction.
FWP_E_TIMEOUT 0x80320012	The call timed out while waiting to acquire the transaction lock.
FWP_E_NET_EVENTS_DISABLED 0x80320013	Collection of network diagnostic events is disabled.
FWP_E_INCOMPATIBLE_LAYER 0x80320014	The operation is not supported by the specified layer.
FWP_E_KM_CLIENTS_ONLY 0x80320015	The call is allowed for kernel-mode callers only.
FWP_E_LIFETIME_MISMATCH 0x80320016	The call tried to associate two objects with incompatible lifetimes.
FWP_E_BUILTIN_OBJECT 0x80320017	The object is built in and, therefore, cannot be deleted.
FWP_E_TOO_MANY_BOOTTIME_FILTERS 0x80320018	The maximum number of boot-time filters has been reached.
FWP_E_NOTIFICATION_DROPPED 0x80320019	A notification could not be delivered because a message queue is at its maximum capacity.

Value	Meaning
FWP_E_TRAFFIC_MISMATCH 0x8032001A	The traffic parameters do not match those for the security association context.
FWP_E_INCOMPATIBLE_SA_STATE 0x8032001B	The call is not allowed for the current security association state.
FWP_E_NULL_POINTER 0x8032001C	A required pointer is null.
FWP_E_INVALID_ENUMERATOR 0x8032001D	An enumerator is not valid.
FWP_E_INVALID_FLAGS 0x8032001E	The flags field contains an invalid value.
FWP_E_INVALID_NET_MASK 0x8032001F	A network mask is not valid.
FWP_E_INVALID_RANGE 0x80320020	An FWP_RANGE is not valid.
FWP_E_INVALID_INTERVAL 0x80320021	The time interval is not valid.
FWP_E_ZERO_LENGTH_ARRAY 0x80320022	An array that must contain at least one element that is zero-length.
FWP_E_NULL_DISPLAY_NAME 0x80320023	The <b>displayData.name</b> field cannot be null.
FWP_E_INVALID_ACTION_TYPE 0x80320024	The action type is not one of the allowed action types for a filter.
FWP_E_INVALID_WEIGHT 0x80320025	The filter weight is not valid.
FWP_E_MATCH_TYPE_MISMATCH 0x80320026	A filter condition contains a match type that is not compatible with the operands.
FWP_E_TYPE_MISMATCH 0x80320027	An FWP_VALUE or FWPM_CONDITION_VALUE is of the wrong type.
FWP_E_OUT_OF_BOUNDS 0x80320028	An integer value is outside the allowed range.
FWP_E_RESERVED 0x80320029	A reserved field is nonzero.
FWP_E_DUPLICATE_CONDITION	A filter cannot contain multiple

Value	Meaning
0x8032002A	conditions operating on a single field.
FWP_E_DUPLICATE_KEYMOD 0x8032002B	A policy cannot contain the same keying module more than once.
FWP_E_ACTION_INCOMPATIBLE_WITH_LAYER 0x8032002C	The action type is not compatible with the layer.
FWP_E_ACTION_INCOMPATIBLE_WITH_SUBLAYER 0x8032002D	The action type is not compatible with the sublayer.
FWP_E_CONTEXT_INCOMPATIBLE_WITH_LAYER 0x8032002E	The raw context or the provider context is not compatible with the layer.
FWP_E_CONTEXT_INCOMPATIBLE_WITH_CALLOUT 0x8032002F	The raw context or the provider context is not compatible with the callout.
FWP_E_INCOMPATIBLE_AUTH_METHOD 0x80320030	The authentication method is not compatible with the policy type.
FWP_E_INCOMPATIBLE_DH_GROUP 0x80320031	The Diffie-Hellman group is not compatible with the policy type.
FWP_E_EM_NOT_SUPPORTED 0x80320032	An Internet Key Exchange (IKE) policy cannot contain an Extended Mode policy.
FWP_E_NEVER_MATCH 0x80320033	The enumeration template or subscription will never match any objects.
FWP_E_PROVIDER_CONTEXT_MISMATCH 0x80320034	The provider context is of the wrong type.
FWP_E_INVALID_PARAMETER 0x80320035	The parameter is incorrect.
FWP_E_TOO_MANY_SUBLAYERS 0x80320036	The maximum number of sublayers has been reached.
FWP_E_CALLOUT_NOTIFICATION_FAILED 0x80320037	The notification function for a callout returned an error.
FWP_E_INCOMPATIBLE_AUTH_CONFIG 0x80320038	The IPsec authentication configuration is not compatible with the authentication type.
FWP_E_INCOMPATIBLE_CIPHER_CONFIG 0x80320039	The IPsec cipher configuration is not compatible with the cipher type.



Value	Meaning
ERROR_NDIS_INTERFACE_CLOSING 0x80340002	The binding to the network interface is being closed.
ERROR_NDIS_BAD_VERSION 0x80340004	An invalid version was specified.
ERROR_NDIS_BAD_CHARACTERISTICS 0x80340005	An invalid characteristics table was used.
ERROR_NDIS_ADAPTER_NOT_FOUND 0x80340006	Failed to find the network interface, or the network interface is not ready.
ERROR_NDIS_OPEN_FAILED 0x80340007	Failed to open the network interface.
ERROR_NDIS_DEVICE_FAILED 0x80340008	The network interface has encountered an internal unrecoverable failure.
ERROR_NDIS_MULTICAST_FULL 0x80340009	The multicast list on the network interface is full.
ERROR_NDIS_MULTICAST_EXISTS 0x8034000A	An attempt was made to add a duplicate multicast address to the list.
ERROR_NDIS_MULTICAST_NOT_FOUND 0x8034000B	At attempt was made to remove a multicast address that was never added.
ERROR_NDIS_REQUEST_ABORTED 0x8034000C	The network interface aborted the request.
ERROR_NDIS_RESET_IN_PROGRESS 0x8034000D	The network interface cannot process the request because it is being reset.
ERROR_NDIS_INVALID_PACKET 0x8034000F	An attempt was made to send an invalid packet on a network interface.
ERROR_NDIS_INVALID_DEVICE_REQUEST 0x80340010	The specified request is not a valid operation for the target device.
ERROR_NDIS_ADAPTER_NOT_READY 0x80340011	The network interface is not ready to complete this operation.
ERROR_NDIS_INVALID_LENGTH 0x80340014	The length of the buffer submitted for this operation is not valid.
ERROR_NDIS_INVALID_DATA 0x80340015	The data used for this operation is not valid.

Value	Meaning
ERROR_NDIS_BUFFER_TOO_SHORT 0x80340016	The length of the buffer submitted for this operation is too small.
ERROR_NDIS_INVALID_OID 0x80340017	The network interface does not support this OID.
ERROR_NDIS_ADAPTER_REMOVED 0x80340018	The network interface has been removed.
ERROR_NDIS_UNSUPPORTED_MEDIA 0x80340019	The network interface does not support this media type.
ERROR_NDIS_GROUP_ADDRESS_IN_USE 0x8034001A	An attempt was made to remove a token ring group address that is in use by other components.
ERROR_NDIS_FILE_NOT_FOUND 0x8034001B	An attempt was made to map a file that cannot be found.
ERROR_NDIS_ERROR_READING_FILE 0x8034001C	An error occurred while the NDIS tried to map the file.
ERROR_NDIS_ALREADY_MAPPED 0x8034001D	An attempt was made to map a file that is already mapped.
ERROR_NDIS_RESOURCE_CONFLICT 0x8034001E	An attempt to allocate a hardware resource failed because the resource is used by another component.
ERROR_NDIS_MEDIA_DISCONNECTED 0x8034001F	The I/O operation failed because network media is disconnected or the wireless access point is out of range.
ERROR_NDIS_INVALID_ADDRESS 0x80340022	The network address used in the request is invalid.
ERROR_NDIS_PAUSED 0x8034002A	The offload operation on the network interface has been paused.
ERROR_NDIS_INTERFACE_NOT_FOUND 0x8034002B	The network interface was not found.
ERROR_NDIS_UNSUPPORTED_REVISION 0x8034002C	The revision number specified in the structure is not supported.
ERROR_NDIS_INVALID_PORT 0x8034002D	The specified port does not exist on this network interface.

Value	Meaning
ERROR_NDIS_INVALID_PORT_STATE 0x8034002E	The current state of the specified port on this network interface does not support the requested operation.
ERROR_NDIS_NOT_SUPPORTED 0x803400BB	The network interface does not support this request.
ERROR_NDIS_DOT11_AUTO_CONFIG_ENABLED 0x80342000	The wireless local area network (LAN) interface is in auto-configuration mode and does not support the requested parameter change operation.
ERROR_NDIS_DOT11_MEDIA_IN_USE 0x80342001	The wireless LAN interface is busy and cannot perform the requested operation.
ERROR_NDIS_DOT11_POWER_STATE_INVALID 0x80342002	The wireless LAN interface is shutting down and does not support the requested operation.
TRK_E_NOT_FOUND 0x8DEAD01B	A requested object was not found.
TRK_E_VOLUME_QUOTA_EXCEEDED 0x8DEAD01C	The server received a CREATE_VOLUME subrequest of a SYNC_VOLUMES request, but the ServerVolumeTable size limit for the RequestMachine has already been reached.
TRK_SERVER_TOO_BUSY 0x8DEAD01E	The server is busy, and the client should retry the request at a later time.
ERROR_AUDITING_DISABLED 0xC0090001	The specified event is currently not being audited.
ERROR_ALL_SIDS_FILTERED 0xC0090002	The SID filtering operation removed all SIDs.
ERROR_BIZRULES_NOT_ENABLED 0xC0090003	Business rule scripts are disabled for the calling application.
NS_E_NOCONNECTION 0xC00D0005L	There is no connection established with the Windows Media server. The operation failed.
NS_E_CANNOTCONNECT 0xC00D0006L	Unable to establish a connection to the server.

Value	Meaning
NS_E_CANNOTDESTROYTITLE 0xC00D0007L	Unable to destroy the title.
NS_E_CANNOTRENAMETITLE 0xC00D0008L	Unable to rename the title.
NS_E_CANNOTOFFLINEDISK 0xC00D0009L	Unable to offline disk.
NS_E_CANNOTONLINEDISK 0xC00D000AL	Unable to online disk.
NS_E_NOREGISTEREDWALKER 0xC00D000BL	There is no file parser registered for this type of file.
NS_E_NOFUNNEL 0xC00D000CL	There is no data connection established.
NS_E_NO_LOCALPLAY 0xC00D000DL	Failed to load the local play DLL.
NS_E_NETWORK_BUSY 0xC00D000EL	The network is busy.
NS_E_TOO_MANY_SESS 0xC00D000FL	The server session limit was exceeded.
NS_E_ALREADY_CONNECTED 0xC00D0010L	The network connection already exists.
NS_E_INVALID_INDEX 0xC00D0011L	Index %1 is invalid.
NS_E_PROTOCOL_MISMATCH 0xC00D0012L	There is no protocol or protocol version supported by both the client and the server.
NS_E_TIMEOUT 0xC00D0013L	The server, a computer set up to offer multimedia content to other computers, could not handle your request for multimedia content in a timely manner. Please try again later.
NS_E_NET_WRITE 0xC00D0014L	Error writing to the network.
NS_E_NET_READ 0xC00D0015L	Error reading from the network.
NS_E_DISK_WRITE 0xC00D0016L	Error writing to a disk.

Value	Meaning
NS_E_DISK_READ 0xC00D0017L	Error reading from a disk.
NS_E_FILE_WRITE 0xC00D0018L	Error writing to a file.
NS_E_FILE_READ 0xC00D0019L	Error reading from a file.
NS_E_FILE_NOT_FOUND 0xC00D001AL	The system cannot find the file specified.
NS_E_FILE_EXISTS 0xC00D001BL	The file already exists.
NS_E_INVALID_NAME 0xC00D001CL	The file name, directory name, or volume label syntax is incorrect.
NS_E_FILE_OPEN_FAILED 0xC00D001DL	Failed to open a file.
NS_E_FILE_ALLOCATION_FAILED 0xC00D001EL	Unable to allocate a file.
NS_E_FILE_INIT_FAILED 0xC00D001FL	Unable to initialize a file.
NS_E_FILE_PLAY_FAILED 0xC00D0020L	Unable to play a file.
NS_E_SET_DISK_UID_FAILED 0xC00D0021L	Could not set the disk UID.
NS_E_INDUCED 0xC00D0022L	An error was induced for testing purposes.
NS_E_CCLINK_DOWN 0xC00D0023L	Two Content Servers failed to communicate.
NS_E_INTERNAL 0xC00D0024L	An unknown error occurred.
NS_E_BUSY 0xC00D0025L	The requested resource is in use.
NS_E_UNRECOGNIZED_STREAM_TYPE 0xC00D0026L	The specified protocol is not recognized. Be sure that the file name and syntax, such as slashes, are correct for the protocol.
NS_E_NETWORK_SERVICE_FAILURE	The network service provider

Value	Meaning
0xC00D0027L	failed.
NS_E_NETWORK_RESOURCE_FAILURE 0xC00D0028L	An attempt to acquire a network resource failed.
NS_E_CONNECTION_FAILURE 0xC00D0029L	The network connection has failed.
NS_E_SHUTDOWN 0xC00D002AL	The session is being terminated locally.
NS_E_INVALID_REQUEST 0xC00D002BL	The request is invalid in the current state.
NS_E_INSUFFICIENT_BANDWIDTH 0xC00D002CL	There is insufficient bandwidth available to fulfill the request.
NS_E_NOT_REBUILDING 0xC00D002DL	The disk is not rebuilding.
NS_E_LATE_OPERATION 0xC00D002EL	An operation requested for a particular time could not be carried out on schedule.
NS_E_INVALID_DATA 0xC00D002FL	Invalid or corrupt data was encountered.
NS_E_FILE_BANDWIDTH_LIMIT 0xC00D0030L	The bandwidth required to stream a file is higher than the maximum file bandwidth allowed on the server.
NS_E_OPEN_FILE_LIMIT 0xC00D0031L	The client cannot have any more files open simultaneously.
NS_E_BAD_CONTROL_DATA 0xC00D0032L	The server received invalid data from the client on the control connection.
NS_E_NO_STREAM 0xC00D0033L	There is no stream available.
NS_E_STREAM_END 0xC00D0034L	There is no more data in the stream.
NS_E_SERVER_NOT_FOUND 0xC00D0035L	The specified server could not be found.
NS_E_DUPLICATE_NAME 0xC00D0036L	The specified name is already in use.
NS_E_DUPLICATE_ADDRESS 0xC00D0037L	The specified address is already in use.

Value	Meaning
NS_E_BAD_MULTICAST_ADDRESS 0xC00D0038L	The specified address is not a valid multicast address.
NS_E_BAD_ADAPTER_ADDRESS 0xC00D0039L	The specified adapter address is invalid.
NS_E_BAD_DELIVERY_MODE 0xC00D003AL	The specified delivery mode is invalid.
NS_E_INVALID_CHANNEL 0xC00D003BL	The specified station does not exist.
NS_E_INVALID_STREAM 0xC00D003CL	The specified stream does not exist.
NS_E_INVALID_ARCHIVE 0xC00D003DL	The specified archive could not be opened.
NS_E_NOTITLES 0xC00D003EL	The system cannot find any titles on the server.
NS_E_INVALID_CLIENT 0xC00D003FL	The system cannot find the client specified.
NS_E_INVALID_BLACKHOLE_ADDRESS 0xC00D0040L	The Blackhole Address is not initialized.
NS_E_INCOMPATIBLE_FORMAT 0xC00D0041L	The station does not support the stream format.
NS_E_INVALID_KEY 0xC00D0042L	The specified key is not valid.
NS_E_INVALID_PORT 0xC00D0043L	The specified port is not valid.
NS_E_INVALID_TTL 0xC00D0044L	The specified TTL is not valid.
NS_E_STRIDE_REFUSED 0xC00D0045L	The request to fast forward or rewind could not be fulfilled.
NS_E_MMSAUTOSERVER_CANTFINDWALKER 0xC00D0046L	Unable to load the appropriate file parser.
NS_E_MAX_BITRATE 0xC00D0047L	Cannot exceed the maximum bandwidth limit.
NS_E_LOGFILEPERIOD 0xC00D0048L	Invalid value for LogFilePeriod.
NS_E_MAX_CLIENTS	Cannot exceed the maximum client limit.

Value	Meaning
0xC00D0049L	
NS_E_LOG_FILE_SIZE 0xC00D004AL	The maximum log file size has been reached.
NS_E_MAX_FILERATE 0xC00D004BL	Cannot exceed the maximum file rate.
NS_E_WALKER_UNKNOWN 0xC00D004CL	Unknown file type.
NS_E_WALKER_SERVER 0xC00D004DL	The specified file, %1, cannot be loaded onto the specified server, %2.
NS_E_WALKER_USAGE 0xC00D004EL	There was a usage error with file parser.
NS_E_TIGER_FAIL 0xC00D0050L	The Title Server %1 has failed.
NS_E_CUB_FAIL 0xC00D0053L	Content Server %1 (%2) has failed.
NS_E_DISK_FAIL 0xC00D0055L	Disk %1 ( %2 ) on Content Server %3, has failed.
NS_E_MAX_FUNNELS_ALERT 0xC00D0060L	The NetShow data stream limit of %1 streams was reached.
NS_E_ALLOCATE_FILE_FAIL 0xC00D0061L	The NetShow Video Server was unable to allocate a %1 block file named %2.
NS_E_PAGING_ERROR 0xC00D0062L	A Content Server was unable to page a block.
NS_E_BAD_BLOCK0_VERSION 0xC00D0063L	Disk %1 has unrecognized control block version %2.
NS_E_BAD_DISK_UID 0xC00D0064L	Disk %1 has incorrect uid %2.
NS_E_BAD_FSMAJOR_VERSION 0xC00D0065L	Disk %1 has unsupported file system major version %2.
NS_E_BAD_STAMPNUMBER 0xC00D0066L	Disk %1 has bad stamp number in control block.
NS_E_PARTIALLY_REBUILT_DISK 0xC00D0067L	Disk %1 is partially reconstructed.
NS_E_ENACTPLAN_GIVEUP	EnactPlan gives up.



Value	Meaning
0xC00D0068L	
MCMADM_E_REGKEY_NOT_FOUND 0xC00D006AL	The key was not found in the registry.
NS_E_NO_FORMATS 0xC00D006BL	The publishing point cannot be started because the server does not have the appropriate stream formats. Use the Multicast Announcement Wizard to create a new announcement for this publishing point.
NS_E_NO_REFERENCES 0xC00D006CL	No reference URLs were found in an ASX file.
NS_E_WAVE_OPEN 0xC00D006DL	Error opening wave device, the device might be in use.
NS_E_CANNOTCONNECTEVENTS 0xC00D006FL	Unable to establish a connection to the NetShow event monitor service.
NS_E_NO_DEVICE 0xC00D0071L	No device driver is present on the system.
NS_E_NO_SPECIFIED_DEVICE 0xC00D0072L	No specified device driver is present.
NS_E_MONITOR_GIVEUP 0xC00D00C8L	Netshow Events Monitor is not operational and has been disconnected.
NS_E_REMIRRORED_DISK 0xC00D00C9L	Disk %1 is remirrored.
NS_E_INSUFFICIENT_DATA 0xC00D00CAL	Insufficient data found.
NS_E_ASSERT 0xC00D00CBL	1 failed in file %2 line %3.
NS_E_BAD_ADAPTER_NAME 0xC00D00CCL	The specified adapter name is invalid.
NS_E_NOT_LICENSED 0xC00D00CDL	The application is not licensed for this feature.
NS_E_NO_SERVER_CONTACT 0xC00D00CEL	Unable to contact the server.
NS_E_TOO_MANY_TITLES 0xC00D00CFL	Maximum number of titles exceeded.

Value	Meaning
NS_E_TITLE_SIZE_EXCEEDED 0xC00D00D0L	Maximum size of a title exceeded.
NS_E_UDP_DISABLED 0xC00D00D1L	UDP protocol not enabled. Not trying %1!s!.
NS_E_TCP_DISABLED 0xC00D00D2L	TCP protocol not enabled. Not trying %1!s!.
NS_E_HTTP_DISABLED 0xC00D00D3L	HTTP protocol not enabled. Not trying %1!s!.
NS_E_LICENSE_EXPIRED 0xC00D00D4L	The product license has expired.
NS_E_TITLE_BITRATE 0xC00D00D5L	Source file exceeds the per title maximum bitrate. See NetShow Theater documentation for more information.
NS_E_EMPTY_PROGRAM_NAME 0xC00D00D6L	The program name cannot be empty.
NS_E_MISSING_CHANNEL 0xC00D00D7L	Station %1 does not exist.
NS_E_NO_CHANNELS 0xC00D00D8L	You need to define at least one station before this operation can complete.
NS_E_INVALID_INDEX2 0xC00D00D9L	The index specified is invalid.
NS_E_CUB_FAIL_LINK 0xC00D0190L	Content Server %1 (%2) has failed its link to Content Server %3.
NS_E_BAD_CUB_UID 0xC00D0192L	Content Server %1 (%2) has incorrect uid %3.
NS_E_GLITCH_MODE 0xC00D0195L	Server unreliable because multiple components failed.
NS_E_NO_MEDIA_PROTOCOL 0xC00D019BL	Content Server %1 (%2) is unable to communicate with the Media System Network Protocol.
NS_E_NOTHING_TO_DO 0xC00D07F1L	Nothing to do.
NS_E_NO_MULTICAST 0xC00D07F2L	Not receiving data from the server.

Value	Meaning
NS_E_INVALID_INPUT_FORMAT 0xC00D0BB8L	The input media format is invalid.
NS_E_MSAUDIO_NOT_INSTALLED 0xC00D0BB9L	The MSAudio codec is not installed on this system.
NS_E_UNEXPECTED_MSAUDIO_ERROR 0xC00D0BBAL	An unexpected error occurred with the MSAudio codec.
NS_E_INVALID_OUTPUT_FORMAT 0xC00D0BBBL	The output media format is invalid.
NS_E_NOT_CONFIGURED 0xC00D0BBCL	The object must be fully configured before audio samples can be processed.
NS_E_PROTECTED_CONTENT 0xC00D0BBDL	You need a license to perform the requested operation on this media file.
NS_E_LICENSE_REQUIRED 0xC00D0BBEL	You need a license to perform the requested operation on this media file.
NS_E_TAMPERED_CONTENT 0xC00D0BBFL	This media file is corrupted or invalid. Contact the content provider for a new file.
NS_E_LICENSE_OUTOFDATE 0xC00D0BC0L	The license for this media file has expired. Get a new license or contact the content provider for further assistance.
NS_E_LICENSE_INCORRECT_RIGHTS 0xC00D0BC1L	You are not allowed to open this file. Contact the content provider for further assistance.
NS_E_AUDIO_CODEC_NOT_INSTALLED 0xC00D0BC2L	The requested audio codec is not installed on this system.
NS_E_AUDIO_CODEC_ERROR 0xC00D0BC3L	An unexpected error occurred with the audio codec.
NS_E_VIDEO_CODEC_NOT_INSTALLED 0xC00D0BC4L	The requested video codec is not installed on this system.
NS_E_VIDEO_CODEC_ERROR 0xC00D0BC5L	An unexpected error occurred with the video codec.
NS_E_INVALIDPROFILE 0xC00D0BC6L	The Profile is invalid.
NS_E_INCOMPATIBLE_VERSION 0xC00D0BC7L	A new version of the SDK is needed to play the requested content.

Value	Meaning
NS_E_OFFLINE_MODE 0xC00D0BCAL	The requested URL is not available in offline mode.
NS_E_NOT_CONNECTED 0xC00D0BCBL	The requested URL cannot be accessed because there is no network connection.
NS_E_TOO_MUCH_DATA 0xC00D0BCCL	The encoding process was unable to keep up with the amount of supplied data.
NS_E_UNSUPPORTED_PROPERTY 0xC00D0BCDL	The given property is not supported.
NS_E_8BIT_WAVE_UNSUPPORTED 0xC00D0BCEL	Windows Media Player cannot copy the files to the CD because they are 8-bit. Convert the files to 16-bit, 44-kHz stereo files by using Sound Recorder or another audio-processing program, and then try again.
NS_E_NO_MORE_SAMPLES 0xC00D0BCFL	There are no more samples in the current range.
NS_E_INVALID_SAMPLING_RATE 0xC00D0BD0L	The given sampling rate is invalid.
NS_E_MAX_PACKET_SIZE_TOO_SMALL 0xC00D0BD1L	The given maximum packet size is too small to accommodate this profile.)
NS_E_LATE_PACKET 0xC00D0BD2L	The packet arrived too late to be of use.
NS_E_DUPLICATE_PACKET 0xC00D0BD3L	The packet is a duplicate of one received before.
NS_E_SDK_BUFFERTOOSMALL 0xC00D0BD4L	Supplied buffer is too small.
NS_E_INVALID_NUM_PASSES 0xC00D0BD5L	The wrong number of preprocessing passes was used for the stream's output type.
NS_E_ATTRIBUTE_READ_ONLY 0xC00D0BD6L	An attempt was made to add, modify, or delete a read only attribute.
NS_E_ATTRIBUTE_NOT_ALLOWED 0xC00D0BD7L	An attempt was made to add attribute that is not allowed for the given media type.

Value	Meaning
NS_E_INVALID_EDL 0xC00D0BD8L	The EDL provided is invalid.
NS_E_DATA_UNIT_EXTENSION_TOO_LARGE 0xC00D0BD9L	The Data Unit Extension data was too large to be used.
NS_E_CODEC_DMO_ERROR 0xC00D0BDAL	An unexpected error occurred with a DMO codec.
NS_E_FEATURE_DISABLED_BY_GROUP_POLICY 0xC00D0BDCL	This feature has been disabled by group policy.
NS_E_FEATURE_DISABLED_IN_SKU 0xC00D0BDDL	This feature is disabled in this SKU.
NS_E_NO_CD 0xC00D0FA0L	There is no CD in the CD drive. Insert a CD, and then try again.
NS_E_CANT_READ_DIGITAL 0xC00D0FA1L	Windows Media Player could not use digital playback to play the CD. To switch to analog playback, on the Tools menu, click Options, and then click the Devices tab. Double-click the CD drive, and then in the Playback area, click Analog. For additional assistance, click Web Help.
NS_E_DEVICE_DISCONNECTED 0xC00D0FA2L	Windows Media Player no longer detects a connected portable device. Reconnect your portable device, and then try synchronizing the file again.
NS_E_DEVICE_NOT_SUPPORT_FORMAT 0xC00D0FA3L	Windows Media Player cannot play the file. The portable device does not support the specified file type.
NS_E_SLOW_READ_DIGITAL 0xC00D0FA4L	Windows Media Player could not use digital playback to play the CD. The Player has automatically switched the CD drive to analog playback. To switch back to digital CD playback, use the Devices tab. For additional assistance, click Web Help.
NS_E_MIXER_INVALID_LINE 0xC00D0FA5L	An invalid line error occurred in the mixer.
NS_E_MIXER_INVALID_CONTROL	An invalid control error

Value	Meaning
0xC00D0FA6L	occurred in the mixer.
NS_E_MIXER_INVALID_VALUE 0xC00D0FA7L	An invalid value error occurred in the mixer.
NS_E_MIXER_UNKNOWN_MMRESULT 0xC00D0FA8L	An unrecognized MMRESULT occurred in the mixer.
NS_E_USER_STOP 0xC00D0FA9L	User has stopped the operation.
NS_E_MP3_FORMAT_NOT_FOUND 0xC00D0FAAL	Windows Media Player cannot rip the track because a compatible MP3 encoder is not installed on your computer. Install a compatible MP3 encoder or choose a different format to rip to (such as Windows Media Audio).
NS_E_CD_READ_ERROR_NO_CORRECTION 0xC00D0FABL	Windows Media Player cannot read the CD. The disc might be dirty or damaged. Turn on error correction, and then try again.
NS_E_CD_READ_ERROR 0xC00D0FACL	Windows Media Player cannot read the CD. The disc might be dirty or damaged or the CD drive might be malfunctioning.
NS_E_CD_SLOW_COPY 0xC00D0FADL	For best performance, do not play CD tracks while ripping them.
NS_E_CD_COPYTO_CD 0xC00D0FAEL	It is not possible to directly burn tracks from one CD to another CD. You must first rip the tracks from the CD to your computer, and then burn the files to a blank CD.
NS_E_MIXER_NODRIVER 0xC00D0FAFL	Could not open a sound mixer driver.
NS_E_REDBOOK_ENABLED_WHILE_COPYING 0xC00D0FB0L	Windows Media Player cannot rip tracks from the CD correctly because the CD drive settings in Device Manager do not match the CD drive settings in the Player.
NS_E_CD_REFRESH 0xC00D0FB1L	Windows Media Player is busy reading the CD.
NS_E_CD_DRIVER_PROBLEM	Windows Media Player could not use digital playback to

Value	Meaning
0xC00D0FB2L	play the CD. The Player has automatically switched the CD drive to analog playback. To switch back to digital CD playback, use the Devices tab. For additional assistance, click Web Help.
NS_E_WONT_DO_DIGITAL 0xC00D0FB3L	Windows Media Player could not use digital playback to play the CD. The Player has automatically switched the CD drive to analog playback. To switch back to digital CD playback, use the Devices tab. For additional assistance, click Web Help.
NS_E_WMPXML_NOERROR 0xC00D0FB4L	A call was made to GetParseError on the XML parser but there was no error to retrieve.
NS_E_WMPXML_ENDOFDATA 0xC00D0FB5L	The XML Parser ran out of data while parsing.
NS_E_WMPXML_PARSEERROR 0xC00D0FB6L	A generic parse error occurred in the XML parser but no information is available.
NS_E_WMPXML_ATTRIBUTENOTFOUND 0xC00D0FB7L	A call get GetNamedAttribute or GetNamedAttributeIndex on the XML parser resulted in the index not being found.
NS_E_WMPXML_PINOTFOUND 0xC00D0FB8L	A call was made go GetNamedPI on the XML parser, but the requested Processing Instruction was not found.
NS_E_WMPXML_EMPTYDOC 0xC00D0FB9L	Persist was called on the XML parser, but the parser has no data to persist.
NS_E_WMP_PATH_ALREADY_IN_LIBRARY 0xC00D0FBAL	This file path is already in the library.
NS_E_WMP_FILESCANALREADYSTARTED 0xC00D0FBEL	Windows Media Player is already searching for files to add to your library. Wait for the current process to finish before attempting to search again.
NS_E_WMP_HME_INVALIDOBJECTID 0xC00D0FBFL	Windows Media Player is unable to find the media you

Value	Meaning
	are looking for.
NS_E_WMP_MF_CODE_EXPIRED 0xC00D0FC0L	A component of Windows Media Player is out-of-date. If you are running a pre-release version of Windows, try upgrading to a more recent version.
NS_E_WMP_HME_NOTSEARCHABLEFORITEMS 0xC00D0FC1L	This container does not support search on items.
NS_E_WMP_ADDTOLIBRARY_FAILED 0xC00D0FC7L	Windows Media Player encountered a problem while adding one or more files to the library. For additional assistance, click Web Help.
NS_E_WMP_WINDOWSAPIFAILURE 0xC00D0FC8L	A Windows API call failed but no error information was available.
NS_E_WMP_RECORDING_NOT_ALLOWED 0xC00D0FC9L	This file does not have burn rights. If you obtained this file from an online store, go to the online store to get burn rights.
NS_E_DEVICE_NOT_READY 0xC00D0FCAL	Windows Media Player no longer detects a connected portable device. Reconnect your portable device, and then try to sync the file again.
NS_E_DAMAGED_FILE 0xC00D0FCBL	Windows Media Player cannot play the file because it is corrupted.
NS_E_MPDB_GENERIC 0xC00D0FCCL	Windows Media Player encountered an error while attempting to access information in the library. Try restarting the Player.
NS_E_FILE_FAILED_CHECKS 0xC00D0FCDL	The file cannot be added to the library because it is smaller than the "Skip files smaller than" setting. To add the file, change the setting on the Library tab. For additional assistance, click Web Help.
NS_E_MEDIA_LIBRARY_FAILED 0xC00D0FCEL	Windows Media Player cannot create the library. You must be logged on as an administrator or a member of the Administrators group to install the Player. For more information, contact your



Value	Meaning
	system administrator.
NS_E_SHARING_VIOLATION 0xC00D0FCFL	The file is already in use. Close other programs that might be using the file, or stop playing the file, and then try again.
NS_E_NO_ERROR_STRING_FOUND 0xC00D0FD0L	Windows Media Player has encountered an unknown error.
NS_E_WMPOCX_NO_REMOTE_CORE 0xC00D0FD1L	The Windows Media Player ActiveX control cannot connect to remote media services, but will continue with local media services.
NS_E_WMPOCX_NO_ACTIVE_CORE 0xC00D0FD2L	The requested method or property is not available because the Windows Media Player ActiveX control has not been properly activated.
NS_E_WMPOCX_NOT_RUNNING_REMOTELY 0xC00D0FD3L	The Windows Media Player ActiveX control is not running in remote mode.
NS_E_WMPOCX_NO_REMOTE_WINDOW 0xC00D0FD4L	An error occurred while trying to get the remote Windows Media Player window.
NS_E_WMPOCX_ERRORMANAGERNOTAVAILABLE 0xC00D0FD5L	Windows Media Player has encountered an unknown error.
NS_E_PLUGIN_NOTSHUTDOWN 0xC00D0FD6L	Windows Media Player was not closed properly. A damaged or incompatible plug-in might have caused the problem to occur. As a precaution, all optional plug-ins have been disabled.
NS_E_WMP_CANNOT_FIND_FOLDER 0xC00D0FD7L	Windows Media Player cannot find the specified path. Verify that the path is typed correctly. If it is, the path does not exist in the specified location, or the computer where the path is located is not available.
NS_E_WMP_STREAMING_RECORDING_NOT_ALLOWED 0xC00D0FD8L	Windows Media Player cannot save a file that is being streamed.
NS_E_WMP_PLUGINDLL_NOTFOUND	Windows Media Player cannot

Value	Meaning
0xC00D0FD9L	find the selected plug-in. The Player will try to remove it from the menu. To use this plug-in, install it again.
NS_E_NEED_TO_ASK_USER 0xC00D0FDAL	Action requires input from the user.
NS_E_WMPOCX_PLAYER_NOT_DOCKED 0xC00D0FDBL	The Windows Media Player ActiveX control must be in a docked state for this action to be performed.
NS_E_WMP_EXTERNAL_NOTREADY 0xC00D0FDCL	The Windows Media Player external object is not ready.
NS_E_WMP_MLS_STALE_DATA 0xC00D0FDDL	Windows Media Player cannot perform the requested action. Your computer's time and date might not be set correctly.
NS_E_WMP_UI_SUBCONTROLSNOTSUPPORTED 0xC00D0FDEL	The control (%s) does not support creation of sub-controls, yet (%d) sub-controls have been specified.
NS_E_WMP_UI_VERSIONMISMATCH 0xC00D0FDL	Version mismatch: (%.1f required, %.1f found).
NS_E_WMP_UI_NOTATHEMEFILE 0xC00D0FE0L	The layout manager was given valid XML that wasn't a theme file.
NS_E_WMP_UI_SUBELEMENTNOTFOUND 0xC00D0FE1L	The %s subelement could not be found on the %s object.
NS_E_WMP_UI_VERSIONPARSE 0xC00D0FE2L	An error occurred parsing the version tag.\nValid version tags are of the form:\n\n\t.
NS_E_WMP_UI_VIEWIDNOTFOUND 0xC00D0FE3L	The view specified in for the 'currentViewID' property (%s) was not found in this theme file.
NS_E_WMP_UI_PASSTHROUGH 0xC00D0FE4L	This error used internally for hit testing.
NS_E_WMP_UI_OBJECTNOTFOUND 0xC00D0FE5L	Attributes were specified for the %s object, but the object was not available to send them to.
NS_E_WMP_UI_SECONDHANDLER 0xC00D0FE6L	The %s event already has a handler, the second handler was ignored.

Value	Meaning
NS_E_WMP_UI_NOSKININZIP 0xC00D0FE7L	No .wms file found in skin archive.
NS_E_WMP_URLDOWNLOADFAILED 0xC00D0FEAL	Windows Media Player encountered a problem while downloading the file. For additional assistance, click Web Help.
NS_E_WMPOCX_UNABLE_TO_LOAD_SKIN 0xC00D0FEBL	The Windows Media Player ActiveX control cannot load the requested uiMode and cannot roll back to the existing uiMode.
NS_E_WMP_INVALID_SKIN 0xC00D0FECL	Windows Media Player encountered a problem with the skin file. The skin file might not be valid.
NS_E_WMP_SENDMAILFAILED 0xC00D0FEDL	Windows Media Player cannot send the link because your e-mail program is not responding. Verify that your e-mail program is configured properly, and then try again. For more information about e-mail, see Windows Help.
NS_E_WMP_LOCKEDINSKINMODE 0xC00D0FEEL	Windows Media Player cannot switch to full mode because your computer administrator has locked this skin.
NS_E_WMP_FAILED_TO_SAVE_FILE 0xC00D0FEFL	Windows Media Player encountered a problem while saving the file. For additional assistance, click Web Help.
NS_E_WMP_SAVEAS_READONLY 0xC00D0FF0L	Windows Media Player cannot overwrite a read-only file. Try using a different file name.
NS_E_WMP_FAILED_TO_SAVE_PLAYLIST 0xC00D0FF1L	Windows Media Player encountered a problem while creating or saving the playlist. For additional assistance, click Web Help.
NS_E_WMP_FAILED_TO_OPEN_WMD 0xC00D0FF2L	Windows Media Player cannot open the Windows Media Download file. The file might be damaged.
NS_E_WMP_CANT_PLAY_PROTECTED 0xC00D0FF3L	The file cannot be added to the library because it is a protected DVR-MS file. This

Value	Meaning
	content cannot be played back by Windows Media Player.
NS_E_SHARING_STATE_OUT_OF_SYNC 0xC00D0FF4L	Media sharing has been turned off because a required Windows setting or component has changed. For additional assistance, click Web Help.
NS_E_WMPOCX_REMOTE_PLAYER_ALREADY_RUNNING 0xC00D0FFAL	Exclusive Services launch failed because the Windows Media Player is already running.
NS_E_WMP_RBC_JPGMAPPINGIMAGE 0xC00D1004L	JPG Images are not recommended for use as a mappingImage.
NS_E_WMP_JPGTRANSPARENCY 0xC00D1005L	JPG Images are not recommended when using a transparencyColor.
NS_E_WMP_INVALID_MAX_VAL 0xC00D1009L	The Max property cannot be less than Min property.
NS_E_WMP_INVALID_MIN_VAL 0xC00D100AL	The Min property cannot be greater than Max property.
NS_E_WMP_CS_JPGPOSITIONIMAGE 0xC00D100EL	JPG Images are not recommended for use as a positionImage.
NS_E_WMP_CS_NOTEVENLYDIVISIBLE 0xC00D100FL	The (%s) image's size is not evenly divisible by the positionImage's size.
NS_E_WMPZIP_NOTAZIPFILE 0xC00D1018L	The ZIP reader opened a file and its signature did not match that of the ZIP files.
NS_E_WMPZIP_CORRUPT 0xC00D1019L	The ZIP reader has detected that the file is corrupted.
NS_E_WMPZIP_FILENOTFOUND 0xC00D101AL	GetFileStream, SaveToFile, or SaveTemp file was called on the ZIP reader with a file name that was not found in the ZIP file.
NS_E_WMP_IMAGE_FILETYPE_UNSUPPORTED 0xC00D1022L	Image type not supported.
NS_E_WMP_IMAGE_INVALID_FORMAT 0xC00D1023L	Image file may be corrupt.
NS_E_WMP_GIF_UNEXPECTED_ENDOFFILE	Unexpected end of file. GIF file

Value	Meaning
0xC00D1024L	may be corrupt.
NS_E_WMP_GIF_INVALID_FORMAT 0xC00D1025L	Invalid GIF file.
NS_E_WMP_GIF_BAD_VERSION_NUMBER 0xC00D1026L	Invalid GIF version. Only 87a or 89a supported.
NS_E_WMP_GIF_NO_IMAGE_IN_FILE 0xC00D1027L	No images found in GIF file.
NS_E_WMP_PNG_INVALIDFORMAT 0xC00D1028L	Invalid PNG image file format.
NS_E_WMP_PNG_UNSUPPORTED_BITDEPTH 0xC00D1029L	PNG bitdepth not supported.
NS_E_WMP_PNG_UNSUPPORTED_COMPRESSION 0xC00D102AL	Compression format defined in PNG file not supported,
NS_E_WMP_PNG_UNSUPPORTED_FILTER 0xC00D102BL	Filter method defined in PNG file not supported.
NS_E_WMP_PNG_UNSUPPORTED_INTERLACE 0xC00D102CL	Interlace method defined in PNG file not supported.
NS_E_WMP_PNG_UNSUPPORTED_BAD_CRC 0xC00D102DL	Bad CRC in PNG file.
NS_E_WMP_BMP_INVALID_BITMASK 0xC00D102EL	Invalid bitmask in BMP file.
NS_E_WMP_BMP_TOPDOWN_DIB_UNSUPPORTED 0xC00D102FL	Topdown DIB not supported.
NS_E_WMP_BMP_BITMAP_NOT_CREATED 0xC00D1030L	Bitmap could not be created.
NS_E_WMP_BMP_COMPRESSION_UNSUPPORTED 0xC00D1031L	Compression format defined in BMP not supported.
NS_E_WMP_BMP_INVALID_FORMAT 0xC00D1032L	Invalid Bitmap format.
NS_E_WMP_JPG_JERR_ARITHCODING_NOTIMPL 0xC00D1033L	JPEG Arithmetic coding not supported.
NS_E_WMP_JPG_INVALID_FORMAT 0xC00D1034L	Invalid JPEG format.
NS_E_WMP_JPG_BAD_DCTSIZE 0xC00D1035L	Invalid JPEG format.

Value	Meaning
NS_E_WMP_JPG_BAD_VERSION_NUMBER 0xC00D1036L	Internal version error. Unexpected JPEG library version.
NS_E_WMP_JPG_BAD_PRECISION 0xC00D1037L	Internal JPEG Library error. Unsupported JPEG data precision.
NS_E_WMP_JPG_CCIR601_NOTIMPL 0xC00D1038L	JPEG CCIR601 not supported.
NS_E_WMP_JPG_NO_IMAGE_IN_FILE 0xC00D1039L	No image found in JPEG file.
NS_E_WMP_JPG_READ_ERROR 0xC00D103AL	Could not read JPEG file.
NS_E_WMP_JPG_FRACT_SAMPLE_NOTIMPL 0xC00D103BL	JPEG Fractional sampling not supported.
NS_E_WMP_JPG_IMAGE_TOO_BIG 0xC00D103CL	JPEG image too large. Maximum image size supported is 65500 X 65500.
NS_E_WMP_JPG_UNEXPECTED_ENDOFFILE 0xC00D103DL	Unexpected end of file reached in JPEG file.
NS_E_WMP_JPG_SOF_UNSUPPORTED 0xC00D103EL	Unsupported JPEG SOF marker found.
NS_E_WMP_JPG_UNKNOWN_MARKER 0xC00D103FL	Unknown JPEG marker found.
NS_E_WMP_FAILED_TO_OPEN_IMAGE 0xC00D1044L	Windows Media Player cannot display the picture file. The player either does not support the picture type or the picture is corrupted.
NS_E_WMP_DAI_SONGTOOSHORT 0xC00D1049L	Windows Media Player cannot compute a Digital Audio Id for the song. It is too short.
NS_E_WMG_RATEUNAVAILABLE 0xC00D104AL	Windows Media Player cannot play the file at the requested speed.
NS_E_WMG_PLUGINUNAVAILABLE 0xC00D104BL	The rendering or digital signal processing plug-in cannot be instantiated.
NS_E_WMG_CANNOTQUEUE 0xC00D104CL	The file cannot be queued for seamless playback.
NS_E_WMG_PREROLLICENSEACQUISITIONNOTALLOWED	Windows Media Player cannot download media usage rights

Value	Meaning
0xC00D104DL	for a file in the playlist.
NS_E_WMG_UNEXPECTEDPREROLLSTATUS 0xC00D104EL	Windows Media Player encountered an error while trying to queue a file.
NS_E_WMG_INVALID_COPP_CERTIFICATE 0xC00D1051L	Windows Media Player cannot play the protected file. The Player cannot verify that the connection to your video card is secure. Try installing an updated device driver for your video card.
NS_E_WMG_COPP_SECURITY_INVALID 0xC00D1052L	Windows Media Player cannot play the protected file. The Player detected that the connection to your hardware might not be secure.
NS_E_WMG_COPP_UNSUPPORTED 0xC00D1053L	Windows Media Player output link protection is unsupported on this system.
NS_E_WMG_INVALIDSTATE 0xC00D1054L	Operation attempted in an invalid graph state.
NS_E_WMG_SINKALREADYEXISTS 0xC00D1055L	A renderer cannot be inserted in a stream while one already exists.
NS_E_WMG_NOSDKINTERFACE 0xC00D1056L	The Windows Media SDK interface needed to complete the operation does not exist at this time.
NS_E_WMG_NOTALLOUTPUTSRENDERED 0xC00D1057L	Windows Media Player cannot play a portion of the file because it requires a codec that either could not be downloaded or that is not supported by the Player.
NS_E_WMG_FILETRANSFERNOTALLOWED 0xC00D1058L	File transfer streams are not allowed in the standalone Player.
NS_E_WMR_UNSUPPORTEDSTREAM 0xC00D1059L	Windows Media Player cannot play the file. The Player does not support the format you are trying to play.
NS_E_WMR_PINNOTFOUND 0xC00D105AL	An operation was attempted on a pin that does not exist in the DirectShow filter graph.
NS_E_WMR_WAITINGONFORMATSWITCH	Specified operation cannot be completed while waiting for a

Value	Meaning
0xC00D105BL	media format change from the SDK.
NS_E_WMR_NOSOURCEFILTER 0xC00D105CL	Specified operation cannot be completed because the source filter does not exist.
NS_E_WMR_PINTYPENOMATCH 0xC00D105DL	The specified type does not match this pin.
NS_E_WMR_NOCALLBACKAVAILABLE 0xC00D105EL	The WMR Source Filter does not have a callback available.
NS_E_WMR_SAMPLEPROPERTYNOTSET 0xC00D1062L	The specified property has not been set on this sample.
NS_E_WMR_CANNOT_RENDER_BINARY_STREAM 0xC00D1063L	A plug-in is required to correctly play the file. To determine if the plug-in is available to download, click Web Help.
NS_E_WMG_LICENSE_TAMPERED 0xC00D1064L	Windows Media Player cannot play the file because your media usage rights are corrupted. If you previously backed up your media usage rights, try restoring them.
NS_E_WMR_WILLNOT_RENDER_BINARY_STREAM 0xC00D1065L	Windows Media Player cannot play protected files that contain binary streams.
NS_E_WMX_UNRECOGNIZED_PLAYLIST_FORMAT 0xC00D1068L	Windows Media Player cannot play the playlist because it is not valid.
NS_E_ASX_INVALIDFORMAT 0xC00D1069L	Windows Media Player cannot play the playlist because it is not valid.
NS_E_ASX_INVALIDVERSION 0xC00D106AL	A later version of Windows Media Player might be required to play this playlist.
NS_E_ASX_INVALID_REPEAT_BLOCK 0xC00D106BL	The format of a REPEAT loop within the current playlist file is not valid.
NS_E_ASX_NOTHING_TO_WRITE 0xC00D106CL	Windows Media Player cannot save the playlist because it does not contain any items.
NS_E_URLLIST_INVALIDFORMAT 0xC00D106DL	Windows Media Player cannot play the playlist because it is not valid.



Value	Meaning
NS_E_WMX_ATTRIBUTE_DOES_NOT_EXIST 0xC00D106EL	The specified attribute does not exist.
NS_E_WMX_ATTRIBUTE_ALREADY_EXISTS 0xC00D106FL	The specified attribute already exists.
NS_E_WMX_ATTRIBUTE_UNRETRIEVABLE 0xC00D1070L	Cannot retrieve the specified attribute.
NS_E_WMX_ITEM_DOES_NOT_EXIST 0xC00D1071L	The specified item does not exist in the current playlist.
NS_E_WMX_ITEM_TYPE_ILLEGAL 0xC00D1072L	Items of the specified type cannot be created within the current playlist.
NS_E_WMX_ITEM_UNSETTABLE 0xC00D1073L	The specified item cannot be set in the current playlist.
NS_E_WMX_PLAYLIST_EMPTY 0xC00D1074L	Windows Media Player cannot perform the requested action because the playlist does not contain any items.
NS_E_MLS_SMARTPLAYLIST_FILTER_NOT_REGISTERED 0xC00D1075L	The specified auto playlist contains a filter type that is either not valid or is not installed on this computer.
NS_E_WMX_INVALID_FORMAT_OVER_NESTING 0xC00D1076L	Windows Media Player cannot play the file because the associated playlist contains too many nested playlists.
NS_E_WMPCORE_NOSOURCEURLSTRING 0xC00D107CL	Windows Media Player cannot find the file. Verify that the path is typed correctly. If it is, the file might not exist in the specified location, or the computer where the file is stored might not be available.
NS_E_WMPCORE_COCREATEFAILEDFORGITOBJECT 0xC00D107DL	Failed to create the Global Interface Table.
NS_E_WMPCORE_FAILEDTOGETMARSHALLEVENTHANDLERINTERFACE 0xC00D107EL	Failed to get the marshaled graph event handler interface.
NS_E_WMPCORE_BUFFERTOOSMALL 0xC00D107FL	Buffer is too small for copying media type.
NS_E_WMPCORE_UNAVAILABLE 0xC00D1080L	The current state of the Player does not allow this operation.
NS_E_WMPCORE_INVALIDPLAYLISTMODE	The playlist manager does not

Value	Meaning
0xC00D1081L	understand the current play mode (for example, shuffle or normal).
NS_E_WMPCORE_ITEMNOTINPLAYLIST 0xC00D1086L	Windows Media Player cannot play the file because it is not in the current playlist.
NS_E_WMPCORE_PLAYLISTEMPTY 0xC00D1087L	There are no items in the playlist. Add items to the playlist, and then try again.
NS_E_WMPCORE_NOBROWSER 0xC00D1088L	The Web page cannot be displayed because no Web browser is installed on your computer.
NS_E_WMPCORE_UNRECOGNIZED_MEDIA_URL 0xC00D1089L	Windows Media Player cannot find the specified file. Verify the path is typed correctly. If it is, the file does not exist in the specified location, or the computer where the file is stored is not available.
NS_E_WMPCORE_GRAPH_NOT_IN_LIST 0xC00D108AL	Graph with the specified URL was not found in the prerolled graph list.
NS_E_WMPCORE_PLAYLIST_EMPTY_OR_SINGLE_MEDIA 0xC00D108BL	Windows Media Player cannot perform the requested operation because there is only one item in the playlist.
NS_E_WMPCORE_ERRORSINKNOTREGISTERED 0xC00D108CL	An error sink was never registered for the calling object.
NS_E_WMPCORE_ERRORMANAGERNOTAVAILABLE 0xC00D108DL	The error manager is not available to respond to errors.
NS_E_WMPCORE_WEBHELPFAILED 0xC00D108EL	The Web Help URL cannot be opened.
NS_E_WMPCORE_MEDIA_ERROR_RESUME_FAILED 0xC00D108FL	Could not resume playing next item in playlist.
NS_E_WMPCORE_NO_REF_IN_ENTRY 0xC00D1090L	Windows Media Player cannot play the file because the associated playlist does not contain any items or the playlist is not valid.
NS_E_WMPCORE_WMX_LIST_ATTRIBUTE_NAME_EMPTY 0xC00D1091L	An empty string for playlist attribute name was found.
NS_E_WMPCORE_WMX_LIST_ATTRIBUTE_NAME_ILLEGAL	A playlist attribute name that

Value	Meaning
0xC00D1092L	is not valid was found.
NS_E_WMPCORE_WMX_LIST_ATTRIBUTE_VALUE_EMPTY 0xC00D1093L	An empty string for a playlist attribute value was found.
NS_E_WMPCORE_WMX_LIST_ATTRIBUTE_VALUE_ILLEGAL 0xC00D1094L	An illegal value for a playlist attribute was found.
NS_E_WMPCORE_WMX_LIST_ITEM_ATTRIBUTE_NAME_EMPTY 0xC00D1095L	An empty string for a playlist item attribute name was found.
NS_E_WMPCORE_WMX_LIST_ITEM_ATTRIBUTE_NAME_ILLEGAL 0xC00D1096L	An illegal value for a playlist item attribute name was found.
NS_E_WMPCORE_WMX_LIST_ITEM_ATTRIBUTE_VALUE_EMPTY 0xC00D1097L	An illegal value for a playlist item attribute was found.
NS_E_WMPCORE_LIST_ENTRY_NO_REF 0xC00D1098L	The playlist does not contain any items.
NS_E_WMPCORE_MISNAMED_FILE 0xC00D1099L	Windows Media Player cannot play the file. The file is either corrupted or the Player does not support the format you are trying to play.
NS_E_WMPCORE_CODEC_NOT_TRUSTED 0xC00D109AL	The codec downloaded for this file does not appear to be properly signed, so it cannot be installed.
NS_E_WMPCORE_CODEC_NOT_FOUND 0xC00D109BL	Windows Media Player cannot play the file. One or more codecs required to play the file could not be found.
NS_E_WMPCORE_CODEC_DOWNLOAD_NOT_ALLOWED 0xC00D109CL	Windows Media Player cannot play the file because a required codec is not installed on your computer. To try downloading the codec, turn on the "Download codecs automatically" option.
NS_E_WMPCORE_ERROR_DOWNLOADING_PLAYLIST 0xC00D109DL	Windows Media Player encountered a problem while downloading the playlist. For additional assistance, click Web Help.
NS_E_WMPCORE_FAILED_TO_BUILD_PLAYLIST 0xC00D109EL	Failed to build the playlist.
NS_E_WMPCORE_PLAYLIST_ITEM_ALTERNATE_NONE	Playlist has no alternates to

Value	Meaning
0xC00D109FL	switch into.
NS_E_WMPCORE_PLAYLIST_ITEM_ALTERNATE_EXHAUSTED 0xC00D10A0L	No more playlist alternates available to switch to.
NS_E_WMPCORE_PLAYLIST_ITEM_ALTERNATE_NAME_NOT_FOUND 0xC00D10A1L	Could not find the name of the alternate playlist to switch into.
NS_E_WMPCORE_PLAYLIST_ITEM_ALTERNATE_MORPH_FAILED 0xC00D10A2L	Failed to switch to an alternate for this media.
NS_E_WMPCORE_PLAYLIST_ITEM_ALTERNATE_INIT_FAILED 0xC00D10A3L	Failed to initialize an alternate for the media.
NS_E_WMPCORE_MEDIA_ALTERNATE_REF_EMPTY 0xC00D10A4L	No URL specified for the roll over Refs in the playlist file.
NS_E_WMPCORE_PLAYLIST_NO_EVENT_NAME 0xC00D10A5L	Encountered a playlist with no name.
NS_E_WMPCORE_PLAYLIST_EVENT_ATTRIBUTE_ABSENT 0xC00D10A6L	A required attribute in the event block of the playlist was not found.
NS_E_WMPCORE_PLAYLIST_EVENT_EMPTY 0xC00D10A7L	No items were found in the event block of the playlist.
NS_E_WMPCORE_PLAYLIST_STACK_EMPTY 0xC00D10A8L	No playlist was found while returning from a nested playlist.
NS_E_WMPCORE_CURRENT_MEDIA_NOT_ACTIVE 0xC00D10A9L	The media item is not active currently.
NS_E_WMPCORE_USER_CANCEL 0xC00D10ABL	Windows Media Player cannot perform the requested action because you chose to cancel it.
NS_E_WMPCORE_PLAYLIST_REPEAT_EMPTY 0xC00D10ACL	Windows Media Player encountered a problem with the playlist. The format of the playlist is not valid.
NS_E_WMPCORE_PLAYLIST_REPEAT_START_MEDIA_NONE 0xC00D10ADL	Media object corresponding to start of a playlist repeat block was not found.
NS_E_WMPCORE_PLAYLIST_REPEAT_END_MEDIA_NONE 0xC00D10AEL	Media object corresponding to the end of a playlist repeat block was not found.
NS_E_WMPCORE_INVALID_PLAYLIST_URL 0xC00D10AFL	The playlist URL supplied to the playlist manager is not valid.

Value	Meaning
NS_E_WMPCORE_MISMATCHED_RUNTIME 0xC00D10B0L	Windows Media Player cannot play the file because it is corrupted.
NS_E_WMPCORE_PLAYLIST_IMPORT_FAILED_NO_ITEMS 0xC00D10B1L	Windows Media Player cannot add the playlist to the library because the playlist does not contain any items.
NS_E_WMPCORE_VIDEO_TRANSFORM_FILTER_INSERTION 0xC00D10B2L	An error has occurred that could prevent the changing of the video contrast on this media.
NS_E_WMPCORE_MEDIA_UNAVAILABLE 0xC00D10B3L	Windows Media Player cannot play the file. If the file is located on the Internet, connect to the Internet. If the file is located on a removable storage card, insert the storage card.
NS_E_WMPCORE_WMX_ENTRYREF_NO_REF 0xC00D10B4L	The playlist contains an ENTRYREF for which no href was parsed. Check the syntax of playlist file.
NS_E_WMPCORE_NO_PLAYABLE_MEDIA_IN_PLAYLIST 0xC00D10B5L	Windows Media Player cannot play any items in the playlist. To find information about the problem, click the Now Playing tab, and then click the icon next to each file in the List pane.
NS_E_WMPCORE_PLAYLIST_EMPTY_NESTED_PLAYLIST_SKIPPED_ITEMS 0xC00D10B6L	Windows Media Player cannot play some or all of the items in the playlist because the playlist is nested.
NS_E_WMPCORE_BUSY 0xC00D10B7L	Windows Media Player cannot play the file at this time. Try again later.
NS_E_WMPCORE_MEDIA_CHILD_PLAYLIST_UNAVAILABLE 0xC00D10B8L	There is no child playlist available for this media item at this time.
NS_E_WMPCORE_MEDIA_NO_CHILD_PLAYLIST 0xC00D10B9L	There is no child playlist for this media item.
NS_E_WMPCORE_FILE_NOT_FOUND 0xC00D10BAL	Windows Media Player cannot find the file. The link from the item in the library to its associated digital media file might be broken. To fix the problem, try repairing the link

Value	Meaning
	or removing the item from the library.
NS_E_WMPCORE_TEMP_FILE_NOT_FOUND 0xC00D10BBL	The temporary file was not found.
NS_E_WMDM_REVOKED 0xC00D10BCL	Windows Media Player cannot sync the file because the device needs to be updated.
NS_E_DDRAW_GENERIC 0xC00D10BDL	Windows Media Player cannot play the video because there is a problem with your video card.
NS_E_DISPLAY_MODE_CHANGE_FAILED 0xC00D10BEL	Windows Media Player failed to change the screen mode for full-screen video playback.
NS_E_PLAYLIST_CONTAINS_ERRORS 0xC00D10BFL	Windows Media Player cannot play one or more files. For additional information, right-click an item that cannot be played, and then click Error Details.
NS_E_CHANGING_PROXY_NAME 0xC00D10C0L	Cannot change the proxy name if the proxy setting is not set to custom.
NS_E_CHANGING_PROXY_PORT 0xC00D10C1L	Cannot change the proxy port if the proxy setting is not set to custom.
NS_E_CHANGING_PROXY_EXCEPTIONLIST 0xC00D10C2L	Cannot change the proxy exception list if the proxy setting is not set to custom.
NS_E_CHANGING_PROXYBYPASS 0xC00D10C3L	Cannot change the proxy bypass flag if the proxy setting is not set to custom.
NS_E_CHANGING_PROXY_PROTOCOL_NOT_FOUND 0xC00D10C4L	Cannot find the specified protocol.
NS_E_GRAPH_NOAUDIOLANGUAGE 0xC00D10C5L	Cannot change the language settings. Either the graph has no audio or the audio only supports one language.
NS_E_GRAPH_NOAUDIOLANGUAGESELECTED 0xC00D10C6L	The graph has no audio language selected.
NS_E_CORECD_NOTAMEDIACD 0xC00D10C7L	This is not a media CD.
NS_E_WMPCORE_MEDIA_URL_TOO_LONG	Windows Media Player cannot

Value	Meaning
0xC00D10C8L	play the file because the URL is too long.
NS_E_WMPFLASH_CANT_FIND_COM_SERVER 0xC00D10C9L	To play the selected item, you must install the Macromedia Flash Player. To download the Macromedia Flash Player, go to the Adobe Web site.
NS_E_WMPFLASH_INCOMPATIBLEVERSION 0xC00D10CAL	To play the selected item, you must install a later version of the Macromedia Flash Player. To download the Macromedia Flash Player, go to the Adobe Web site.
NS_E_WMPOCXGRAPH_IE_DISALLOWS_ACTIVEX_CONTROLS 0xC00D10CBL	Windows Media Player cannot play the file because your Internet security settings prohibit the use of ActiveX controls.
NS_E_NEED_CORE_REFERENCE 0xC00D10CCL	The use of this method requires an existing reference to the Player object.
NS_E_MEDIACD_READ_ERROR 0xC00D10CDL	Windows Media Player cannot play the CD. The disc might be dirty or damaged.
NS_E_IE_DISALLOWS_ACTIVEX_CONTROLS 0xC00D10CEL	Windows Media Player cannot play the file because your Internet security settings prohibit the use of ActiveX controls.
NS_E_FLASH_PLAYBACK_NOT_ALLOWED 0xC00D10CFL	Flash playback has been turned off in Windows Media Player.
NS_E_UNABLE_TO_CREATE_RIP_LOCATION 0xC00D10D0L	Windows Media Player cannot rip the CD because a valid rip location cannot be created.
NS_E_WMPCORE_SOME_CODECS_MISSING 0xC00D10D1L	Windows Media Player cannot play the file because a required codec is not installed on your computer.
NS_E_WMP_RIP_FAILED 0xC00D10D2L	Windows Media Player cannot rip one or more tracks from the CD.
NS_E_WMP_FAILED_TO_RIP_TRACK 0xC00D10D3L	Windows Media Player encountered a problem while ripping the track from the CD. For additional assistance, click Web Help.

Value	Meaning
NS_E_WMP_ERASE_FAILED 0xC00D10D4L	Windows Media Player encountered a problem while erasing the disc. For additional assistance, click Web Help.
NS_E_WMP_FORMAT_FAILED 0xC00D10D5L	Windows Media Player encountered a problem while formatting the device. For additional assistance, click Web Help.
NS_E_WMP_CANNOT_BURN_NON_LOCAL_FILE 0xC00D10D6L	This file cannot be burned to a CD because it is not located on your computer.
NS_E_WMP_FILE_TYPE_CANNOT_BURN_TO_AUDIO_CD 0xC00D10D7L	It is not possible to burn this file type to an audio CD. Windows Media Player can burn the following file types to an audio CD: WMA, MP3, or WAV.
NS_E_WMP_FILE_DOES_NOT_FIT_ON_CD 0xC00D10D8L	This file is too large to fit on a disc.
NS_E_WMP_FILE_NO_DURATION 0xC00D10D9L	It is not possible to determine if this file can fit on a disc because Windows Media Player cannot detect the length of the file. Playing the file before burning may enable the Player to detect the file length.
NS_E_PDA_FAILED_TO_BURN 0xC00D10DAL	Windows Media Player encountered a problem while burning the file to the disc. For additional assistance, click Web Help.
NS_E_FAILED_DOWNLOAD_ABORT_BURN 0xC00D10DCL	Windows Media Player cannot burn the audio CD because some items in the list that you chose to buy could not be downloaded from the online store.
NS_E_WMPCORE_DEVICE_DRIVERS_MISSING 0xC00D10DDL	Windows Media Player cannot play the file. Try using Windows Update or Device Manager to update the device drivers for your audio and video cards. For information about using Windows Update or Device Manager, see Windows Help.



Value	Meaning
NS_E_WMPIM_USEROFFLINE 0xC00D1126L	Windows Media Player has detected that you are not connected to the Internet. Connect to the Internet, and then try again.
NS_E_WMPIM_USERCANCELED 0xC00D1127L	The attempt to connect to the Internet was canceled.
NS_E_WMPIM_DIALUPFAILED 0xC00D1128L	The attempt to connect to the Internet failed.
NS_E_WINSOCK_ERROR_STRING 0xC00D1129L	Windows Media Player has encountered an unknown network error.
NS_E_WMPBR_NOLISTENER 0xC00D1130L	No window is currently listening to Backup and Restore events.
NS_E_WMPBR_BACKUPCANCEL 0xC00D1131L	Your media usage rights were not backed up because the backup was canceled.
NS_E_WMPBR_RESTORECANCEL 0xC00D1132L	Your media usage rights were not restored because the restoration was canceled.
NS_E_WMPBR_ERRORWITHURL 0xC00D1133L	An error occurred while backing up or restoring your media usage rights. A required Web page cannot be displayed.
NS_E_WMPBR_NAMECOLLISION 0xC00D1134L	Your media usage rights were not backed up because the backup was canceled.
NS_E_WMPBR_DRIVE_INVALID 0xC00D1137L	Windows Media Player cannot restore your media usage rights from the specified location. Choose another location, and then try again.
NS_E_WMPBR_BACKUPRESTOREFAILED 0xC00D1138L	Windows Media Player cannot backup or restore your media usage rights.
NS_E_WMP_CONVERT_FILE_FAILED 0xC00D1158L	Windows Media Player cannot add the file to the library.
NS_E_WMP_CONVERT_NO_RIGHTS_ERRORURL 0xC00D1159L	Windows Media Player cannot add the file to the library because the content provider prohibits it. For assistance, contact the company that provided the file.

Value	Meaning
NS_E_WMP_CONVERT_NO_RIGHTS_NOERRORURL 0xC00D115AL	Windows Media Player cannot add the file to the library because the content provider prohibits it. For assistance, contact the company that provided the file.
NS_E_WMP_CONVERT_FILE_CORRUPT 0xC00D115BL	Windows Media Player cannot add the file to the library. The file might not be valid.
NS_E_WMP_CONVERT_PLUGIN_UNAVAILABLE_ERRORURL 0xC00D115CL	Windows Media Player cannot add the file to the library. The plug-in required to add the file is not installed properly. For assistance, click Web Help to display the Web site of the company that provided the file.
NS_E_WMP_CONVERT_PLUGIN_UNAVAILABLE_NOERRORURL 0xC00D115DL	Windows Media Player cannot add the file to the library. The plug-in required to add the file is not installed properly. For assistance, contact the company that provided the file.
NS_E_WMP_CONVERT_PLUGIN_UNKNOWN_FILE_OWNER 0xC00D115EL	Windows Media Player cannot add the file to the library. The plug-in required to add the file is not installed properly. For assistance, contact the company that provided the file.
NS_E_DVD_DISC_COPY_PROTECT_OUTPUT_NS 0xC00D1160L	Windows Media Player cannot play this DVD. Try installing an updated driver for your video card or obtaining a newer video card.
NS_E_DVD_DISC_COPY_PROTECT_OUTPUT_FAILED 0xC00D1161L	This DVD's resolution exceeds the maximum allowed by your component video outputs. Try reducing your screen resolution to 640 x 480, or turn off analog component outputs and use a VGA connection to your monitor.
NS_E_DVD_NO_SUBPICTURE_STREAM 0xC00D1162L	Windows Media Player cannot display subtitles or highlights in DVD menus. Reinstall the DVD decoder or contact the DVD drive manufacturer to obtain an updated decoder.

Value	Meaning
NS_E_DVD_COPY_PROTECT 0xC00D1163L	Windows Media Player cannot play this DVD because there is a problem with digital copy protection between your DVD drive, decoder, and video card. Try installing an updated driver for your video card.
NS_E_DVD_AUTHORIZING_PROBLEM 0xC00D1164L	Windows Media Player cannot play the DVD. The disc was created in a manner that the Player does not support.
NS_E_DVD_INVALID_DISC_REGION 0xC00D1165L	Windows Media Player cannot play the DVD because the disc prohibits playback in your region of the world. You must obtain a disc that is intended for your geographic region.
NS_E_DVD_COMPATIBLE_VIDEO_CARD 0xC00D1166L	Windows Media Player cannot play the DVD because your video card does not support DVD playback.
NS_E_DVD_MACROVISION 0xC00D1167L	Windows Media Player cannot play this DVD because it is not possible to turn on analog copy protection on the output display. Try installing an updated driver for your video card.
NS_E_DVD_SYSTEM_DECODER_REGION 0xC00D1168L	Windows Media Player cannot play the DVD because the region assigned to your DVD drive does not match the region assigned to your DVD decoder.
NS_E_DVD_DISC_DECODER_REGION 0xC00D1169L	Windows Media Player cannot play the DVD because the disc prohibits playback in your region of the world. You must obtain a disc that is intended for your geographic region.
NS_E_DVD_NO_VIDEO_STREAM 0xC00D116AL	Windows Media Player cannot play DVD video. You might need to adjust your Windows display settings. Open display settings in Control Panel, and then try lowering your screen resolution and color quality settings.
NS_E_DVD_NO_AUDIO_STREAM	Windows Media Player cannot play DVD audio. Verify that

Value	Meaning
0xC00D116BL	your sound card is set up correctly, and then try again.
NS_E_DVD_GRAPH_BUILDING 0xC00D116CL	Windows Media Player cannot play DVD video. Close any open files and quit any other programs, and then try again. If the problem persists, restart your computer.
NS_E_DVD_NO_DECODER 0xC00D116DL	Windows Media Player cannot play the DVD because a compatible DVD decoder is not installed on your computer.
NS_E_DVD_PARENTAL 0xC00D116EL	Windows Media Player cannot play the scene because it has a parental rating higher than the rating that you are authorized to view.
NS_E_DVD_CANNOT_JUMP 0xC00D116FL	Windows Media Player cannot skip to the requested location on the DVD.
NS_E_DVD_DEVICE_CONTENTION 0xC00D1170L	Windows Media Player cannot play the DVD because it is currently in use by another program. Quit the other program that is using the DVD, and then try again.
NS_E_DVD_NO_VIDEO_MEMORY 0xC00D1171L	Windows Media Player cannot play DVD video. You might need to adjust your Windows display settings. Open display settings in Control Panel, and then try lowering your screen resolution and color quality settings.
NS_E_DVD_CANNOT_COPY_PROTECTED 0xC00D1172L	Windows Media Player cannot rip the DVD because it is copy protected.
NS_E_DVD_REQUIRED_PROPERTY_NOT_SET 0xC00D1173L	One of more of the required properties has not been set.
NS_E_DVD_INVALID_TITLE_CHAPTER 0xC00D1174L	The specified title and/or chapter number does not exist on this DVD.
NS_E_NO_CD_BURNER 0xC00D1176L	Windows Media Player cannot burn the files because the Player cannot find a burner. If the burner is connected properly, try using Windows Update to install the latest

Value	Meaning
	device driver.
NS_E_DEVICE_IS_NOT_READY 0xC00D1177L	Windows Media Player does not detect storage media in the selected device. Insert storage media into the device, and then try again.
NS_E_PDA_UNSUPPORTED_FORMAT 0xC00D1178L	Windows Media Player cannot sync this file. The Player might not support the file type.
NS_E_NO_PDA 0xC00D1179L	Windows Media Player does not detect a portable device. Connect your portable device, and then try again.
NS_E_PDA_UNSPECIFIED_ERROR 0xC00D117AL	Windows Media Player encountered an error while communicating with the device. The storage card on the device might be full, the device might be turned off, or the device might not allow playlists or folders to be created on it.
NS_E_MEMSTORAGE_BAD_DATA 0xC00D117BL	Windows Media Player encountered an error while burning a CD.
NS_E_PDA_FAIL_SELECT_DEVICE 0xC00D117CL	Windows Media Player encountered an error while communicating with a portable device or CD drive.
NS_E_PDA_FAIL_READ_WAVE_FILE 0xC00D117DL	Windows Media Player cannot open the WAV file.
NS_E_IMAPI_LOSSOFSTREAMING 0xC00D117EL	Windows Media Player failed to burn all the files to the CD. Select a slower recording speed, and then try again.
NS_E_PDA_DEVICE_FULL 0xC00D117FL	There is not enough storage space on the portable device to complete this operation. Delete some unneeded files on the portable device, and then try again.
NS_E_FAIL_LAUNCH_ROXIO_PLUGIN 0xC00D1180L	Windows Media Player cannot burn the files. Verify that your burner is connected properly, and then try again. If the problem persists, reinstall the Player.

Value	Meaning
NS_E_PDA_DEVICE_FULL_IN_SESSION 0xC00D1181L	Windows Media Player did not sync some files to the device because there is not enough storage space on the device.
NS_E_IMAPI_MEDIUM_INVALIDTYPE 0xC00D1182L	The disc in the burner is not valid. Insert a blank disc into the burner, and then try again.
NS_E_PDA_MANUALDEVICE 0xC00D1183L	Windows Media Player cannot perform the requested action because the device does not support sync.
NS_E_PDA_PARTNERSHIPNOTEXIST 0xC00D1184L	To perform the requested action, you must first set up sync with the device.
NS_E_PDA_CANNOT_CREATE_ADDITIONAL_SYNC_RELATIONSHIP 0xC00D1185L	You have already created sync partnerships with 16 devices. To create a new sync partnership, you must first end an existing partnership.
NS_E_PDA_NO_TRANSCODE_OF_DRM 0xC00D1186L	Windows Media Player cannot sync the file because protected files cannot be converted to the required quality level or file format.
NS_E_PDA_TRANSCODECACHEFULL 0xC00D1187L	The folder that stores converted files is full. Either empty the folder or increase its size, and then try again.
NS_E_PDA_TOO_MANY_FILE_COLLISIONS 0xC00D1188L	There are too many files with the same name in the folder on the device. Change the file name or sync to a different folder.
NS_E_PDA_CANNOT_TRANSCODE 0xC00D1189L	Windows Media Player cannot convert the file to the format required by the device.
NS_E_PDA_TOO_MANY_FILES_IN_DIRECTORY 0xC00D118AL	You have reached the maximum number of files your device allows in a folder. If your device supports playback from subfolders, try creating subfolders on the device and storing some files in them.
NS_E_PROCESSINGSHOWSYNCSWIZARD 0xC00D118BL	Windows Media Player is already trying to start the Device Setup Wizard.

Value	Meaning
NS_E_PDA_TRANSCODE_NOT_PERMITTED 0xC00D118CL	Windows Media Player cannot convert this file format. If an updated version of the codec used to compress this file is available, install it and then try to sync the file again.
NS_E_PDA_INITIALIZINGDEVICES 0xC00D118DL	Windows Media Player is busy setting up devices. Try again later.
NS_E_PDA_OBSOLETE_SP 0xC00D118EL	Your device is using an outdated driver that is no longer supported by Windows Media Player. For additional assistance, click Web Help.
NS_E_PDA_TITLE_COLLISION 0xC00D118FL	Windows Media Player cannot sync the file because a file with the same name already exists on the device. Change the file name or try to sync the file to a different folder.
NS_E_PDA_DEVICESUPPORTDISABLED 0xC00D1190L	Automatic and manual sync have been turned off temporarily. To sync to a device, restart Windows Media Player.
NS_E_PDA_NO_LONGER_AVAILABLE 0xC00D1191L	This device is not available. Connect the device to the computer, and then try again.
NS_E_PDA_ENCODER_NOT_RESPONDING 0xC00D1192L	Windows Media Player cannot sync the file because an error occurred while converting the file to another quality level or format. If the problem persists, remove the file from the list of files to sync.
NS_E_PDA_CANNOT_SYNC_FROM_LOCATION 0xC00D1193L	Windows Media Player cannot sync the file to your device. The file might be stored in a location that is not supported. Copy the file from its current location to your hard disk, add it to your library, and then try to sync the file again.
NS_E_WMP_PROTOCOL_PROBLEM 0xC00D1194L	Windows Media Player cannot open the specified URL. Verify that the Player is configured to use all available protocols, and then try again.

Value	Meaning
NS_E_WMP_NO_DISK_SPACE 0xC00D1195L	Windows Media Player cannot perform the requested action because there is not enough storage space on your computer. Delete some unneeded files on your hard disk, and then try again.
NS_E_WMP_LOGON_FAILURE 0xC00D1196L	The server denied access to the file. Verify that you are using the correct user name and password.
NS_E_WMP_CANNOT_FIND_FILE 0xC00D1197L	Windows Media Player cannot find the file. If you are trying to play, burn, or sync an item that is in your library, the item might point to a file that has been moved, renamed, or deleted.
NS_E_WMP_SERVER_INACCESSIBLE 0xC00D1198L	Windows Media Player cannot connect to the server. The server name might not be correct, the server might not be available, or your proxy settings might not be correct.
NS_E_WMP_UNSUPPORTED_FORMAT 0xC00D1199L	Windows Media Player cannot play the file. The Player might not support the file type or might not support the codec that was used to compress the file.
NS_E_WMP_DSHOW_UNSUPPORTED_FORMAT 0xC00D119AL	Windows Media Player cannot play the file. The Player might not support the file type or a required codec might not be installed on your computer.
NS_E_WMP_PLAYLIST_EXISTS 0xC00D119BL	Windows Media Player cannot create the playlist because the name already exists. Type a different playlist name.
NS_E_WMP_NONMEDIA_FILES 0xC00D119CL	Windows Media Player cannot delete the playlist because it contains items that are not digital media files. Any digital media files in the playlist were deleted.
NS_E_WMP_INVALID_ASX 0xC00D119DL	The playlist cannot be opened because it is stored in a shared folder on another computer. If possible, move the playlist to the playlists



Value	Meaning
	folder on your computer.
NS_E_WMP_ALREADY_IN_USE 0xC00D119EL	Windows Media Player is already in use. Stop playing any items, close all Player dialog boxes, and then try again.
NS_E_WMP_IMAPI_FAILURE 0xC00D119FL	Windows Media Player encountered an error while burning. Verify that the burner is connected properly and that the disc is clean and not damaged.
NS_E_WMP_WMDM_FAILURE 0xC00D11A0L	Windows Media Player has encountered an unknown error with your portable device. Reconnect your portable device, and then try again.
NS_E_WMP_CODEEC_NEEDED_WITH_4CC 0xC00D11A1L	A codec is required to play this file. To determine if this codec is available to download from the Web, click Web Help.
NS_E_WMP_CODEEC_NEEDED_WITH_FORMATTAG 0xC00D11A2L	An audio codec is needed to play this file. To determine if this codec is available to download from the Web, click Web Help.
NS_E_WMP_MSSAP_NOT_AVAILABLE 0xC00D11A3L	To play the file, you must install the latest Windows service pack. To install the service pack from the Windows Update Web site, click Web Help.
NS_E_WMP_WMDM_INTERFACEDAD 0xC00D11A4L	Windows Media Player no longer detects a portable device. Reconnect your portable device, and then try again.
NS_E_WMP_WMDM_NOTCERTIFIED 0xC00D11A5L	Windows Media Player cannot sync the file because the portable device does not support protected files.
NS_E_WMP_WMDM_LICENSE_NOTEXIST 0xC00D11A6L	This file does not have sync rights. If you obtained this file from an online store, go to the online store to get sync rights.
NS_E_WMP_WMDM_LICENSE_EXPIRED 0xC00D11A7L	Windows Media Player cannot sync the file because the sync rights have expired. Go to the

Value	Meaning
	content provider's online store to get new sync rights.
NS_E_WMP_WMDM_BUSY 0xC00D11A8L	The portable device is already in use. Wait until the current task finishes or quit other programs that might be using the portable device, and then try again.
NS_E_WMP_WMDM_NORIGHTS 0xC00D11A9L	Windows Media Player cannot sync the file because the content provider or device prohibits it. You might be able to resolve this problem by going to the content provider's online store to get sync rights.
NS_E_WMP_WMDM_INCORRECT_RIGHTS 0xC00D11AAL	The content provider has not granted you the right to sync this file. Go to the content provider's online store to get sync rights.
NS_E_WMP_IMAPI_GENERIC 0xC00D11ABL	Windows Media Player cannot burn the files to the CD. Verify that the disc is clean and not damaged. If necessary, select a slower recording speed or try a different brand of blank discs.
NS_E_WMP_IMAPI_DEVICE_NOTPRESENT 0xC00D11ADL	Windows Media Player cannot burn the files. Verify that the burner is connected properly, and then try again.
NS_E_WMP_IMAPI_DEVICE_BUSY 0xC00D11AEL	Windows Media Player cannot burn the files. Verify that the burner is connected properly and that the disc is clean and not damaged. If the burner is already in use, wait until the current task finishes or quit other programs that might be using the burner.
NS_E_WMP_IMAPI_LOSS_OF_STREAMING 0xC00D11AFL	Windows Media Player cannot burn the files to the CD.
NS_E_WMP_SERVER_UNAVAILABLE 0xC00D11B0L	Windows Media Player cannot play the file. The server might not be available or there might be a problem with your network or firewall settings.
NS_E_WMP_FILE_OPEN_FAILED	Windows Media Player encountered a problem while

Value	Meaning
0xC00D11B1L	playing the file. For additional assistance, click Web Help.
NS_E_WMP_VERIFY_ONLINE 0xC00D11B2L	Windows Media Player must connect to the Internet to verify the file's media usage rights. Connect to the Internet, and then try again.
NS_E_WMP_SERVER_NOT_RESPONDING 0xC00D11B3L	Windows Media Player cannot play the file because a network error occurred. The server might not be available. Verify that you are connected to the network and that your proxy settings are correct.
NS_E_WMP_DRM_CORRUPT_BACKUP 0xC00D11B4L	Windows Media Player cannot restore your media usage rights because it could not find any backed up rights on your computer.
NS_E_WMP_DRM_LICENSE_SERVER_UNAVAILABLE 0xC00D11B5L	Windows Media Player cannot download media usage rights because the server is not available (for example, the server might be busy or not online).
NS_E_WMP_NETWORK_FIREWALL 0xC00D11B6L	Windows Media Player cannot play the file. A network firewall might be preventing the Player from opening the file by using the UDP transport protocol. If you typed a URL in the Open URL dialog box, try using a different transport protocol (for example, "http:").
NS_E_WMP_NO_REMOVABLE_MEDIA 0xC00D11B7L	Insert the removable media, and then try again.
NS_E_WMP_PROXY_CONNECT_TIMEOUT 0xC00D11B8L	Windows Media Player cannot play the file because the proxy server is not responding. The proxy server might be temporarily unavailable or your Player proxy settings might not be valid.
NS_E_WMP_NEED_UPGRADE 0xC00D11B9L	To play the file, you might need to install a later version of Windows Media Player. On the Help menu, click Check for Updates, and then follow the instructions. For additional

Value	Meaning
	assistance, click Web Help.
NS_E_WMP_AUDIO_HW_PROBLEM 0xC00D11BAL	Windows Media Player cannot play the file because there is a problem with your sound device. There might not be a sound device installed on your computer, it might be in use by another program, or it might not be functioning properly.
NS_E_WMP_INVALID_PROTOCOL 0xC00D11BBL	Windows Media Player cannot play the file because the specified protocol is not supported. If you typed a URL in the Open URL dialog box, try using a different transport protocol (for example, "http:" or "rtsp:").
NS_E_WMP_INVALID_LIBRARY_ADD 0xC00D11BCL	Windows Media Player cannot add the file to the library because the file format is not supported.
NS_E_WMP_MMS_NOT_SUPPORTED 0xC00D11BDL	Windows Media Player cannot play the file because the specified protocol is not supported. If you typed a URL in the Open URL dialog box, try using a different transport protocol (for example, "mms:").
NS_E_WMP_NO_PROTOCOLS_SELECTED 0xC00D11BEL	Windows Media Player cannot play the file because there are no streaming protocols selected. Select one or more protocols, and then try again.
NS_E_WMP_GOFULLSCREEN_FAILED 0xC00D11BFL	Windows Media Player cannot switch to Full Screen. You might need to adjust your Windows display settings. Open display settings in Control Panel, and then try setting Hardware acceleration to Full.
NS_E_WMP_NETWORK_ERROR 0xC00D11C0L	Windows Media Player cannot play the file because a network error occurred. The server might not be available (for example, the server is busy or not online) or you might not be connected to the network.

Value	Meaning
NS_E_WMP_CONNECT_TIMEOUT 0xC00D11C1L	Windows Media Player cannot play the file because the server is not responding. Verify that you are connected to the network, and then try again later.
NS_E_WMP_MULTICAST_DISABLED 0xC00D11C2L	Windows Media Player cannot play the file because the multicast protocol is not enabled. On the Tools menu, click Options, click the Network tab, and then select the Multicast check box. For additional assistance, click Web Help.
NS_E_WMP_SERVER_DNS_TIMEOUT 0xC00D11C3L	Windows Media Player cannot play the file because a network problem occurred. Verify that you are connected to the network, and then try again later.
NS_E_WMP_PROXY_NOT_FOUND 0xC00D11C4L	Windows Media Player cannot play the file because the network proxy server cannot be found. Verify that your proxy settings are correct, and then try again.
NS_E_WMP_TAMPERED_CONTENT 0xC00D11C5L	Windows Media Player cannot play the file because it is corrupted.
NS_E_WMP_OUTOFMEMORY 0xC00D11C6L	Your computer is running low on memory. Quit other programs, and then try again.
NS_E_WMP_AUDIO_CODEC_NOT_INSTALLED 0xC00D11C7L	Windows Media Player cannot play, burn, rip, or sync the file because a required audio codec is not installed on your computer.
NS_E_WMP_VIDEO_CODEC_NOT_INSTALLED 0xC00D11C8L	Windows Media Player cannot play the file because the required video codec is not installed on your computer.
NS_E_WMP_IMAPI_DEVICE_INVALIDTYPE 0xC00D11C9L	Windows Media Player cannot burn the files. If the burner is busy, wait for the current task to finish. If necessary, verify that the burner is connected properly and that you have installed the latest device

Value	Meaning
	driver.
NS_E_WMP_DRM_DRIVER_AUTH_FAILURE 0xC00D11CAL	Windows Media Player cannot play the protected file because there is a problem with your sound device. Try installing a new device driver or use a different sound device.
NS_E_WMP_NETWORK_RESOURCE_FAILURE 0xC00D11CBL	Windows Media Player encountered a network error. Restart the Player.
NS_E_WMP_UPGRADE_APPLICATION 0xC00D11CCL	Windows Media Player is not installed properly. Reinstall the Player.
NS_E_WMP_UNKNOWN_ERROR 0xC00D11CDL	Windows Media Player encountered an unknown error. For additional assistance, click Web Help.
NS_E_WMP_INVALID_KEY 0xC00D11CEL	Windows Media Player cannot play the file because the required codec is not valid.
NS_E_WMP_CD_ANOTHER_USER 0xC00D11CFL	The CD drive is in use by another user. Wait for the task to complete, and then try again.
NS_E_WMP_DRM_NEEDS_AUTHORIZATION 0xC00D11D0L	Windows Media Player cannot play, sync, or burn the protected file because a problem occurred with the Windows Media Digital Rights Management (DRM) system. You might need to connect to the Internet to update your DRM components. For additional assistance, click Web Help.
NS_E_WMP_BAD_DRIVER 0xC00D11D1L	Windows Media Player cannot play the file because there might be a problem with your sound or video device. Try installing an updated device driver.
NS_E_WMP_ACCESS_DENIED 0xC00D11D2L	Windows Media Player cannot access the file. The file might be in use, you might not have access to the computer where the file is stored, or your proxy settings might not be correct.

Value	Meaning
NS_E_WMP_LICENSE_RESTRICTS 0xC00D11D3L	The content provider prohibits this action. Go to the content provider's online store to get new media usage rights.
NS_E_WMP_INVALID_REQUEST 0xC00D11D4L	Windows Media Player cannot perform the requested action at this time.
NS_E_WMP_CD_STASH_NO_SPACE 0xC00D11D5L	Windows Media Player cannot burn the files because there is not enough free disk space to store the temporary files. Delete some unneeded files on your hard disk, and then try again.
NS_E_WMP_DRM_NEW_HARDWARE 0xC00D11D6L	Your media usage rights have become corrupted or are no longer valid. This might happen if you have replaced hardware components in your computer.
NS_E_WMP_DRM_INVALID_SIG 0xC00D11D7L	The required Windows Media Digital Rights Management (DRM) component cannot be validated. You might be able resolve the problem by reinstalling the Player.
NS_E_WMP_DRM_CANNOT_RESTORE 0xC00D11D8L	You have exceeded your restore limit for the day. Try restoring your media usage rights tomorrow.
NS_E_WMP_BURN_DISC_OVERFLOW 0xC00D11D9L	Some files might not fit on the CD. The required space cannot be calculated accurately because some files might be missing duration information. To ensure the calculation is accurate, play the files that are missing duration information.
NS_E_WMP_DRM_GENERIC_LICENSE_FAILURE 0xC00D11DAL	Windows Media Player cannot verify the file's media usage rights. If you obtained this file from an online store, go to the online store to get the necessary rights.
NS_E_WMP_DRM_NO_SECURE_CLOCK 0xC00D11DBL	It is not possible to sync because this device's internal clock is not set correctly. To set the clock, select the option to set the device clock on the

Value	Meaning
	Privacy tab of the Options dialog box, connect to the Internet, and then sync the device again. For additional assistance, click Web Help.
NS_E_WMP_DRM_NO_RIGHTS 0xC00D11DCL	Windows Media Player cannot play, burn, rip, or sync the protected file because you do not have the appropriate rights.
NS_E_WMP_DRM_INDIV_FAILED 0xC00D11DDL	Windows Media Player encountered an error during upgrade.
NS_E_WMP_SERVER_NONEWCONNECTIONS 0xC00D11DEL	Windows Media Player cannot connect to the server because it is not accepting any new connections. This could be because it has reached its maximum connection limit. Please try again later.
NS_E_WMP_MULTIPLE_ERROR_IN_PLAYLIST 0xC00D11DFL	A number of queued files cannot be played. To find information about the problem, click the Now Playing tab, and then click the icon next to each file in the List pane.
NS_E_WMP_IMAPI2_ERASE_FAIL 0xC00D11E0L	Windows Media Player encountered an error while erasing the rewritable CD or DVD. Verify that the CD or DVD burner is connected properly and that the disc is clean and not damaged.
NS_E_WMP_IMAPI2_ERASE_DEVICE_BUSY 0xC00D11E1L	Windows Media Player cannot erase the rewritable CD or DVD. Verify that the CD or DVD burner is connected properly and that the disc is clean and not damaged. If the burner is already in use, wait until the current task finishes or quit other programs that might be using the burner.
NS_E_WMP_DRM_COMPONENT_FAILURE 0xC00D11E2L	A Windows Media Digital Rights Management (DRM) component encountered a problem. If you are trying to use a file that you obtained from an online store, try going to the online store and getting



Value	Meaning
	the appropriate usage rights.
NS_E_WMP_DRM_NO_DEVICE_CERT 0xC00D11E3L	It is not possible to obtain device's certificate. Please contact the device manufacturer for a firmware update or for other steps to resolve this problem.
NS_E_WMP_SERVER_SECURITY_ERROR 0xC00D11E4L	Windows Media Player encountered an error when connecting to the server. The security information from the server could not be validated.
NS_E_WMP_AUDIO_DEVICE_LOST 0xC00D11E5L	An audio device was disconnected or reconfigured. Verify that the audio device is connected, and then try to play the item again.
NS_E_WMP_IMAPI_MEDIA_INCOMPATIBLE 0xC00D11E6L	Windows Media Player could not complete burning because the disc is not compatible with your drive. Try inserting a different kind of recordable media or use a disc that supports a write speed that is compatible with your drive.
NS_E_SYNCWIZ_DEVICE_FULL 0xC00D11EEL	Windows Media Player cannot save the sync settings because your device is full. Delete some unneeded files on your device and then try again.
NS_E_SYNCWIZ_CANNOT_CHANGE_SETTINGS 0xC00D11EFL	It is not possible to change sync settings at this time. Try again later.
NS_E_TRANSCODE_DELETECACHEERROR 0xC00D11F0L	Windows Media Player cannot delete these files currently. If the Player is synchronizing, wait until it is complete and then try again.
NS_E_CD_NO_BUFFERS_READ 0xC00D11F8L	Windows Media Player could not use digital mode to read the CD. The Player has automatically switched the CD drive to analog mode. To switch back to digital mode, use the Devices tab. For additional assistance, click Web Help.
NS_E_CD_EMPTY_TRACK_QUEUE	No CD track was specified for

Value	Meaning
0xC00D11F9L	playback.
NS_E_CD_NO_READER 0xC00D11FAL	The CD filter was not able to create the CD reader.
NS_E_CD_ISRC_INVALID 0xC00D11FBL	Invalid ISRC code.
NS_E_CD_MEDIA_CATALOG_NUMBER_INVALID 0xC00D11FCL	Invalid Media Catalog Number.
NS_E_SLOW_READ_DIGITAL_WITH_ERRORCORRECTION 0xC00D11FDL	Windows Media Player cannot play audio CDs correctly because the CD drive is slow and error correction is turned on. To increase performance, turn off playback error correction for this drive.
NS_E_CD_SPEEDDETECT_NOT_ENOUGH_READS 0xC00D11FEL	Windows Media Player cannot estimate the CD drive's playback speed because the CD track is too short.
NS_E_CD_QUEUEING_DISABLED 0xC00D11FFL	Cannot queue the CD track because queuing is not enabled.
NS_E_WMP_DRM_ACQUIRING_LICENSE 0xC00D1202L	Windows Media Player cannot download additional media usage rights until the current download is complete.
NS_E_WMP_DRM_LICENSE_EXPIRED 0xC00D1203L	The media usage rights for this file have expired or are no longer valid. If you obtained the file from an online store, sign in to the store, and then try again.
NS_E_WMP_DRM_LICENSE_NOTACQUIRED 0xC00D1204L	Windows Media Player cannot download the media usage rights for the file. If you obtained the file from an online store, sign in to the store, and then try again.
NS_E_WMP_DRM_LICENSE_NOTENABLED 0xC00D1205L	The media usage rights for this file are not yet valid. To see when they will become valid, right-click the file in the library, click Properties, and then click the Media Usage Rights tab.
NS_E_WMP_DRM_LICENSE_UNUSABLE 0xC00D1206L	The media usage rights for this file are not valid. If you

Value	Meaning
	obtained this file from an online store, contact the store for assistance.
NS_E_WMP_DRM_LICENSE_CONTENT_REVOKED 0xC00D1207L	The content provider has revoked the media usage rights for this file. If you obtained this file from an online store, ask the store if a new version of the file is available.
NS_E_WMP_DRM_LICENSE_NOSAP 0xC00D1208L	The media usage rights for this file require a feature that is not supported in your current version of Windows Media Player or your current version of Windows. Try installing the latest version of the Player. If you obtained this file from an online store, contact the store for further assistance.
NS_E_WMP_DRM_UNABLE_TO_ACQUIRE_LICENSE 0xC00D1209L	Windows Media Player cannot download media usage rights at this time. Try again later.
NS_E_WMP_LICENSE_REQUIRED 0xC00D120AL	Windows Media Player cannot play, burn, or sync the file because the media usage rights are missing. If you obtained the file from an online store, sign in to the store, and then try again.
NS_E_WMP_PROTECTED_CONTENT 0xC00D120BL	Windows Media Player cannot play, burn, or sync the file because the media usage rights are missing. If you obtained the file from an online store, sign in to the store, and then try again.
NS_E_WMP_POLICY_VALUE_NOT_CONFIGURED 0xC00D122AL	Windows Media Player cannot read a policy. This can occur when the policy does not exist in the registry or when the registry cannot be read.
NS_E_PDA_CANNOT_SYNC_FROM_INTERNET 0xC00D1234L	Windows Media Player cannot sync content streamed directly from the Internet. If possible, download the file to your computer, and then try to sync the file.
NS_E_PDA_CANNOT_SYNC_INVALID_PLAYLIST	This playlist is not valid or is

Value	Meaning
0xC00D1235L	corrupted. Create a new playlist using Windows Media Player, then sync the new playlist instead.
NS_E_PDA_FAILED_TO_SYNCHRONIZE_FILE 0xC00D1236L	Windows Media Player encountered a problem while synchronizing the file to the device. For additional assistance, click Web Help.
NS_E_PDA_SYNC_FAILED 0xC00D1237L	Windows Media Player encountered an error while synchronizing to the device.
NS_E_PDA_DELETE_FAILED 0xC00D1238L	Windows Media Player cannot delete a file from the device.
NS_E_PDA_FAILED_TO_RETRIEVE_FILE 0xC00D1239L	Windows Media Player cannot copy a file from the device to your library.
NS_E_PDA_DEVICE_NOT_RESPONDING 0xC00D123AL	Windows Media Player cannot communicate with the device because the device is not responding. Try reconnecting the device, resetting the device, or contacting the device manufacturer for updated firmware.
NS_E_PDA_FAILED_TO_TRANSCODE_PHOTO 0xC00D123BL	Windows Media Player cannot sync the picture to the device because a problem occurred while converting the file to another quality level or format. The original file might be damaged or corrupted.
NS_E_PDA_FAILED_TO_ENCRYPT_TRANSCODED_FILE 0xC00D123CL	Windows Media Player cannot convert the file. The file might have been encrypted by the Encrypted File System (EFS). Try decrypting the file first and then synchronizing it. For information about how to decrypt a file, see Windows Help and Support.
NS_E_PDA_CANNOT_TRANSCODE_TO_AUDIO 0xC00D123DL	Your device requires that this file be converted in order to play on the device. However, the device either does not support playing audio, or Windows Media Player cannot convert the file to an audio format that is supported by

Value	Meaning
	the device.
NS_E_PDA_CANNOT_TRANSCODE_TO_VIDEO 0xC00D123EL	Your device requires that this file be converted in order to play on the device. However, the device either does not support playing video, or Windows Media Player cannot convert the file to a video format that is supported by the device.
NS_E_PDA_CANNOT_TRANSCODE_TO_IMAGE 0xC00D123FL	Your device requires that this file be converted in order to play on the device. However, the device either does not support displaying pictures, or Windows Media Player cannot convert the file to a picture format that is supported by the device.
NS_E_PDA_RETRIEVED_FILE_FILENAME_TOO_LONG 0xC00D1240L	Windows Media Player cannot sync the file to your computer because the file name is too long. Try renaming the file on the device.
NS_E_PDA_CEWMDM_DRM_ERROR 0xC00D1241L	Windows Media Player cannot sync the file because the device is not responding. This typically occurs when there is a problem with the device firmware. For additional assistance, click Web Help.
NS_E_INCOMPLETE_PLAYLIST 0xC00D1242L	Incomplete playlist.
NS_E_PDA_SYNC_RUNNING 0xC00D1243L	It is not possible to perform the requested action because sync is in progress. You can either stop sync or wait for it to complete, and then try again.
NS_E_PDA_SYNC_LOGIN_ERROR 0xC00D1244L	Windows Media Player cannot sync the subscription content because you are not signed in to the online store that provided it. Sign in to the online store, and then try again.
NS_E_PDA_TRANSCODE_CODEC_NOT_FOUND 0xC00D1245L	Windows Media Player cannot convert the file to the format required by the device. One or more codecs required to

Value	Meaning
	convert the file could not be found.
NS_E_CANNOT_SYNC_DRM_TO_NON_JANUS_DEVICE 0xC00D1246L	It is not possible to sync subscription files to this device.
NS_E_CANNOT_SYNC_PREVIOUS_SYNC_RUNNING 0xC00D1247L	Your device is operating slowly or is not responding. Until the device responds, it is not possible to sync again. To return the device to normal operation, try disconnecting it from the computer or resetting it.
NS_E_WMP_HWND_NOTFOUND 0xC00D125CL	The Windows Media Player download manager cannot function properly because the Player main window cannot be found. Try restarting the Player.
NS_E_BKGDOWNLOAD_WRONG_NO_FILES 0xC00D125DL	Windows Media Player encountered a download that has the wrong number of files. This might occur if another program is trying to create jobs with the same signature as the Player.
NS_E_BKGDOWNLOAD_COMPLETECANCELLEDJOB 0xC00D125EL	Windows Media Player tried to complete a download that was already canceled. The file will not be available.
NS_E_BKGDOWNLOAD_CANCELCOMPLETEDJOB 0xC00D125FL	Windows Media Player tried to cancel a download that was already completed. The file will not be removed.
NS_E_BKGDOWNLOAD_NOJOBPOINTER 0xC00D1260L	Windows Media Player is trying to access a download that is not valid.
NS_E_BKGDOWNLOAD_INVALIDJOBSIGNATURE 0xC00D1261L	This download was not created by Windows Media Player.
NS_E_BKGDOWNLOAD_FAILED_TO_CREATE_TEMPFILE 0xC00D1262L	The Windows Media Player download manager cannot create a temporary file name. This might occur if the path is not valid or if the disk is full.
NS_E_BKGDOWNLOAD_PLUGIN_FAILEDINITIALIZE 0xC00D1263L	The Windows Media Player download manager plug-in cannot start. This might occur if the system is out of

Value	Meaning
	resources.
NS_E_BKGDOWNLOAD_PLUGIN_FAILEDTOMOVEFILE 0xC00D1264L	The Windows Media Player download manager cannot move the file.
NS_E_BKGDOWNLOAD_CALLFUNCFAILED 0xC00D1265L	The Windows Media Player download manager cannot perform a task because the system has no resources to allocate.
NS_E_BKGDOWNLOAD_CALLFUNCTIMEOUT 0xC00D1266L	The Windows Media Player download manager cannot perform a task because the task took too long to run.
NS_E_BKGDOWNLOAD_CALLFUNCENDED 0xC00D1267L	The Windows Media Player download manager cannot perform a task because the Player is terminating the service. The task will be recovered when the Player restarts.
NS_E_BKGDOWNLOAD_WMDUNPACKFAILED 0xC00D1268L	The Windows Media Player download manager cannot expand a WMD file. The file will be deleted and the operation will not be completed successfully.
NS_E_BKGDOWNLOAD_FAILEDINITIALIZE 0xC00D1269L	The Windows Media Player download manager cannot start. This might occur if the system is out of resources.
NS_E_INTERFACE_NOT_REGISTERED_IN_GIT 0xC00D126AL	Windows Media Player cannot access a required functionality. This might occur if the wrong system files or Player DLLs are loaded.
NS_E_BKGDOWNLOAD_INVALID_FILE_NAME 0xC00D126BL	Windows Media Player cannot get the file name of the requested download. The requested download will be canceled.
NS_E_IMAGE_DOWNLOAD_FAILED 0xC00D128EL	Windows Media Player encountered an error while downloading an image.
NS_E_WMP_UDRM_NOUSERLIST 0xC00D12C0L	Windows Media Player cannot update your media usage rights because the Player cannot verify the list of activated users of this

Value	Meaning
	computer.
NS_E_WMP_DRM_NOT_ACQUIRING 0xC00D12C1L	Windows Media Player is trying to acquire media usage rights for a file that is no longer being used. Rights acquisition will stop.
NS_E_WMP_BSTR_TOO_LONG 0xC00D12F2L	The parameter is not valid.
NS_E_WMP_AUTOPLAY_INVALID_STATE 0xC00D12FCL	The state is not valid for this request.
NS_E_WMP_COMPONENT_REVOKED 0xC00D1306L	Windows Media Player cannot play this file until you complete the software component upgrade. After the component has been upgraded, try to play the file again.
NS_E_CURL_NOTSAFE 0xC00D1324L	The URL is not safe for the operation specified.
NS_E_CURL_INVALIDCHAR 0xC00D1325L	The URL contains one or more characters that are not valid.
NS_E_CURL_INVALIDHOSTNAME 0xC00D1326L	The URL contains a host name that is not valid.
NS_E_CURL_INVALIDPATH 0xC00D1327L	The URL contains a path that is not valid.
NS_E_CURL_INVALIDSCHEME 0xC00D1328L	The URL contains a scheme that is not valid.
NS_E_CURL_INVALIDURL 0xC00D1329L	The URL is not valid.
NS_E_CURL_CANTWALK 0xC00D132BL	Windows Media Player cannot play the file. If you clicked a link on a Web page, the link might not be valid.
NS_E_CURL_INVALIDPORT 0xC00D132CL	The URL port is not valid.
NS_E_CURLHELPER_NOTADIRECTORY 0xC00D132DL	The URL is not a directory.
NS_E_CURLHELPER_NOTAFILE 0xC00D132EL	The URL is not a file.
NS_E_CURL_CANTDECODE	The URL contains characters



Value	Meaning
0xC00D132FL	that cannot be decoded. The URL might be truncated or incomplete.
NS_E_CURLHELPER_NOTRELATIVE 0xC00D1330L	The specified URL is not a relative URL.
NS_E_CURL_INVALIDBUFFERSIZE 0xC00D1331L	The buffer is smaller than the size specified.
NS_E_SUBSCRIPTIONSERVICE_PLAYBACK_DISALLOWED 0xC00D1356L	The content provider has not granted you the right to play this file. Go to the content provider's online store to get play rights.
NS_E_CANNOT_BUY_OR_DOWNLOAD_FROM_MULTIPLE_SERVICES 0xC00D1357L	Windows Media Player cannot purchase or download content from multiple online stores.
NS_E_CANNOT_BUY_OR_DOWNLOAD_CONTENT 0xC00D1358L	The file cannot be purchased or downloaded. The file might not be available from the online store.
NS_E_NOT_CONTENT_PARTNER_TRACK 0xC00D135AL	The provider of this file cannot be identified.
NS_E_TRACK_DOWNLOAD_REQUIRES_ALBUM_PURCHASE 0xC00D135BL	The file is only available for download when you buy the entire album.
NS_E_TRACK_DOWNLOAD_REQUIRES_PURCHASE 0xC00D135CL	You must buy the file before you can download it.
NS_E_TRACK_PURCHASE_MAXIMUM_EXCEEDED 0xC00D135DL	You have exceeded the maximum number of files that can be purchased in a single transaction.
NS_E_SUBSCRIPTIONSERVICE_LOGIN_FAILED 0xC00D135FL	Windows Media Player cannot sign in to the online store. Verify that you are using the correct user name and password. If the problem persists, the store may be temporarily unavailable.
NS_E_SUBSCRIPTIONSERVICE_DOWNLOAD_TIMEOUT 0xC00D1360L	Windows Media Player cannot download this item because the server is not responding. The server might be temporarily unavailable or you may have lost your Internet connection.
NS_E_CONTENT_PARTNER_STILL_INITIALIZING	Content Partner still

Value	Meaning
0xC00D1362L	initializing.
NS_E_OPEN_CONTAINING_FOLDER_FAILED 0xC00D1363L	The folder could not be opened. The folder may have been moved or deleted.
NS_E_ADVANCEDEDIT_TOO_MANY_PICTURES 0xC00D136AL	Windows Media Player could not add all of the images to the file because the images exceeded the 7 megabyte (MB) limit.
NS_E_REDIRECT 0xC00D1388L	The client redirected to another server.
NS_E_STALE_PRESENTATION 0xC00D1389L	The streaming media description is no longer current.
NS_E_NAMESPACE_WRONG_PERSIST 0xC00D138AL	It is not possible to create a persistent namespace node under a transient parent node.
NS_E_NAMESPACE_WRONG_TYPE 0xC00D138BL	It is not possible to store a value in a namespace node that has a different value type.
NS_E_NAMESPACE_NODE_CONFLICT 0xC00D138CL	It is not possible to remove the root namespace node.
NS_E_NAMESPACE_NODE_NOT_FOUND 0xC00D138DL	The specified namespace node could not be found.
NS_E_NAMESPACE_BUFFER_TOO_SMALL 0xC00D138EL	The buffer supplied to hold namespace node string is too small.
NS_E_NAMESPACE_TOO_MANY_CALLBACKS 0xC00D138FL	The callback list on a namespace node is at the maximum size.
NS_E_NAMESPACE_DUPLICATE_CALLBACK 0xC00D1390L	It is not possible to register an already-registered callback on a namespace node.
NS_E_NAMESPACE_CALLBACK_NOT_FOUND 0xC00D1391L	Cannot find the callback in the namespace when attempting to remove the callback.
NS_E_NAMESPACE_NAME_TOO_LONG 0xC00D1392L	The namespace node name exceeds the allowed maximum length.
NS_E_NAMESPACE_DUPLICATE_NAME 0xC00D1393L	Cannot create a namespace node that already exists.

Value	Meaning
NS_E_NAMESPACE_EMPTY_NAME 0xC00D1394L	The namespace node name cannot be a null string.
NS_E_NAMESPACE_INDEX_TOO_LARGE 0xC00D1395L	Finding a child namespace node by index failed because the index exceeded the number of children.
NS_E_NAMESPACE_BAD_NAME 0xC00D1396L	The namespace node name is invalid.
NS_E_NAMESPACE_WRONG_SECURITY 0xC00D1397L	It is not possible to store a value in a namespace node that has a different security type.
NS_E_CACHE_ARCHIVE_CONFLICT 0xC00D13ECL	The archive request conflicts with other requests in progress.
NS_E_CACHE_ORIGIN_SERVER_NOT_FOUND 0xC00D13EDL	The specified origin server cannot be found.
NS_E_CACHE_ORIGIN_SERVER_TIMEOUT 0xC00D13EEL	The specified origin server is not responding.
NS_E_CACHE_NOT_BROADCAST 0xC00D13EFL	The internal code for HTTP status code 412 Precondition Failed due to not broadcast type.
NS_E_CACHE_CANNOT_BE_CACHED 0xC00D13F0L	The internal code for HTTP status code 403 Forbidden due to not cacheable.
NS_E_CACHE_NOT_MODIFIED 0xC00D13F1L	The internal code for HTTP status code 304 Not Modified.
NS_E_CANNOT_REMOVE_PUBLISHING_POINT 0xC00D1450L	It is not possible to remove a cache or proxy publishing point.
NS_E_CANNOT_REMOVE_PLUGIN 0xC00D1451L	It is not possible to remove the last instance of a type of plug-in.
NS_E_WRONG_PUBLISHING_POINT_TYPE 0xC00D1452L	Cache and proxy publishing points do not support this property or method.
NS_E_UNSUPPORTED_LOAD_TYPE 0xC00D1453L	The plug-in does not support the specified load type.
NS_E_INVALID_PLUGIN_LOAD_TYPE_CONFIGURATION 0xC00D1454L	The plug-in does not support any load types. The plug-in must support at least one load

Value	Meaning
	type.
NS_E_INVALID_PUBLISHING_POINT_NAME 0xC00D1455L	The publishing point name is invalid.
NS_E_TOO_MANY_MULTICAST_SINKS 0xC00D1456L	Only one multicast data writer plug-in can be enabled for a publishing point.
NS_E_PUBLISHING_POINT_INVALID_REQUEST_WHILE_STARTED 0xC00D1457L	The requested operation cannot be completed while the publishing point is started.
NS_E_MULTICAST_PLUGIN_NOT_ENABLED 0xC00D1458L	A multicast data writer plug-in must be enabled in order for this operation to be completed.
NS_E_INVALID_OPERATING_SYSTEM_VERSION 0xC00D1459L	This feature requires Windows Server 2003, Enterprise Edition.
NS_E_PUBLISHING_POINT_REMOVED 0xC00D145AL	The requested operation cannot be completed because the specified publishing point has been removed.
NS_E_INVALID_PUSH_PUBLISHING_POINT_START_REQUEST 0xC00D145BL	Push publishing points are started when the encoder starts pushing the stream. This publishing point cannot be started by the server administrator.
NS_E_UNSUPPORTED_LANGUAGE 0xC00D145CL	The specified language is not supported.
NS_E_WRONG_OS_VERSION 0xC00D145DL	Windows Media Services will only run on Windows Server 2003, Standard Edition and Windows Server 2003, Enterprise Edition.
NS_E_PUBLISHING_POINT_STOPPED 0xC00D145EL	The operation cannot be completed because the publishing point has been stopped.
NS_E_PLAYLIST_ENTRY_ALREADY_PLAYING 0xC00D14B4L	The playlist entry is already playing.
NS_E_EMPTY_PLAYLIST 0xC00D14B5L	The playlist or directory you are requesting does not contain content.
NS_E_PLAYLIST_PARSE_FAILURE 0xC00D14B6L	The server was unable to parse the requested playlist

Value	Meaning
	file.
NS_E_PLAYLIST_UNSUPPORTED_ENTRY 0xC00D14B7L	The requested operation is not supported for this type of playlist entry.
NS_E_PLAYLIST_ENTRY_NOT_IN_PLAYLIST 0xC00D14B8L	Cannot jump to a playlist entry that is not inserted in the playlist.
NS_E_PLAYLIST_ENTRY_SEEK 0xC00D14B9L	Cannot seek to the desired playlist entry.
NS_E_PLAYLIST_RECURSIVE_PLAYLISTS 0xC00D14BAL	Cannot play recursive playlist.
NS_E_PLAYLIST_TOO_MANY_NESTED_PLAYLISTS 0xC00D14BBL	The number of nested playlists exceeded the limit the server can handle.
NS_E_PLAYLIST_SHUTDOWN 0xC00D14BCL	Cannot execute the requested operation because the playlist has been shut down by the Media Server.
NS_E_PLAYLIST_END_RECEDING 0xC00D14BDL	The playlist has ended while receding.
NS_E_DATAPATH_NO_SINK 0xC00D1518L	The data path does not have an associated data writer plug-in.
NS_E_INVALID_PUSH_TEMPLATE 0xC00D151AL	The specified push template is invalid.
NS_E_INVALID_PUSH_PUBLISHING_POINT 0xC00D151BL	The specified push publishing point is invalid.
NS_E_CRITICAL_ERROR 0xC00D151CL	The requested operation cannot be performed because the server or publishing point is in a critical error state.
NS_E_NO_NEW_CONNECTIONS 0xC00D151DL	The content can not be played because the server is not currently accepting connections. Try connecting at a later time.
NS_E_WSX_INVALID_VERSION 0xC00D151EL	The version of this playlist is not supported by the server.
NS_E_HEADER_MISMATCH 0xC00D151FL	The command does not apply to the current media header user by a server component.

Value	Meaning
NS_E_PUSH_DUPLICATE_PUBLISHING_POINT_NAME 0xC00D1520L	The specified publishing point name is already in use.
NS_E_NO_SCRIPT_ENGINE 0xC00D157CL	There is no script engine available for this file.
NS_E_PLUGIN_ERROR_REPORTED 0xC00D157DL	The plug-in has reported an error. See the Troubleshooting tab or the NT Application Event Log for details.
NS_E_SOURCE_PLUGIN_NOT_FOUND 0xC00D157EL	No enabled data source plug-in is available to access the requested content.
NS_E_PLAYLIST_PLUGIN_NOT_FOUND 0xC00D157FL	No enabled playlist parser plug-in is available to access the requested content.
NS_E_DATA_SOURCE_ENUMERATION_NOT_SUPPORTED 0xC00D1580L	The data source plug-in does not support enumeration.
NS_E_MEDIA_PARSER_INVALID_FORMAT 0xC00D1581L	The server cannot stream the selected file because it is either damaged or corrupt. Select a different file.
NS_E_SCRIPT_DEBUGGER_NOT_INSTALLED 0xC00D1582L	The plug-in cannot be enabled because a compatible script debugger is not installed on this system. Install a script debugger, or disable the script debugger option on the general tab of the plug-in's properties page and try again.
NS_E_FEATURE_REQUIRES_ENTERPRISE_SERVER 0xC00D1583L	The plug-in cannot be loaded because it requires Windows Server 2003, Enterprise Edition.
NS_E_WIZARD_RUNNING 0xC00D1584L	Another wizard is currently running. Please close the other wizard or wait until it finishes before attempting to run this wizard again.
NS_E_INVALID_LOG_URL 0xC00D1585L	Invalid log URL. Multicast logging URL must look like "http://servername/isapibackend.dll" .
NS_E_INVALID_MTU_RANGE 0xC00D1586L	Invalid MTU specified. The valid range for maximum packet size is between 36 and 65507 bytes .

Value	Meaning
NS_E_INVALID_PLAY_STATISTICS 0xC00D1587L	Invalid play statistics for logging .
NS_E_LOG_NEED_TO_BE_SKIPPED 0xC00D1588L	The log needs to be skipped .
NS_E_HTTP_TEXT_DATACONTAINER_SIZE_LIMIT_EXCEEDED 0xC00D1589L	The size of the data exceeded the limit the WMS HTTP Download Data Source plugin can handle.
NS_E_PORT_IN_USE 0xC00D158AL	One usage of each socket address (protocol/network address/port) is permitted. Verify that other services or applications are not attempting to use the same port and then try to enable the plug-in again.
NS_E_PORT_IN_USE_HTTP 0xC00D158BL	One usage of each socket address (protocol/network address/port) is permitted. Verify that other services (such as IIS) or applications are not attempting to use the same port and then try to enable the plug-in again.
NS_E_HTTP_TEXT_DATACONTAINER_INVALID_SERVER_RESPONSE 0xC00D158CL	The WMS HTTP Download Data Source plugin was unable to receive the remote server's response.
NS_E_ARCHIVE_REACH_QUOTA 0xC00D158DL	The archive plug-in has reached its quota.
NS_E_ARCHIVE_ABORT_DUE_TO_BCAST 0xC00D158EL	The archive plug-in aborted because the source was from broadcast.
NS_E_ARCHIVE_GAP_DETECTED 0xC00D158FL	The archive plug-in detected an interrupt in the source.
NS_E_AUTHORIZATION_FILE_NOT_FOUND 0xC00D1590L	The system cannot find the file specified.
NS_E_BAD_MARKIN 0xC00D1B58L	The mark-in time should be greater than 0 and less than the mark-out time.
NS_E_BAD_MARKOUT 0xC00D1B59L	The mark-out time should be greater than the mark-in time and less than the file duration.
NS_E_NOMATCHING_MEDIASOURCE	No matching media type is

Value	Meaning
0xC00D1B5AL	found in the source %1.
NS_E_UNSUPPORTED_SOURCETYPE 0xC00D1B5BL	The specified source type is not supported.
NS_E_TOO_MANY_AUDIO 0xC00D1B5CL	It is not possible to specify more than one audio input.
NS_E_TOO_MANY_VIDEO 0xC00D1B5DL	It is not possible to specify more than two video inputs.
NS_E_NOMATCHING_ELEMENT 0xC00D1B5EL	No matching element is found in the list.
NS_E_MISMATCHED_MEDIACONTENT 0xC00D1B5FL	The profile's media types must match the media types defined for the session.
NS_E_CANNOT_DELETE_ACTIVE_SOURCEGROUP 0xC00D1B60L	It is not possible to remove an active source while encoding.
NS_E_AUDIODEVICE_BUSY 0xC00D1B61L	It is not possible to open the specified audio capture device because it is currently in use.
NS_E_AUDIODEVICE_UNEXPECTED 0xC00D1B62L	It is not possible to open the specified audio capture device because an unexpected error has occurred.
NS_E_AUDIODEVICE_BADFORMAT 0xC00D1B63L	The audio capture device does not support the specified audio format.
NS_E_VIDEODEVICE_BUSY 0xC00D1B64L	It is not possible to open the specified video capture device because it is currently in use.
NS_E_VIDEODEVICE_UNEXPECTED 0xC00D1B65L	It is not possible to open the specified video capture device because an unexpected error has occurred.
NS_E_INVALIDCALL_WHILE_ENCODER_RUNNING 0xC00D1B66L	This operation is not allowed while encoding.
NS_E_NO_PROFILE_IN_SOURCEGROUP 0xC00D1B67L	No profile is set for the source.
NS_E_VIDEODRIVER_UNSTABLE 0xC00D1B68L	The video capture driver returned an unrecoverable error. It is now in an unstable state.
NS_E_VIDCAPSTARTFAILED 0xC00D1B69L	It was not possible to start the video device.



Value	Meaning
NS_E_VIDSOURCECOMPRESSION 0xC00D1B6AL	The video source does not support the requested output format or color depth.
NS_E_VIDSOURCESIZE 0xC00D1B6BL	The video source does not support the requested capture size.
NS_E_ICMQUERYFORMAT 0xC00D1B6CL	It was not possible to obtain output information from the video compressor.
NS_E_VIDCAPCREATEWINDOW 0xC00D1B6DL	It was not possible to create a video capture window.
NS_E_VIDCAPDRVINUSE 0xC00D1B6EL	There is already a stream active on this video device.
NS_E_NO_MEDIAFORMAT_IN_SOURCE 0xC00D1B6FL	No media format is set in source.
NS_E_NO_VALID_OUTPUT_STREAM 0xC00D1B70L	Cannot find a valid output stream from the source.
NS_E_NO_VALID_SOURCE_PLUGIN 0xC00D1B71L	It was not possible to find a valid source plug-in for the specified source.
NS_E_NO_ACTIVE_SOURCEGROUP 0xC00D1B72L	No source is currently active.
NS_E_NO_SCRIPT_STREAM 0xC00D1B73L	No script stream is set in the current source.
NS_E_INVALIDCALL_WHILE_ARCHIVAL_RUNNING 0xC00D1B74L	This operation is not allowed while archiving.
NS_E_INVALIDPACKETSIZE 0xC00D1B75L	The setting for the maximum packet size is not valid.
NS_E_PLUGIN_CLSID_INVALID 0xC00D1B76L	The plug-in CLSID specified is not valid.
NS_E_UNSUPPORTED_ARCHIVETYPE 0xC00D1B77L	This archive type is not supported.
NS_E_UNSUPPORTED_ARCHIVEOPERATION 0xC00D1B78L	This archive operation is not supported.
NS_E_ARCHIVE_FILENAME_NOTSET 0xC00D1B79L	The local archive file name was not set.
NS_E_SOURCEGROUP_NOTPREPARED 0xC00D1B7AL	The source is not yet prepared.

Value	Meaning
NS_E_PROFILE_MISMATCH 0xC00D1B7BL	Profiles on the sources do not match.
NS_E_INCORRECTCLIPSETTINGS 0xC00D1B7CL	The specified crop values are not valid.
NS_E_NOSTATSAVAILABLE 0xC00D1B7DL	No statistics are available at this time.
NS_E_NOTARCHIVING 0xC00D1B7EL	The encoder is not archiving.
NS_E_INVALIDCALL_WHILE_ENCODER_STOPPED 0xC00D1B7FL	This operation is only allowed during encoding.
NS_E_NOSOURCEGROUPS 0xC00D1B80L	This SourceGroupCollection doesn't contain any SourceGroups.
NS_E_INVALIDINPUTFPS 0xC00D1B81L	This source does not have a frame rate of 30 fps. Therefore, it is not possible to apply the inverse telecine filter to the source.
NS_E_NO_DATAVIEW_SUPPORT 0xC00D1B82L	It is not possible to display your source or output video in the Video panel.
NS_E_CODEC_UNAVAILABLE 0xC00D1B83L	One or more codecs required to open this content could not be found.
NS_E_ARCHIVE_SAME_AS_INPUT 0xC00D1B84L	The archive file has the same name as an input file. Change one of the names before continuing.
NS_E_SOURCE_NOTSPECIFIED 0xC00D1B85L	The source has not been set up completely.
NS_E_NO_REALTIME_TIMECOMPRESSION 0xC00D1B86L	It is not possible to apply time compression to a broadcast session.
NS_E_UNSUPPORTED_ENCODER_DEVICE 0xC00D1B87L	It is not possible to open this device.
NS_E_UNEXPECTED_DISPLAY_SETTINGS 0xC00D1B88L	It is not possible to start encoding because the display size or color has changed since the current session was defined. Restore the previous settings or create a new session.

Value	Meaning
NS_E_NO_AUDIODATA 0xC00D1B89L	No audio data has been received for several seconds. Check the audio source and restart the encoder.
NS_E_INPUTSOURCE_PROBLEM 0xC00D1B8AL	One or all of the specified sources are not working properly. Check that the sources are configured correctly.
NS_E_WME_VERSION_MISMATCH 0xC00D1B8BL	The supplied configuration file is not supported by this version of the encoder.
NS_E_NO_REALTIME_PREPROCESS 0xC00D1B8CL	It is not possible to use image preprocessing with live encoding.
NS_E_NO_REPEAT_PREPROCESS 0xC00D1B8DL	It is not possible to use two-pass encoding when the source is set to loop.
NS_E_CANNOT_PAUSE_LIVEBROADCAST 0xC00D1B8EL	It is not possible to pause encoding during a broadcast.
NS_E_DRM_PROFILE_NOT_SET 0xC00D1B8FL	A DRM profile has not been set for the current session.
NS_E_DUPLICATE_DRMPROFILE 0xC00D1B90L	The profile ID is already used by a DRM profile. Specify a different profile ID.
NS_E_INVALID_DEVICE 0xC00D1B91L	The setting of the selected device does not support control for playing back tapes.
NS_E_SPEECHEDL_ON_NON_MIXEDMODE 0xC00D1B92L	You must specify a mixed voice and audio mode in order to use an optimization definition file.
NS_E_DRM_PASSWORD_TOO_LONG 0xC00D1B93L	The specified password is too long. Type a password with fewer than 8 characters.
NS_E_DEVCONTROL_FAILED_SEEK 0xC00D1B94L	It is not possible to seek to the specified mark-in point.
NS_E_INTERLACE_REQUIRE_SAMESIZE 0xC00D1B95L	When you choose to maintain the interlacing in your video, the output video size must match the input video size.
NS_E_TOO_MANY_DEVICECONTROL 0xC00D1B96L	Only one device control plug-in can control a device.

Value	Meaning
NS_E_NO_MULTIPASS_FOR_LIVEDEVICE 0xC00D1B97L	You must also enable storing content to hard disk temporarily in order to use two-pass encoding with the input device.
NS_E_MISSING_AUDIENCE 0xC00D1B98L	An audience is missing from the output stream configuration.
NS_E_AUDIENCE_CONTENTTYPE_MISMATCH 0xC00D1B99L	All audiences in the output tree must have the same content type.
NS_E_MISSING_SOURCE_INDEX 0xC00D1B9AL	A source index is missing from the output stream configuration.
NS_E_NUM_LANGUAGE_MISMATCH 0xC00D1B9BL	The same source index in different audiences should have the same number of languages.
NS_E_LANGUAGE_MISMATCH 0xC00D1B9CL	The same source index in different audiences should have the same languages.
NS_E_VBRMODE_MISMATCH 0xC00D1B9DL	The same source index in different audiences should use the same VBR encoding mode.
NS_E_INVALID_INPUT_AUDIENCE_INDEX 0xC00D1B9EL	The bit rate index specified is not valid.
NS_E_INVALID_INPUT_LANGUAGE 0xC00D1B9FL	The specified language is not valid.
NS_E_INVALID_INPUT_STREAM 0xC00D1BA0L	The specified source type is not valid.
NS_E_EXPECT_MONO_WAV_INPUT 0xC00D1BA1L	The source must be a mono channel .wav file.
NS_E_INPUT_WAVFORMAT_MISMATCH 0xC00D1BA2L	All the source .wav files must have the same format.
NS_E_RECORDQ_DISK_FULL 0xC00D1BA3L	The hard disk being used for temporary storage of content has reached the minimum allowed disk space. Create more space on the hard disk and restart encoding.
NS_E_NO_PAL_INVERSE_TELECINE 0xC00D1BA4L	It is not possible to apply the inverse telecine feature to PAL content.

Value	Meaning
NS_E_ACTIVE_SG_DEVICE_DISCONNECTED 0xC00D1BA5L	A capture device in the current active source is no longer available.
NS_E_ACTIVE_SG_DEVICE_CONTROL_DISCONNECTED 0xC00D1BA6L	A device used in the current active source for device control is no longer available.
NS_E_NO_FRAMES_SUBMITTED_TO_ANALYZER 0xC00D1BA7L	No frames have been submitted to the analyzer for analysis.
NS_E_INPUT_DOESNOT_SUPPORT_SMPTE 0xC00D1BA8L	The source video does not support time codes.
NS_E_NO_SMPTE_WITH_MULTIPLE_SOURCEGROUPS 0xC00D1BA9L	It is not possible to generate a time code when there are multiple sources in a session.
NS_E_BAD_CONTENTEDL 0xC00D1BAAL	The voice codec optimization definition file can not be found or is corrupted.
NS_E_INTERLACEMODE_MISMATCH 0xC00D1BABL	The same source index in different audiences should have the same interlace mode.
NS_E_NONSQUAREPIXELMODE_MISMATCH 0xC00D1BACL	The same source index in different audiences should have the same nonsquare pixel mode.
NS_E_SMPTEMODE_MISMATCH 0xC00D1BADL	The same source index in different audiences should have the same time code mode.
NS_E_END_OF_TAPE 0xC00D1BAEL	Either the end of the tape has been reached or there is no tape. Check the device and tape.
NS_E_NO_MEDIA_IN_AUDIENCE 0xC00D1BAFL	No audio or video input has been specified.
NS_E_NO_AUDIENCES 0xC00D1BB0L	The profile must contain a bit rate.
NS_E_NO_AUDIO_COMPAT 0xC00D1BB1L	You must specify at least one audio stream to be compatible with Windows Media Player 7.1.
NS_E_INVALID_VBR_COMPAT 0xC00D1BB2L	Using a VBR encoding mode is not compatible with Windows Media Player 7.1.

Value	Meaning
NS_E_NO_PROFILE_NAME 0xC00D1BB3L	You must specify a profile name.
NS_E_INVALID_VBR_WITH_UNCOMP 0xC00D1BB4L	It is not possible to use a VBR encoding mode with uncompressed audio or video.
NS_E_MULTIPLE_VBR_AUDIENCES 0xC00D1BB5L	It is not possible to use MBR encoding with VBR encoding.
NS_E_UNCOMP_COMP_COMBINATION 0xC00D1BB6L	It is not possible to mix uncompressed and compressed content in a session.
NS_E_MULTIPLE_AUDIO_CODECS 0xC00D1BB7L	All audiences must use the same audio codec.
NS_E_MULTIPLE_AUDIO_FORMATS 0xC00D1BB8L	All audiences should use the same audio format to be compatible with Windows Media Player 7.1.
NS_E_AUDIO_BITRATE_STEPDOWN 0xC00D1BB9L	The audio bit rate for an audience with a higher total bit rate must be greater than one with a lower total bit rate.
NS_E_INVALID_AUDIO_PEAKRATE 0xC00D1BBAL	The audio peak bit rate setting is not valid.
NS_E_INVALID_AUDIO_PEAKRATE_2 0xC00D1BBBL	The audio peak bit rate setting must be greater than the audio bit rate setting.
NS_E_INVALID_AUDIO_BUFFERMAX 0xC00D1BBCL	The setting for the maximum buffer size for audio is not valid.
NS_E_MULTIPLE_VIDEO_CODECS 0xC00D1BBDL	All audiences must use the same video codec.
NS_E_MULTIPLE_VIDEO_SIZES 0xC00D1BBEL	All audiences should use the same video size to be compatible with Windows Media Player 7.1.
NS_E_INVALID_VIDEO_BITRATE 0xC00D1BBFL	The video bit rate setting is not valid.
NS_E_VIDEO_BITRATE_STEPDOWN 0xC00D1BC0L	The video bit rate for an audience with a higher total bit rate must be greater than one with a lower total bit rate.
NS_E_INVALID_VIDEO_PEAKRATE	The video peak bit rate setting

Value	Meaning
0xC00D1BC1L	is not valid.
NS_E_INVALID_VIDEO_PEAKRATE_2 0xC00D1BC2L	The video peak bit rate setting must be greater than the video bit rate setting.
NS_E_INVALID_VIDEO_WIDTH 0xC00D1BC3L	The video width setting is not valid.
NS_E_INVALID_VIDEO_HEIGHT 0xC00D1BC4L	The video height setting is not valid.
NS_E_INVALID_VIDEO_FPS 0xC00D1BC5L	The video frame rate setting is not valid.
NS_E_INVALID_VIDEO_KEYFRAME 0xC00D1BC6L	The video key frame setting is not valid.
NS_E_INVALID_VIDEO_IQUALITY 0xC00D1BC7L	The video image quality setting is not valid.
NS_E_INVALID_VIDEO_CQUALITY 0xC00D1BC8L	The video codec quality setting is not valid.
NS_E_INVALID_VIDEO_BUFFER 0xC00D1BC9L	The video buffer setting is not valid.
NS_E_INVALID_VIDEO_BUFFERMAX 0xC00D1BCAL	The setting for the maximum buffer size for video is not valid.
NS_E_INVALID_VIDEO_BUFFERMAX_2 0xC00D1BCBL	The value of the video maximum buffer size setting must be greater than the video buffer size setting.
NS_E_INVALID_VIDEO_WIDTH_ALIGN 0xC00D1BCCL	The alignment of the video width is not valid.
NS_E_INVALID_VIDEO_HEIGHT_ALIGN 0xC00D1BCDL	The alignment of the video height is not valid.
NS_E_MULTIPLE_SCRIPT_BITRATES 0xC00D1BCEL	All bit rates must have the same script bit rate.
NS_E_INVALID_SCRIPT_BITRATE 0xC00D1BCFL	The script bit rate specified is not valid.
NS_E_MULTIPLE_FILE_BITRATES 0xC00D1BD0L	All bit rates must have the same file transfer bit rate.
NS_E_INVALID_FILE_BITRATE 0xC00D1BD1L	The file transfer bit rate is not valid.

Value	Meaning
NS_E_SAME_AS_INPUT_COMBINATION 0xC00D1BD2L	All audiences in a profile should either be same as input or have video width and height specified.
NS_E_SOURCE_CANNOT_LOOP 0xC00D1BD3L	This source type does not support looping.
NS_E_INVALID_FOLDDOWN_COEFFICIENTS 0xC00D1BD4L	The fold-down value needs to be between -144 and 0.
NS_E_DRMPROFILE_NOTFOUND 0xC00D1BD5L	The specified DRM profile does not exist in the system.
NS_E_INVALID_TIMECODE 0xC00D1BD6L	The specified time code is not valid.
NS_E_NO_AUDIO_TIMECOMPRESSION 0xC00D1BD7L	It is not possible to apply time compression to a video-only session.
NS_E_NO_TWOPASS_TIMECOMPRESSION 0xC00D1BD8L	It is not possible to apply time compression to a session that is using two-pass encoding.
NS_E_TIMECODE_REQUIRES_VIDEOSTREAM 0xC00D1BD9L	It is not possible to generate a time code for an audio-only session.
NS_E_NO_MBR_WITH_TIMECODE 0xC00D1BDAL	It is not possible to generate a time code when you are encoding content at multiple bit rates.
NS_E_INVALID_INTERLACEMODE 0xC00D1BDBL	The video codec selected does not support maintaining interlacing in video.
NS_E_INVALID_INTERLACE_COMPAT 0xC00D1BDCL	Maintaining interlacing in video is not compatible with Windows Media Player 7.1.
NS_E_INVALID_NONSQUAREPIXEL_COMPAT 0xC00D1BDDL	Allowing nonsquare pixel output is not compatible with Windows Media Player 7.1.
NS_E_INVALID_SOURCE_WITH_DEVICE_CONTROL 0xC00D1BDEL	Only capture devices can be used with device control.
NS_E_CANNOT_GENERATE_BROADCAST_INFO_FOR_QUALITYVBR 0xC00D1BDFL	It is not possible to generate the stream format file if you are using quality-based VBR encoding for the audio or video stream. Instead use the Windows Media file generated after encoding to create the



Value	Meaning
	announcement file.
NS_E_EXCEED_MAX_DRM_PROFILE_LIMIT 0xC00D1BE0L	It is not possible to create a DRM profile because the maximum number of profiles has been reached. You must delete some DRM profiles before creating new ones.
NS_E_DEVICECONTROL_UNSTABLE 0xC00D1BE1L	The device is in an unstable state. Check that the device is functioning properly and a tape is in place.
NS_E_INVALID_PIXEL_ASPECT_RATIO 0xC00D1BE2L	The pixel aspect ratio value must be between 1 and 255.
NS_E_AUDIENCE__LANGUAGE_CONTENTTYPE_MISMATCH 0xC00D1BE3L	All streams with different languages in the same audience must have same properties.
NS_E_INVALID_PROFILE_CONTENTTYPE 0xC00D1BE4L	The profile must contain at least one audio or video stream.
NS_E_TRANSFORM_PLUGIN_NOT_FOUND 0xC00D1BE5L	The transform plug-in could not be found.
NS_E_TRANSFORM_PLUGIN_INVALID 0xC00D1BE6L	The transform plug-in is not valid. It may be damaged or you may not have the required permissions to access the plug-in.
NS_E_EDL_REQUIRED_FOR_DEVICE_MULTIPASS 0xC00D1BE7L	To use two-pass encoding, you must enable device control and setup an edit decision list (EDL) that has at least one entry.
NS_E_INVALID_VIDEO_WIDTH_FOR_INTERLACED_ENCODING 0xC00D1BE8L	When you choose to maintain the interlacing in your video, the output video size must be a multiple of 4.
NS_E_MARKIN_UNSUPPORTED 0xC00D1BE9L	Markin/Markout is unsupported with this source type.
NS_E_DRM_INVALID_APPLICATION 0xC00D2711L	A problem has occurred in the Digital Rights Management component. Contact product support for this application.
NS_E_DRM_LICENSE_STORE_ERROR 0xC00D2712L	License storage is not working. Contact Microsoft

Value	Meaning
	product support.
NS_E_DRM_SECURE_STORE_ERROR 0xC00D2713L	Secure storage is not working. Contact Microsoft product support.
NS_E_DRM_LICENSE_STORE_SAVE_ERROR 0xC00D2714L	License acquisition did not work. Acquire a new license or contact the content provider for further assistance.
NS_E_DRM_SECURE_STORE_UNLOCK_ERROR 0xC00D2715L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_INVALID_CONTENT 0xC00D2716L	The media file is corrupted. Contact the content provider to get a new file.
NS_E_DRM_UNABLE_TO_OPEN_LICENSE 0xC00D2717L	The license is corrupted. Acquire a new license.
NS_E_DRM_INVALID_LICENSE 0xC00D2718L	The license is corrupted or invalid. Acquire a new license
NS_E_DRM_INVALID_MACHINE 0xC00D2719L	Licenses cannot be copied from one computer to another. Use License Management to transfer licenses, or get a new license for the media file.
NS_E_DRM_ENUM_LICENSE_FAILED 0xC00D271BL	License storage is not working. Contact Microsoft product support.
NS_E_DRM_INVALID_LICENSE_REQUEST 0xC00D271CL	The media file is corrupted. Contact the content provider to get a new file.
NS_E_DRM_UNABLE_TO_INITIALIZE 0xC00D271DL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_ACQUIRE_LICENSE 0xC00D271EL	The license could not be acquired. Try again later.
NS_E_DRM_INVALID_LICENSE_ACQUIRED 0xC00D271FL	License acquisition did not work. Acquire a new license or contact the content provider for further assistance.
NS_E_DRM_NO_RIGHTS 0xC00D2720L	The requested operation cannot be performed on this file.

Value	Meaning
NS_E_DRM_KEY_ERROR 0xC00D2721L	The requested action cannot be performed because a problem occurred with the Windows Media Digital Rights Management (DRM) components on your computer.
NS_E_DRM_ENCRYPT_ERROR 0xC00D2722L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_DECRYPT_ERROR 0xC00D2723L	The media file is corrupted. Contact the content provider to get a new file.
NS_E_DRM_LICENSE_INVALID_XML 0xC00D2725L	The license is corrupted. Acquire a new license.
NS_E_DRM_NEEDS_INDIVIDUALIZATION 0xC00D2728L	A security upgrade is required to perform the operation on this media file.
NS_E_DRM_ALREADY_INDIVIDUALIZED 0xC00D2729L	You already have the latest security components. No upgrade is necessary at this time.
NS_E_DRM_ACTION_NOT_QUERIED 0xC00D272AL	The application cannot perform this action. Contact product support for this application.
NS_E_DRM_ACQUIRING_LICENSE 0xC00D272BL	You cannot begin a new license acquisition process until the current one has been completed.
NS_E_DRM_INDIVIDUALIZING 0xC00D272CL	You cannot begin a new security upgrade until the current one has been completed.
NS_E_BACKUP_RESTORE_FAILURE 0xC00D272DL	Failure in Backup-Restore.
NS_E_BACKUP_RESTORE_BAD_REQUEST_ID 0xC00D272EL	Bad Request ID in Backup-Restore.
NS_E_DRM_PARAMETERS_MISMATCHED 0xC00D272FL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_LICENSE_OBJECT	A license cannot be created for this media file. Reinstall the

Value	Meaning
0xC00D2730L	application.
NS_E_DRM_UNABLE_TO_CREATE_INDI_OBJECT 0xC00D2731L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_ENCRYPT_OBJECT 0xC00D2732L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_DECRYPT_OBJECT 0xC00D2733L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_PROPERTIES_OBJECT 0xC00D2734L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_BACKUP_OBJECT 0xC00D2735L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_INDIVIDUALIZE_ERROR 0xC00D2736L	The security upgrade failed. Try again later.
NS_E_DRM_LICENSE_OPEN_ERROR 0xC00D2737L	License storage is not working. Contact Microsoft product support.
NS_E_DRM_LICENSE_CLOSE_ERROR 0xC00D2738L	License storage is not working. Contact Microsoft product support.
NS_E_DRM_GET_LICENSE_ERROR 0xC00D2739L	License storage is not working. Contact Microsoft product support.
NS_E_DRM_QUERY_ERROR 0xC00D273AL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_REPORT_ERROR 0xC00D273BL	A problem has occurred in the Digital Rights Management component. Contact product support for this application.
NS_E_DRM_GET_LICENSESTRING_ERROR 0xC00D273CL	License storage is not working. Contact Microsoft product support.
NS_E_DRM_GET_CONTENTSTRING_ERROR	The media file is corrupted. Contact the content provider

Value	Meaning
0xC00D273DL	to get a new file.
NS_E_DRM_MONITOR_ERROR 0xC00D273EL	A problem has occurred in the Digital Rights Management component. Try again later.
NS_E_DRM_UNABLE_TO_SET_PARAMETER 0xC00D273FL	The application has made an invalid call to the Digital Rights Management component. Contact product support for this application.
NS_E_DRM_INVALID_APPDATA 0xC00D2740L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_INVALID_APPDATA_VERSION 0xC00D2741L	A problem has occurred in the Digital Rights Management component. Contact product support for this application.
NS_E_DRM_BACKUP_EXISTS 0xC00D2742L	Licenses are already backed up in this location.
NS_E_DRM_BACKUP_CORRUPT 0xC00D2743L	One or more backed-up licenses are missing or corrupt.
NS_E_DRM_BACKUPRESTORE_BUSY 0xC00D2744L	You cannot begin a new backup process until the current process has been completed.
NS_E_BACKUP_RESTORE_BAD_DATA 0xC00D2745L	Bad Data sent to Backup-Restore.
NS_E_DRM_LICENSE_UNUSABLE 0xC00D2748L	The license is invalid. Contact the content provider for further assistance.
NS_E_DRM_INVALID_PROPERTY 0xC00D2749L	A required property was not set by the application. Contact product support for this application.
NS_E_DRM_SECURE_STORE_NOT_FOUND 0xC00D274AL	A problem has occurred in the Digital Rights Management component of this application. Try to acquire a license again.
NS_E_DRM_CACHED_CONTENT_ERROR 0xC00D274BL	A license cannot be found for this media file. Use License Management to transfer a license for this file from the original computer, or acquire a new license.

Value	Meaning
NS_E_DRM_INDIVIDUALIZATION_INCOMPLETE 0xC00D274CL	A problem occurred during the security upgrade. Try again later.
NS_E_DRM_DRIVER_AUTH_FAILURE 0xC00D274DL	Certified driver components are required to play this media file. Contact Windows Update to see whether updated drivers are available for your hardware.
NS_E_DRM_NEED_UPGRADE_MSSAP 0xC00D274EL	One or more of the Secure Audio Path components were not found or an entry point in those components was not found.
NS_E_DRM_REOPEN_CONTENT 0xC00D274FL	Status message: Reopen the file.
NS_E_DRM_DRIVER_DIGIOUT_FAILURE 0xC00D2750L	Certain driver functionality is required to play this media file. Contact Windows Update to see whether updated drivers are available for your hardware.
NS_E_DRM_INVALID_SECURESTORE_PASSWORD 0xC00D2751L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_APPCERT_REVOKED 0xC00D2752L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_RESTORE_FRAUD 0xC00D2753L	You cannot restore your license(s).
NS_E_DRM_HARDWARE_INCONSISTENT 0xC00D2754L	The licenses for your media files are corrupted. Contact Microsoft product support.
NS_E_DRM_SDMI_TRIGGER 0xC00D2755L	To transfer this media file, you must upgrade the application.
NS_E_DRM_SDMI_NOMORECOPIES 0xC00D2756L	You cannot make any more copies of this media file.
NS_E_DRM_UNABLE_TO_CREATE_HEADER_OBJECT 0xC00D2757L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_KEYS_OBJECT	A problem has occurred in the Digital Rights Management

Value	Meaning
0xC00D2758L	component. Contact Microsoft product support.
NS_E_DRM_LICENSE_NOTACQUIRED 0xC00D2759L	Unable to obtain license.
NS_E_DRM_UNABLE_TO_CREATE_CODING_OBJECT 0xC00D275AL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_STATE_DATA_OBJECT 0xC00D275BL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_BUFFER_TOO_SMALL 0xC00D275CL	The buffer supplied is not sufficient.
NS_E_DRM_UNSUPPORTED_PROPERTY 0xC00D275DL	The property requested is not supported.
NS_E_DRM_ERROR_BAD_NET_RESP 0xC00D275EL	The specified server cannot perform the requested operation.
NS_E_DRM_STORE_NOTALLSTORED 0xC00D275FL	Some of the licenses could not be stored.
NS_E_DRM_SECURITY_COMPONENT_SIGNATURE_INVALID 0xC00D2760L	The Digital Rights Management security upgrade component could not be validated. Contact Microsoft product support.
NS_E_DRM_INVALID_DATA 0xC00D2761L	Invalid or corrupt data was encountered.
NS_E_DRM_POLICY_DISABLE_ONLINE 0xC00D2762L	The Windows Media Digital Rights Management system cannot perform the requested action because your computer or network administrator has enabled the group policy Prevent Windows Media DRM Internet Access. For assistance, contact your administrator.
NS_E_DRM_UNABLE_TO_CREATE_AUTHENTICATION_OBJECT 0xC00D2763L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_NOT_CONFIGURED 0xC00D2764L	Not all of the necessary properties for DRM have been

Value	Meaning
	set.
NS_E_DRM_DEVICE_ACTIVATION_CANCELED 0xC00D2765L	The portable device does not have the security required to copy protected files to it. To obtain the additional security, try to copy the file to your portable device again. When a message appears, click OK.
NS_E_BACKUP_RESTORE_TOO_MANY_RESETS 0xC00D2766L	Too many resets in Backup-Restore.
NS_E_DRM_DEBUGGING_NOT_ALLOWED 0xC00D2767L	Running this process under a debugger while using DRM content is not allowed.
NS_E_DRM_OPERATION_CANCELED 0xC00D2768L	The user canceled the DRM operation.
NS_E_DRM_RESTRICTIONS_NOT_RETRIEVED 0xC00D2769L	The license you are using has associated output restrictions. This license is unusable until these restrictions are queried.
NS_E_DRM_UNABLE_TO_CREATE_PLAYLIST_OBJECT 0xC00D276AL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_PLAYLIST_BURN_OBJECT 0xC00D276BL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_DEVICE_REGISTRATION_OBJECT 0xC00D276CL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_METERING_OBJECT 0xC00D276DL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_TRACK_EXCEEDED_PLAYLIST_RESTICTION 0xC00D2770L	The specified track has exceeded it's specified playlist burn limit in this playlist.
NS_E_DRM_TRACK_EXCEEDED_TRACKBURN_RESTRICTION 0xC00D2771L	The specified track has exceeded it's track burn limit.
NS_E_DRM_UNABLE_TO_GET_DEVICE_CERT 0xC00D2772L	A problem has occurred in obtaining the device's certificate. Contact Microsoft product support.



Value	Meaning
NS_E_DRM_UNABLE_TO_GET_SECURE_CLOCK 0xC00D2773L	A problem has occurred in obtaining the device's secure clock. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_SET_SECURE_CLOCK 0xC00D2774L	A problem has occurred in setting the device's secure clock. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_GET_SECURE_CLOCK_FROM_SERVER 0xC00D2775L	A problem has occurred in obtaining the secure clock from server. Contact Microsoft product support.
NS_E_DRM_POLICY_METERING_DISABLED 0xC00D2776L	This content requires the metering policy to be enabled.
NS_E_DRM_TRANSFER_CHAINED_LICENSES_UNSUPPORTED 0xC00D2777L	Transfer of chained licenses unsupported.
NS_E_DRM_SDK_VERSIONMISMATCH 0xC00D2778L	The Digital Rights Management component is not installed properly. Reinstall the Player.
NS_E_DRM_LIC_NEEDS_DEVICE_CLOCK_SET 0xC00D2779L	The file could not be transferred because the device clock is not set.
NS_E_LICENSE_HEADER_MISSING_URL 0xC00D277AL	The content header is missing an acquisition URL.
NS_E_DEVICE_NOT_WMDRM_DEVICE 0xC00D277BL	The current attached device does not support WMDRM.
NS_E_DRM_INVALID_APPCERT 0xC00D277CL	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_PROTOCOL_FORCEFUL_TERMINATION_ON_PETITION 0xC00D277DL	The client application has been forcefully terminated during a DRM petition.
NS_E_DRM_PROTOCOL_FORCEFUL_TERMINATION_ON_CHALLENGE 0xC00D277EL	The client application has been forcefully terminated during a DRM challenge.
NS_E_DRM_CHECKPOINT_FAILED 0xC00D277FL	Secure storage protection error. Restore your licenses from a previous backup and try again.
NS_E_DRM_BB_UNABLE_TO_INITIALIZE 0xC00D2780L	A problem has occurred in the Digital Rights Management root of trust. Contact Microsoft

Value	Meaning
	product support.
NS_E_DRM_UNABLE_TO_LOAD_HARDWARE_ID 0xC00D2781L	A problem has occurred in retrieving the Digital Rights Management machine identification. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_OPEN_DATA_STORE 0xC00D2782L	A problem has occurred in opening the Digital Rights Management data storage file. Contact Microsoft product.
NS_E_DRM_DATASTORE_CORRUPT 0xC00D2783L	The Digital Rights Management data storage is not functioning properly. Contact Microsoft product support.
NS_E_DRM_UNABLE_TO_CREATE_INMEMORYSTORE_OBJECT 0xC00D2784L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_STUBLIB_REQUIRED 0xC00D2785L	A secured library is required to access the requested functionality.
NS_E_DRM_UNABLE_TO_CREATE_CERTIFICATE_OBJECT 0xC00D2786L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_MIGRATION_TARGET_NOT_ONLINE 0xC00D2787L	A problem has occurred in the Digital Rights Management component during license migration. Contact Microsoft product support.
NS_E_DRM_INVALID_MIGRATION_IMAGE 0xC00D2788L	A problem has occurred in the Digital Rights Management component during license migration. Contact Microsoft product support.
NS_E_DRM_MIGRATION_TARGET_STATES_CORRUPTED 0xC00D2789L	A problem has occurred in the Digital Rights Management component during license migration. Contact Microsoft product support.
NS_E_DRM_MIGRATION_IMPORTER_NOT_AVAILABLE 0xC00D278AL	A problem has occurred in the Digital Rights Management component during license migration. Contact Microsoft product support.
NS_DRM_E_MIGRATION_UPGRADE_WITH_DIFF_SID	A problem has occurred in the

Value	Meaning
0xC00D278BL	Digital Rights Management component during license migration. Contact Microsoft product support.
NS_DRM_E_MIGRATION_SOURCE_MACHINE_IN_USE 0xC00D278CL	The Digital Rights Management component is in use during license migration. Contact Microsoft product support.
NS_DRM_E_MIGRATION_TARGET_MACHINE_LESS_THAN_LH 0xC00D278DL	Licenses are being migrated to a machine running XP or downlevel OS. This operation can only be performed on Windows Vista or a later OS. Contact Microsoft product support.
NS_DRM_E_MIGRATION_IMAGE_ALREADY_EXISTS 0xC00D278EL	Migration Image already exists. Contact Microsoft product support.
NS_E_DRM_HARDWAREID_MISMATCH 0xC00D278FL	The requested action cannot be performed because a hardware configuration change has been detected by the Windows Media Digital Rights Management (DRM) components on your computer.
NS_E_INVALID_DRMV2CLT_STUBLIB 0xC00D2790L	The wrong stublib has been linked to an application or DLL using drmv2clt.dll.
NS_E_DRM_MIGRATION_INVALID_LEGACYV2_DATA 0xC00D2791L	The legacy V2 data being imported is invalid.
NS_E_DRM_MIGRATION_LICENSE_ALREADY_EXISTS 0xC00D2792L	The license being imported already exists.
NS_E_DRM_MIGRATION_INVALID_LEGACYV2_SST_PASSWORD 0xC00D2793L	The password of the Legacy V2 SST entry being imported is incorrect.
NS_E_DRM_MIGRATION_NOT_SUPPORTED 0xC00D2794L	Migration is not supported by the plugin.
NS_E_DRM_UNABLE_TO_CREATE_MIGRATION_IMPORTER_OBJECT 0xC00D2795L	A migration importer cannot be created for this media file. Reinstall the application.
NS_E_DRM_CHECKPOINT_MISMATCH 0xC00D2796L	The requested action cannot be performed because a problem occurred with the Windows Media Digital Rights

Value	Meaning
	Management (DRM) components on your computer.
NS_E_DRM_CHECKPOINT_CORRUPT 0xC00D2797L	The requested action cannot be performed because a problem occurred with the Windows Media Digital Rights Management (DRM) components on your computer.
NS_E_REG_FLUSH_FAILURE 0xC00D2798L	The requested action cannot be performed because a problem occurred with the Windows Media Digital Rights Management (DRM) components on your computer.
NS_E_HDS_KEY_MISMATCH 0xC00D2799L	The requested action cannot be performed because a problem occurred with the Windows Media Digital Rights Management (DRM) components on your computer.
NS_E_DRM_MIGRATION_OPERATION_CANCELLED 0xC00D279AL	Migration was cancelled by the user.
NS_E_DRM_MIGRATION_OBJECT_IN_USE 0xC00D279BL	Migration object is already in use and cannot be called until the current operation completes.
NS_E_DRM_MALFORMED_CONTENT_HEADER 0xC00D279CL	The content header does not comply with DRM requirements and cannot be used.
NS_E_DRM_LICENSE_EXPIRED 0xC00D27D8L	The license for this file has expired and is no longer valid. Contact your content provider for further assistance.
NS_E_DRM_LICENSE_NOTENABLED 0xC00D27D9L	The license for this file is not valid yet, but will be at a future date.
NS_E_DRM_LICENSE_APPSECLOW 0xC00D27DAL	The license for this file requires a higher level of security than the player you are currently using has. Try using a different player or download a newer version of your current player.

Value	Meaning
NS_E_DRM_STORE_NEEDINDI 0xC00D27DBL	The license cannot be stored as it requires security upgrade of Digital Rights Management component.
NS_E_DRM_STORE_NOTALLOWED 0xC00D27DCL	Your machine does not meet the requirements for storing the license.
NS_E_DRM_LICENSE_APP_NOTALLOWED 0xC00D27DDL	The license for this file requires an upgraded version of your player or a different player.
NS_E_DRM_LICENSE_CERT_EXPIRED 0xC00D27DFL	The license server's certificate expired. Make sure your system clock is set correctly. Contact your content provider for further assistance.
NS_E_DRM_LICENSE_SECLow 0xC00D27E0L	The license for this file requires a higher level of security than the player you are currently using has. Try using a different player or download a newer version of your current player.
NS_E_DRM_LICENSE_CONTENT_REVOKED 0xC00D27E1L	The content owner for the license you just acquired is no longer supporting their content. Contact the content owner for a newer version of the content.
NS_E_DRM_DEVICE_NOT_REGISTERED 0xC00D27E2L	The content owner for the license you just acquired requires your device to register to the current machine.
NS_E_DRM_LICENSE_NOSAP 0xC00D280AL	The license for this file requires a feature that is not supported in your current player or operating system. You can try with newer version of your current player or contact your content provider for further assistance.
NS_E_DRM_LICENSE_NOSVP 0xC00D280BL	The license for this file requires a feature that is not supported in your current player or operating system. You can try with newer version of your current player or contact your content provider

Value	Meaning
	for further assistance.
NS_E_DRM_LICENSE_NOWDM 0xC00D280CL	The license for this file requires Windows Driver Model (WDM) audio drivers. Contact your sound card manufacturer for further assistance.
NS_E_DRM_LICENSE_NOTRUSTEDCODEC 0xC00D280DL	The license for this file requires a higher level of security than the player you are currently using has. Try using a different player or download a newer version of your current player.
NS_E_DRM_SOURCEID_NOT_SUPPORTED 0xC00D280EL	The license for this file is not supported by your current player. You can try with newer version of your current player or contact your content provider for further assistance.
NS_E_DRM_NEEDS_UPGRADE_TEMPFILE 0xC00D283DL	An updated version of your media player is required to play the selected content.
NS_E_DRM_NEED_UPGRADE_PD 0xC00D283EL	A new version of the Digital Rights Management component is required. Contact product support for this application to get the latest version.
NS_E_DRM_SIGNATURE_FAILURE 0xC00D283FL	Failed to either create or verify the content header.
NS_E_DRM_LICENSE_SERVER_INFO_MISSING 0xC00D2840L	Could not read the necessary information from the system registry.
NS_E_DRM_BUSY 0xC00D2841L	The DRM subsystem is currently locked by another application or user. Try again later.
NS_E_DRM_PD_TOO_MANY_DEVICES 0xC00D2842L	There are too many target devices registered on the portable media.
NS_E_DRM_INDIV_FRAUD 0xC00D2843L	The security upgrade cannot be completed because the allowed number of daily upgrades has been exceeded. Try again tomorrow.

Value	Meaning
NS_E_DRM_INDIV_NO_CABS 0xC00D2844L	The security upgrade cannot be completed because the server is unable to perform the operation. Try again later.
NS_E_DRM_INDIV_SERVICE_UNAVAILABLE 0xC00D2845L	The security upgrade cannot be performed because the server is not available. Try again later.
NS_E_DRM_RESTORE_SERVICE_UNAVAILABLE 0xC00D2846L	Windows Media Player cannot restore your licenses because the server is not available. Try again later.
NS_E_DRM_CLIENT_CODE_EXPIRED 0xC00D2847L	Windows Media Player cannot play the protected file. Verify that your computer's date is set correctly. If it is correct, on the Help menu, click Check for Player Updates to install the latest version of the Player.
NS_E_DRM_NO_UPLINK_LICENSE 0xC00D2848L	The chained license cannot be created because the referenced uplink license does not exist.
NS_E_DRM_INVALID_KID 0xC00D2849L	The specified KID is invalid.
NS_E_DRM_LICENSE_INITIALIZATION_ERROR 0xC00D284AL	License initialization did not work. Contact Microsoft product support.
NS_E_DRM_CHAIN_TOO_LONG 0xC00D284CL	The uplink license of a chained license cannot itself be a chained license.
NS_E_DRM_UNSUPPORTED_ALGORITHM 0xC00D284DL	The specified encryption algorithm is unsupported.
NS_E_DRM_LICENSE_DELETION_ERROR 0xC00D284EL	License deletion did not work. Contact Microsoft product support.
NS_E_DRM_INVALID_CERTIFICATE 0xC00D28A0L	The client's certificate is corrupted or the signature cannot be verified.
NS_E_DRM_CERTIFICATE_REVOKED 0xC00D28A1L	The client's certificate has been revoked.
NS_E_DRM_LICENSE_UNAVAILABLE 0xC00D28A2L	There is no license available for the requested action.

Value	Meaning
NS_E_DRM_DEVICE_LIMIT_REACHED 0xC00D28A3L	The maximum number of devices in use has been reached. Unable to open additional devices.
NS_E_DRM_UNABLE_TO_VERIFY_PROXIMITY 0xC00D28A4L	The proximity detection procedure could not confirm that the receiver is near the transmitter in the network.
NS_E_DRM_MUST_REGISTER 0xC00D28A5L	The client must be registered before executing the intended operation.
NS_E_DRM_MUST_APPROVE 0xC00D28A6L	The client must be approved before executing the intended operation.
NS_E_DRM_MUST_REVALIDATE 0xC00D28A7L	The client must be revalidated before executing the intended operation.
NS_E_DRM_INVALID_PROXIMITY_RESPONSE 0xC00D28A8L	The response to the proximity detection challenge is invalid.
NS_E_DRM_INVALID_SESSION 0xC00D28A9L	The requested session is invalid.
NS_E_DRM_DEVICE_NOT_OPEN 0xC00D28AAL	The device must be opened before it can be used to receive content.
NS_E_DRM_DEVICE_ALREADY_REGISTERED 0xC00D28ABL	Device registration failed because the device is already registered.
NS_E_DRM_UNSUPPORTED_PROTOCOL_VERSION 0xC00D28ACL	Unsupported WMDRM-ND protocol version.
NS_E_DRM_UNSUPPORTED_ACTION 0xC00D28ADL	The requested action is not supported.
NS_E_DRM_CERTIFICATE_SECURITY_LEVEL_INADEQUATE 0xC00D28AEL	The certificate does not have an adequate security level for the requested action.
NS_E_DRM_UNABLE_TO_OPEN_PORT 0xC00D28AFL	Unable to open the specified port for receiving Proximity messages.
NS_E_DRM_BAD_REQUEST 0xC00D28B0L	The message format is invalid.
NS_E_DRM_INVALID_CRL 0xC00D28B1L	The Certificate Revocation List is invalid or corrupted.



Value	Meaning
NS_E_DRM_ATTRIBUTE_TOO_LONG 0xC00D28B2L	The length of the attribute name or value is too long.
NS_E_DRM_EXPIRED_LICENSEBLOB 0xC00D28B3L	The license blob passed in the cardea request is expired.
NS_E_DRM_INVALID_LICENSEBLOB 0xC00D28B4L	The license blob passed in the cardea request is invalid. Contact Microsoft product support.
NS_E_DRM_INCLUSION_LIST_REQUIRED 0xC00D28B5L	The requested operation can not be performed because the license does not contain an inclusion list.
NS_E_DRM_DRMV2CLT_REVOKED 0xC00D28B6L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_DRM_RIV_TOO_SMALL 0xC00D28B7L	A problem has occurred in the Digital Rights Management component. Contact Microsoft product support.
NS_E_OUTPUT_PROTECTION_LEVEL_UNSUPPORTED 0xC00D2904L	Windows Media Player does not support the level of output protection required by the content.
NS_E_COMPRESSED_DIGITAL_VIDEO_PROTECTION_LEVEL_UNSUPPORTED 0xC00D2905L	Windows Media Player does not support the level of protection required for compressed digital video.
NS_E_UNCOMPRESSED_DIGITAL_VIDEO_PROTECTION_LEVEL_UNSUPPORTED 0xC00D2906L	Windows Media Player does not support the level of protection required for uncompressed digital video.
NS_E_ANALOG_VIDEO_PROTECTION_LEVEL_UNSUPPORTED 0xC00D2907L	Windows Media Player does not support the level of protection required for analog video.
NS_E_COMPRESSED_DIGITAL_AUDIO_PROTECTION_LEVEL_UNSUPPORTED 0xC00D2908L	Windows Media Player does not support the level of protection required for compressed digital audio.
NS_E_UNCOMPRESSED_DIGITAL_AUDIO_PROTECTION_LEVEL_UNSUPPORTED 0xC00D2909L	Windows Media Player does not support the level of protection required for uncompressed digital audio.
NS_E_OUTPUT_PROTECTION_SCHEME_UNSUPPORTED	Windows Media Player does

Value	Meaning
0xC00D290AL	not support the scheme of output protection required by the content.
NS_E_REBOOT_RECOMMENDED 0xC00D2AFAL	Installation was not successful and some file cleanup is not complete. For best results, restart your computer.
NS_E_REBOOT_REQUIRED 0xC00D2AFBL	Installation was not successful. To continue, you must restart your computer.
NS_E_SETUP_INCOMPLETE 0xC00D2AFCL	Installation was not successful.
NS_E_SETUP_DRM_MIGRATION_FAILED 0xC00D2AFDL	Setup cannot migrate the Windows Media Digital Rights Management (DRM) components.
NS_E_SETUP_IGNOREABLE_FAILURE 0xC00D2AFEL	Some skin or playlist components cannot be installed.
NS_E_SETUP_DRM_MIGRATION_FAILED_AND_IGNOREABLE_FAILURE 0xC00D2AFFL	Setup cannot migrate the Windows Media Digital Rights Management (DRM) components. In addition, some skin or playlist components cannot be installed.
NS_E_SETUP_BLOCKED 0xC00D2B00L	Installation is blocked because your computer does not meet one or more of the setup requirements.
NS_E_UNKNOWN_PROTOCOL 0xC00D2EE0L	The specified protocol is not supported.
NS_E_REDIRECT_TO_PROXY 0xC00D2EE1L	The client is redirected to a proxy server.
NS_E_INTERNAL_SERVER_ERROR 0xC00D2EE2L	The server encountered an unexpected condition which prevented it from fulfilling the request.
NS_E_BAD_REQUEST 0xC00D2EE3L	The request could not be understood by the server.
NS_E_ERROR_FROM_PROXY 0xC00D2EE4L	The proxy experienced an error while attempting to contact the media server.
NS_E_PROXY_TIMEOUT	The proxy did not receive a

Value	Meaning
0xC00D2EE5L	timely response while attempting to contact the media server.
NS_E_SERVER_UNAVAILABLE 0xC00D2EE6L	The server is currently unable to handle the request due to a temporary overloading or maintenance of the server.
NS_E_REFUSED_BY_SERVER 0xC00D2EE7L	The server is refusing to fulfill the requested operation.
NS_E_INCOMPATIBLE_SERVER 0xC00D2EE8L	The server is not a compatible streaming media server.
NS_E_MULTICAST_DISABLED 0xC00D2EE9L	The content cannot be streamed because the Multicast protocol has been disabled.
NS_E_INVALID_REDIRECT 0xC00D2EEAL	The server redirected the player to an invalid location.
NS_E_ALL_PROTOCOLS_DISABLED 0xC00D2EEBL	The content cannot be streamed because all protocols have been disabled.
NS_E_MSBD_NO_LONGER_SUPPORTED 0xC00D2EECL	The MSBD protocol is no longer supported. Please use HTTP to connect to the Windows Media stream.
NS_E_PROXY_NOT_FOUND 0xC00D2EEDL	The proxy server could not be located. Please check your proxy server configuration.
NS_E_CANNOT_CONNECT_TO_PROXY 0xC00D2EEEL	Unable to establish a connection to the proxy server. Please check your proxy server configuration.
NS_E_SERVER_DNS_TIMEOUT 0xC00D2EEFL	Unable to locate the media server. The operation timed out.
NS_E_PROXY_DNS_TIMEOUT 0xC00D2EF0L	Unable to locate the proxy server. The operation timed out.
NS_E_CLOSED_ON_SUSPEND 0xC00D2EF1L	Media closed because Windows was shut down.
NS_E_CANNOT_READ_PLAYLIST_FROM_MEDIASERVER 0xC00D2EF2L	Unable to read the contents of a playlist file from a media server.
NS_E_SESSION_NOT_FOUND	Session not found.

Value	Meaning
0xC00D2EF3L	
NS_E_REQUIRE_STREAMING_CLIENT 0xC00D2EF4L	Content requires a streaming media client.
NS_E_PLAYLIST_ENTRY_HAS_CHANGED 0xC00D2EF5L	A command applies to a previous playlist entry.
NS_E_PROXY_ACCESSDENIED 0xC00D2EF6L	The proxy server is denying access. The username and/or password might be incorrect.
NS_E_PROXY_SOURCE_ACCESSDENIED 0xC00D2EF7L	The proxy could not provide valid authentication credentials to the media server.
NS_E_NETWORK_SINK_WRITE 0xC00D2EF8L	The network sink failed to write data to the network.
NS_E_FIREWALL 0xC00D2EF9L	Packets are not being received from the server. The packets might be blocked by a filtering device, such as a network firewall.
NS_E_MMS_NOT_SUPPORTED 0xC00D2EFAL	The MMS protocol is not supported. Please use HTTP or RTSP to connect to the Windows Media stream.
NS_E_SERVER_ACCESSDENIED 0xC00D2EFBL	The Windows Media server is denying access. The username and/or password might be incorrect.
NS_E_RESOURCE_GONE 0xC00D2EFCL	The Publishing Point or file on the Windows Media Server is no longer available.
NS_E_NO_EXISTING_PACKETIZER 0xC00D2EFDL	There is no existing packetizer plugin for a stream.
NS_E_BAD_SYNTAX_IN_SERVER_RESPONSE 0xC00D2EFEL	The response from the media server could not be understood. This might be caused by an incompatible proxy server or media server.
NS_E_RESET_SOCKET_CONNECTION 0xC00D2F00L	The Windows Media Server reset the network connection.
NS_E_TOO_MANY_HOPS 0xC00D2F02L	The request could not reach the media server (too many hops).

Value	Meaning
NS_E_TOO_MUCH_DATA_FROM_SERVER 0xC00D2F05L	The server is sending too much data. The connection has been terminated.
NS_E_CONNECT_TIMEOUT 0xC00D2F06L	It was not possible to establish a connection to the media server in a timely manner. The media server may be down for maintenance, or it may be necessary to use a proxy server to access this media server.
NS_E_PROXY_CONNECT_TIMEOUT 0xC00D2F07L	It was not possible to establish a connection to the proxy server in a timely manner. Please check your proxy server configuration.
NS_E_SESSION_INVALID 0xC00D2F08L	Session not found.
NS_E_PACKETSINK_UNKNOWN_FEC_STREAM 0xC00D2F0AL	Unknown packet sink stream.
NS_E_PUSH_CANNOTCONNECT 0xC00D2F0BL	Unable to establish a connection to the server. Ensure Windows Media Services is started and the HTTP Server control protocol is properly enabled.
NS_E_INCOMPATIBLE_PUSH_SERVER 0xC00D2F0CL	The Server service that received the HTTP push request is not a compatible version of Windows Media Services (WMS). This error may indicate the push request was received by IIS instead of WMS. Ensure WMS is started and has the HTTP Server control protocol properly enabled and try again.
NS_E_END_OF_PLAYLIST 0xC00D32C8L	The playlist has reached its end.
NS_E_USE_FILE_SOURCE 0xC00D32C9L	Use file source.
NS_E_PROPERTY_NOT_FOUND 0xC00D32CAL	The property was not found.
NS_E_PROPERTY_READ_ONLY 0xC00D32CCL	The property is read only.

Value	Meaning
NS_E_TABLE_KEY_NOT_FOUND 0xC00D32CDL	The table key was not found.
NS_E_INVALID_QUERY_OPERATOR 0xC00D32CFL	Invalid query operator.
NS_E_INVALID_QUERY_PROPERTY 0xC00D32D0L	Invalid query property.
NS_E_PROPERTY_NOT_SUPPORTED 0xC00D32D2L	The property is not supported.
NS_E_SCHEMA_CLASSIFY_FAILURE 0xC00D32D4L	Schema classification failure.
NS_E_METADATA_FORMAT_NOT_SUPPORTED 0xC00D32D5L	The metadata format is not supported.
NS_E_METADATA_NO_EDITING_CAPABILITY 0xC00D32D6L	Cannot edit the metadata.
NS_E_METADATA_CANNOT_SET_LOCALE 0xC00D32D7L	Cannot set the locale id.
NS_E_METADATA_LANGUAGE_NOT_SUPPORTED 0xC00D32D8L	The language is not supported in the format.
NS_E_METADATA_NO_RFC1766_NAME_FOR_LOCALE 0xC00D32D9L	There is no RFC1766 name translation for the supplied locale id.
NS_E_METADATA_NOT_AVAILABLE 0xC00D32DAL	The metadata (or metadata item) is not available.
NS_E_METADATA_CACHE_DATA_NOT_AVAILABLE 0xC00D32DBL	The cached metadata (or metadata item) is not available.
NS_E_METADATA_INVALID_DOCUMENT_TYPE 0xC00D32DCL	The metadata document is invalid.
NS_E_METADATA_IDENTIFIER_NOT_AVAILABLE 0xC00D32DDL	The metadata content identifier is not available.
NS_E_METADATA_CANNOT_RETRIEVE_FROM_OFFLINE_CACHE 0xC00D32DEL	Cannot retrieve metadata from the offline metadata cache.
ERROR_MONITOR_INVALID_DESCRIPTOR_CHECKSUM 0xC0261003	Checksum of the obtained monitor descriptor is invalid.
ERROR_MONITOR_INVALID_STANDARD_TIMING_BLOCK 0xC0261004	Monitor descriptor contains an invalid standard timing block.

Value	Meaning
ERROR_MONITOR_WMI_DATABLOCK_REGISTRATION_FAILED 0xC0261005	Windows Management Instrumentation (WMI) data block registration failed for one of the MSMonitorClass WMI subclasses.
ERROR_MONITOR_INVALID_SERIAL_NUMBER_MONDSC_BLOCK 0xC0261006	Provided monitor descriptor block is either corrupted or does not contain the monitor's detailed serial number.
ERROR_MONITOR_INVALID_USER_FRIENDLY_MONDSC_BLOCK 0xC0261007	Provided monitor descriptor block is either corrupted or does not contain the monitor's user-friendly name.
ERROR_MONITOR_NO_MORE_DESCRIPTOR_DATA 0xC0261008	There is no monitor descriptor data at the specified (offset, size) region.
ERROR_MONITOR_INVALID_DETAILED_TIMING_BLOCK 0xC0261009	Monitor descriptor contains an invalid detailed timing block.
ERROR_GRAPHICS_NOT_EXCLUSIVE_MODE_OWNER 0xC0262000	Exclusive mode ownership is needed to create unmanaged primary allocation.
ERROR_GRAPHICS_INSUFFICIENT_DMA_BUFFER 0xC0262001	The driver needs more direct memory access (DMA) buffer space to complete the requested operation.
ERROR_GRAPHICS_INVALID_DISPLAY_ADAPTER 0xC0262002	Specified display adapter handle is invalid.
ERROR_GRAPHICS_ADAPTER_WAS_RESET 0xC0262003	Specified display adapter and all of its state has been reset.
ERROR_GRAPHICS_INVALID_DRIVER_MODEL 0xC0262004	The driver stack does not match the expected driver model.
ERROR_GRAPHICS_PRESENT_MODE_CHANGED 0xC0262005	Present happened but ended up into the changed desktop mode.
ERROR_GRAPHICS_PRESENT_OCCLUDED 0xC0262006	Nothing to present due to desktop occlusion.
ERROR_GRAPHICS_PRESENT_DENIED 0xC0262007	Not able to present due to denial of desktop access.
ERROR_GRAPHICS_CANNOTCOLORCONVERT 0xC0262008	Not able to present with color conversion.
ERROR_GRAPHICS_NO_VIDEO_MEMORY	Not enough video memory

Value	Meaning
0xC0262100	available to complete the operation.
ERROR_GRAPHICS_CANT_LOCK_MEMORY 0xC0262101	Could not probe and lock the underlying memory of an allocation.
ERROR_GRAPHICS_ALLOCATION_BUSY 0xC0262102	The allocation is currently busy.
ERROR_GRAPHICS_TOO_MANY_REFERENCES 0xC0262103	An object being referenced has reach the maximum reference count already and cannot be referenced further.
ERROR_GRAPHICS_TRY_AGAIN_LATER 0xC0262104	A problem could not be solved due to some currently existing condition. The problem should be tried again later.
ERROR_GRAPHICS_TRY_AGAIN_NOW 0xC0262105	A problem could not be solved due to some currently existing condition. The problem should be tried again immediately.
ERROR_GRAPHICS_ALLOCATION_INVALID 0xC0262106	The allocation is invalid.
ERROR_GRAPHICS_UNSWIZZLING_APERTURE_UNAVAILABLE 0xC0262107	No more unswizzling apertures are currently available.
ERROR_GRAPHICS_UNSWIZZLING_APERTURE_UNSUPPORTED 0xC0262108	The current allocation cannot be unswizzled by an aperture.
ERROR_GRAPHICS_CANT_EVICT_PINNED_ALLOCATION 0xC0262109	The request failed because a pinned allocation cannot be evicted.
ERROR_GRAPHICS_INVALID_ALLOCATION_USAGE 0xC0262110	The allocation cannot be used from its current segment location for the specified operation.
ERROR_GRAPHICS_CANT_RENDER_LOCKED_ALLOCATION 0xC0262111	A locked allocation cannot be used in the current command buffer.
ERROR_GRAPHICS_ALLOCATION_CLOSED 0xC0262112	The allocation being referenced has been closed permanently.
ERROR_GRAPHICS_INVALID_ALLOCATION_INSTANCE 0xC0262113	An invalid allocation instance is being referenced.
ERROR_GRAPHICS_INVALID_ALLOCATION_HANDLE 0xC0262114	An invalid allocation handle is being referenced.



Value	Meaning
ERROR_GRAPHICS_WRONG_ALLOCATION_DEVICE 0xC0262115	The allocation being referenced does not belong to the current device.
ERROR_GRAPHICS_ALLOCATION_CONTENT_LOST 0xC0262116	The specified allocation lost its content.
ERROR_GRAPHICS_GPU_EXCEPTION_ON_DEVICE 0xC0262200	Graphics processing unit (GPU) exception is detected on the given device. The device is not able to be scheduled.
ERROR_GRAPHICS_INVALID_VIDPN_TOPOLOGY 0xC0262300	Specified video present network (VidPN) topology is invalid.
ERROR_GRAPHICS_VIDPN_TOPOLOGY_NOT_SUPPORTED 0xC0262301	Specified VidPN topology is valid but is not supported by this model of the display adapter.
ERROR_GRAPHICS_VIDPN_TOPOLOGY_CURRENTLY_NOT_SUPPORTED 0xC0262302	Specified VidPN topology is valid but is not supported by the display adapter at this time, due to current allocation of its resources.
ERROR_GRAPHICS_INVALID_VIDPN 0xC0262303	Specified VidPN handle is invalid.
ERROR_GRAPHICS_INVALID_VIDEO_PRESENT_SOURCE 0xC0262304	Specified video present source is invalid.
ERROR_GRAPHICS_INVALID_VIDEO_PRESENT_TARGET 0xC0262305	Specified video present target is invalid.
ERROR_GRAPHICS_VIDPN_MODALITY_NOT_SUPPORTED 0xC0262306	Specified VidPN modality is not supported (for example, at least two of the pinned modes are not cofunctional).
ERROR_GRAPHICS_INVALID_VIDPN_SOURCEMODESET 0xC0262308	Specified VidPN source mode set is invalid.
ERROR_GRAPHICS_INVALID_VIDPN_TARGETMODESET 0xC0262309	Specified VidPN target mode set is invalid.
ERROR_GRAPHICS_INVALID_FREQUENCY 0xC026230A	Specified video signal frequency is invalid.
ERROR_GRAPHICS_INVALID_ACTIVE_REGION 0xC026230B	Specified video signal active region is invalid.
ERROR_GRAPHICS_INVALID_TOTAL_REGION	Specified video signal total

Value	Meaning
0xC026230C	region is invalid.
ERROR_GRAPHICS_INVALID_VIDEO_PRESENT_SOURCE_MODE 0xC0262310	Specified video present source mode is invalid.
ERROR_GRAPHICS_INVALID_VIDEO_PRESENT_TARGET_MODE 0xC0262311	Specified video present target mode is invalid.
ERROR_GRAPHICS_PINNED_MODE_MUST_REMAIN_IN_SET 0xC0262312	Pinned mode must remain in the set on VidPN's cofunctional modality enumeration.
ERROR_GRAPHICS_PATH_ALREADY_IN_TOPOLOGY 0xC0262313	Specified video present path is already in the VidPN topology.
ERROR_GRAPHICS_MODE_ALREADY_IN_MODESET 0xC0262314	Specified mode is already in the mode set.
ERROR_GRAPHICS_INVALID_VIDEOPRESENTSOURCESET 0xC0262315	Specified video present source set is invalid.
ERROR_GRAPHICS_INVALID_VIDEOPRESENTTARGETSET 0xC0262316	Specified video present target set is invalid.
ERROR_GRAPHICS_SOURCE_ALREADY_IN_SET 0xC0262317	Specified video present source is already in the video present source set.
ERROR_GRAPHICS_TARGET_ALREADY_IN_SET 0xC0262318	Specified video present target is already in the video present target set.
ERROR_GRAPHICS_INVALID_VIDPN_PRESENT_PATH 0xC0262319	Specified VidPN present path is invalid.
ERROR_GRAPHICS_NO_RECOMMENDED_VIDPN_TOPOLOGY 0xC026231A	Miniport has no recommendation for augmentation of the specified VidPN topology.
ERROR_GRAPHICS_INVALID_MONITOR_FREQUENCYRANGESET 0xC026231B	Specified monitor frequency range set is invalid.
ERROR_GRAPHICS_INVALID_MONITOR_FREQUENCYRANGE 0xC026231C	Specified monitor frequency range is invalid.
ERROR_GRAPHICS_FREQUENCYRANGE_NOT_IN_SET 0xC026231D	Specified frequency range is not in the specified monitor frequency range set.
ERROR_GRAPHICS_FREQUENCYRANGE_ALREADY_IN_SET 0xC026231F	Specified frequency range is already in the specified monitor frequency range set.
ERROR_GRAPHICS_STALE_MODESET	Specified mode set is stale.

Value	Meaning
0xC0262320	Reacquire the new mode set.
ERROR_GRAPHICS_INVALID_MONITOR_SOURCEMODESET 0xC0262321	Specified monitor source mode set is invalid.
ERROR_GRAPHICS_INVALID_MONITOR_SOURCE_MODE 0xC0262322	Specified monitor source mode is invalid.
ERROR_GRAPHICS_NO_RECOMMENDED_FUNCTIONAL_VIDPN 0xC0262323	Miniport does not have any recommendation regarding the request to provide a functional VidPN given the current display adapter configuration.
ERROR_GRAPHICS_MODE_ID_MUST_BE_UNIQUE 0xC0262324	ID of the specified mode is already used by another mode in the set.
ERROR_GRAPHICS_EMPTY_ADAPTER_MONITOR_MODE_SUPPORT_INTERSECTION 0xC0262325	System failed to determine a mode that is supported by both the display adapter and the monitor connected to it.
ERROR_GRAPHICS_VIDEO_PRESENT_TARGETS_LESS_THAN_SOURCES 0xC0262326	Number of video present targets must be greater than or equal to the number of video present sources.
ERROR_GRAPHICS_PATH_NOT_IN_TOPOLOGY 0xC0262327	Specified present path is not in the VidPN topology.
ERROR_GRAPHICS_ADAPTER_MUST_HAVE_AT_LEAST_ONE_SOURCE 0xC0262328	Display adapter must have at least one video present source.
ERROR_GRAPHICS_ADAPTER_MUST_HAVE_AT_LEAST_ONE_TARGET 0xC0262329	Display adapter must have at least one video present target.
ERROR_GRAPHICS_INVALID_MONITORDESCRIPTORSET 0xC026232A	Specified monitor descriptor set is invalid.
ERROR_GRAPHICS_INVALID_MONITORDESCRIPTOR 0xC026232B	Specified monitor descriptor is invalid.
ERROR_GRAPHICS_MONITORDESCRIPTOR_NOT_IN_SET 0xC026232C	Specified descriptor is not in the specified monitor descriptor set.
ERROR_GRAPHICS_MONITORDESCRIPTOR_ALREADY_IN_SET 0xC026232D	Specified descriptor is already in the specified monitor descriptor set.
ERROR_GRAPHICS_MONITORDESCRIPTOR_ID_MUST_BE_UNIQUE 0xC026232E	ID of the specified monitor descriptor is already used by another descriptor in the set.

Value	Meaning
ERROR_GRAPHICS_INVALID_VIDPN_TARGET_SUBSET_TYPE 0xC026232F	Specified video present target subset type is invalid.
ERROR_GRAPHICS_RESOURCES_NOT_RELATED 0xC0262330	Two or more of the specified resources are not related to each other, as defined by the interface semantics.
ERROR_GRAPHICS_SOURCE_ID_MUST_BE_UNIQUE 0xC0262331	ID of the specified video present source is already used by another source in the set.
ERROR_GRAPHICS_TARGET_ID_MUST_BE_UNIQUE 0xC0262332	ID of the specified video present target is already used by another target in the set.
ERROR_GRAPHICS_NO_AVAILABLE_VIDPN_TARGET 0xC0262333	Specified VidPN source cannot be used because there is no available VidPN target to connect it to.
ERROR_GRAPHICS_MONITOR_COULD_NOT_BE_ASSOCIATED_WITH_ADAPTER 0xC0262334	Newly arrived monitor could not be associated with a display adapter.
ERROR_GRAPHICS_NO_VIDPNMGR 0xC0262335	Display adapter in question does not have an associated VidPN manager.
ERROR_GRAPHICS_NO_ACTIVE_VIDPN 0xC0262336	VidPN manager of the display adapter in question does not have an active VidPN.
ERROR_GRAPHICS_STALE_VIDPN_TOPOLOGY 0xC0262337	Specified VidPN topology is stale. Re-acquire the new topology.
ERROR_GRAPHICS_MONITOR_NOT_CONNECTED 0xC0262338	There is no monitor connected on the specified video present target.
ERROR_GRAPHICS_SOURCE_NOT_IN_TOPOLOGY 0xC0262339	Specified source is not part of the specified VidPN topology.
ERROR_GRAPHICS_INVALID_PRIMARYSURFACE_SIZE 0xC026233A	Specified primary surface size is invalid.
ERROR_GRAPHICS_INVALID_VISIBLEREGION_SIZE 0xC026233B	Specified visible region size is invalid.
ERROR_GRAPHICS_INVALID_STRIDE 0xC026233C	Specified stride is invalid.
ERROR_GRAPHICS_INVALID_PIXELFORMAT 0xC026233D	Specified pixel format is invalid.

Value	Meaning
ERROR_GRAPHICS_INVALID_COLORBASIS 0xC026233E	Specified color basis is invalid.
ERROR_GRAPHICS_INVALID_PIXELVALUEACCESSMODE 0xC026233F	Specified pixel value access mode is invalid.
ERROR_GRAPHICS_TARGET_NOT_IN_TOPOLOGY 0xC0262340	Specified target is not part of the specified VidPN topology.
ERROR_GRAPHICS_NO_DISPLAY_MODE_MANAGEMENT_SUPPORT 0xC0262341	Failed to acquire display mode management interface.
ERROR_GRAPHICS_VIDPN_SOURCE_IN_USE 0xC0262342	Specified VidPN source is already owned by a display mode manager (DMM) client and cannot be used until that client releases it.
ERROR_GRAPHICS_CANT_ACCESS_ACTIVE_VIDPN 0xC0262343	Specified VidPN is active and cannot be accessed.
ERROR_GRAPHICS_INVALID_PATH_IMPORTANCE_ORDINAL 0xC0262344	Specified VidPN present path importance ordinal is invalid.
ERROR_GRAPHICS_INVALID_PATH_CONTENT_GEOMETRY_TRANSFORMATION 0xC0262345	Specified VidPN present path content geometry transformation is invalid.
ERROR_GRAPHICS_PATH_CONTENT_GEOMETRY_TRANSFORMATION_NOT_SUPPORTED 0xC0262346	Specified content geometry transformation is not supported on the respective VidPN present path.
ERROR_GRAPHICS_INVALID_GAMMA_RAMP 0xC0262347	Specified gamma ramp is invalid.
ERROR_GRAPHICS_GAMMA_RAMP_NOT_SUPPORTED 0xC0262348	Specified gamma ramp is not supported on the respective VidPN present path.
ERROR_GRAPHICS_MULTISAMPLING_NOT_SUPPORTED 0xC0262349	Multisampling is not supported on the respective VidPN present path.
ERROR_GRAPHICS_MODE_NOT_IN_MODESET 0xC026234A	Specified mode is not in the specified mode set.
ERROR_GRAPHICS_INVALID_VIDPN_TOPOLOGY_RECOMMENDATION_REASON 0xC026234D	Specified VidPN topology recommendation reason is invalid.
ERROR_GRAPHICS_INVALID_PATH_CONTENT_TYPE 0xC026234E	Specified VidPN present path content type is invalid.

Value	Meaning
ERROR_GRAPHICS_INVALID_COPYPROTECTION_TYPE 0xC026234F	Specified VidPN present path copy protection type is invalid.
ERROR_GRAPHICS_UNASSIGNED_MODESET_ALREADY_EXISTS 0xC0262350	No more than one unassigned mode set can exist at any given time for a given VidPN source or target.
ERROR_GRAPHICS_INVALID_SCANLINE_ORDERING 0xC0262352	The specified scan line ordering type is invalid.
ERROR_GRAPHICS_TOPOLOGY_CHANGES_NOT_ALLOWED 0xC0262353	Topology changes are not allowed for the specified VidPN.
ERROR_GRAPHICS_NO_AVAILABLE_IMPORTANCE_ORDINALS 0xC0262354	All available importance ordinals are already used in the specified topology.
ERROR_GRAPHICS_INCOMPATIBLE_PRIVATE_FORMAT 0xC0262355	Specified primary surface has a different private format attribute than the current primary surface.
ERROR_GRAPHICS_INVALID_MODE_PRUNING_ALGORITHM 0xC0262356	Specified mode pruning algorithm is invalid.
ERROR_GRAPHICS_SPECIFIED_CHILD_ALREADY_CONNECTED 0xC0262400	Specified display adapter child device already has an external device connected to it.
ERROR_GRAPHICS_CHILD_DESCRIPTOR_NOT_SUPPORTED 0xC0262401	The display adapter child device does not support reporting a descriptor.
ERROR_GRAPHICS_NOT_A_LINKED_ADAPTER 0xC0262430	The display adapter is not linked to any other adapters.
ERROR_GRAPHICS_LEADLINK_NOT_ENUMERATED 0xC0262431	Lead adapter in a linked configuration was not enumerated yet.
ERROR_GRAPHICS_CHAINLINKS_NOT_ENUMERATED 0xC0262432	Some chain adapters in a linked configuration were not enumerated yet.
ERROR_GRAPHICS_ADAPTER_CHAIN_NOT_READY 0xC0262433	The chain of linked adapters is not ready to start because of an unknown failure.
ERROR_GRAPHICS_CHAINLINKS_NOT_STARTED 0xC0262434	An attempt was made to start a lead link display adapter when the chain links were not started yet.
ERROR_GRAPHICS_CHAINLINKS_NOT_POWERED_ON	An attempt was made to turn on a lead link display adapter

Value	Meaning
0xC0262435	when the chain links were turned off.
ERROR_GRAPHICS_INCONSISTENT_DEVICE_LINK_STATE 0xC0262436	The adapter link was found to be in an inconsistent state. Not all adapters are in an expected PNP or power state.
ERROR_GRAPHICS_NOT_POST_DEVICE_DRIVER 0xC0262438	The driver trying to start is not the same as the driver for the posted display adapter.
ERROR_GRAPHICS_OPM_NOT_SUPPORTED 0xC0262500	The driver does not support Output Protection Manager (OPM).
ERROR_GRAPHICS_COPP_NOT_SUPPORTED 0xC0262501	The driver does not support Certified Output Protection Protocol (COPP).
ERROR_GRAPHICS_UAB_NOT_SUPPORTED 0xC0262502	The driver does not support a user-accessible bus (UAB).
ERROR_GRAPHICS_OPM_INVALID_ENCRYPTED_PARAMETERS 0xC0262503	The specified encrypted parameters are invalid.
ERROR_GRAPHICS_OPM_PARAMETER_ARRAY_TOO_SMALL 0xC0262504	An array passed to a function cannot hold all of the data that the function wants to put in it.
ERROR_GRAPHICS_OPM_NO_VIDEO_OUTPUTS_EXIST 0xC0262505	The GDI display device passed to this function does not have any active video outputs.
ERROR_GRAPHICS_PVP_NO_DISPLAY_DEVICE_CORRESPONDS_TO_NAME 0xC0262506	The protected video path (PVP) cannot find an actual GDI display device that corresponds to the passed-in GDI display device name.
ERROR_GRAPHICS_PVP_DISPLAY_DEVICE_NOT_ATTACHED_TO_DESKTOP 0xC0262507	This function failed because the GDI display device passed to it was not attached to the Windows desktop.
ERROR_GRAPHICS_PVP_MIRRORING_DEVICES_NOT_SUPPORTED 0xC0262508	The PVP does not support mirroring display devices because they do not have video outputs.
ERROR_GRAPHICS_OPM_INVALID_POINTER 0xC026250A	The function failed because an invalid pointer parameter was passed to it. A pointer parameter is invalid if it is null, it points to an invalid address, it points to a kernel mode address, or it is not

Value	Meaning
	correctly aligned.
ERROR_GRAPHICS_OPM_INTERNAL_ERROR 0xC026250B	An internal error caused this operation to fail.
ERROR_GRAPHICS_OPM_INVALID_HANDLE 0xC026250C	The function failed because the caller passed in an invalid OPM user mode handle.
ERROR_GRAPHICS_PVP_NO_MONITORS_CORRESPOND_TO_DISPLAY_DEVICE 0xC026250D	This function failed because the GDI device passed to it did not have any monitors associated with it.
ERROR_GRAPHICS_PVP_INVALID_CERTIFICATE_LENGTH 0xC026250E	A certificate could not be returned because the certificate buffer passed to the function was too small.
ERROR_GRAPHICS_OPM_SPANNING_MODE_ENABLED 0xC026250F	A video output could not be created because the frame buffer is in spanning mode.
ERROR_GRAPHICS_OPM_THEATER_MODE_ENABLED 0xC0262510	A video output could not be created because the frame buffer is in theater mode.
ERROR_GRAPHICS_PVP_HFS_FAILED 0xC0262511	The function call failed because the display adapter's hardware functionality scan failed to validate the graphics hardware.
ERROR_GRAPHICS_OPM_INVALID_SRM 0xC0262512	The High-Bandwidth Digital Content Protection (HDCP) System Renewability Message (SRM) passed to this function did not comply with section 5 of the HDCP 1.1 specification.
ERROR_GRAPHICS_OPM_OUTPUT_DOES_NOT_SUPPORT_HDCP 0xC0262513	The video output cannot enable the HDCP system because it does not support it.
ERROR_GRAPHICS_OPM_OUTPUT_DOES_NOT_SUPPORT_ACP 0xC0262514	The video output cannot enable analog copy protection because it does not support it.
ERROR_GRAPHICS_OPM_OUTPUT_DOES_NOT_SUPPORT_CGMSA 0xC0262515	The video output cannot enable the Content Generation Management System Analog (CGMS-A) protection technology because it does not support it.
ERROR_GRAPHICS_OPM_HDCP_SRM_NEVER_SET 0xC0262516	IOPMVideoOutput's GetInformation() method cannot return the version of



Value	Meaning
	the SRM being used because the application never successfully passed an SRM to the video output.
ERROR_GRAPHICS_OPM_RESOLUTION_TOO_HIGH 0xC0262517	IOPMVideoOutput's Configure() method cannot enable the specified output protection technology because the output's screen resolution is too high.
ERROR_GRAPHICS_OPM_ALL_HDCP_HARDWARE_ALREADY_IN_USE 0xC0262518	IOPMVideoOutput's Configure() method cannot enable HDCP because the display adapter's HDCP hardware is already being used by other physical outputs.
ERROR_GRAPHICS_OPM_VIDEO_OUTPUT_NO_LONGER_EXISTS 0xC0262519	The operating system asynchronously destroyed this OPM video output because the operating system's state changed. This error typically occurs because the monitor physical device object (PDO) associated with this video output was removed, the monitor PDO associated with this video output was stopped, the video output's session became a nonconsole session or the video output's desktop became an inactive desktop.
ERROR_GRAPHICS_OPM_SESSION_TYPE_CHANGE_IN_PROGRESS 0xC026251A	IOPMVideoOutput's methods cannot be called when a session is changing its type. There are currently three types of sessions: console, disconnected and remote (remote desktop protocol [RDP] or Independent Computing Architecture [ICA]).
ERROR_GRAPHICS_I2C_NOT_SUPPORTED 0xC0262580	The monitor connected to the specified video output does not have an I2C bus.
ERROR_GRAPHICS_I2C_DEVICE_DOES_NOT_EXIST 0xC0262581	No device on the I2C bus has the specified address.
ERROR_GRAPHICS_I2C_ERROR_TRANSMITTING_DATA 0xC0262582	An error occurred while transmitting data to the device on the I2C bus.

Value	Meaning
ERROR_GRAPHICS_I2C_ERROR_RECEIVING_DATA 0xC0262583	An error occurred while receiving data from the device on the I2C bus.
ERROR_GRAPHICS_DDCCI_VCP_NOT_SUPPORTED 0xC0262584	The monitor does not support the specified Virtual Control Panel (VCP) code.
ERROR_GRAPHICS_DDCCI_INVALID_DATA 0xC0262585	The data received from the monitor is invalid.
ERROR_GRAPHICS_DDCCI_MONITOR_RETURNED_INVALID_TIMING_STATUS_BYTE 0xC0262586	A function call failed because a monitor returned an invalid Timing Status byte when the operating system used the Display Data Channel Command Interface (DDC/CI) Get Timing Report and Timing Message command to get a timing report from a monitor.
ERROR_GRAPHICS_MCA_INVALID_CAPABILITIES_STRING 0xC0262587	The monitor returned a DDC/CI capabilities string that did not comply with the ACCESS.bus 3.0, DDC/CI 1.1 or MCCS 2 Revision 1 specification.
ERROR_GRAPHICS_MCA_INTERNAL_ERROR 0xC0262588	An internal Monitor Configuration API error occurred.
ERROR_GRAPHICS_DDCCI_INVALID_MESSAGE_COMMAND 0xC0262589	An operation failed because a DDC/CI message had an invalid value in its command field.
ERROR_GRAPHICS_DDCCI_INVALID_MESSAGE_LENGTH 0xC026258A	This error occurred because a DDC/CI message length field contained an invalid value.
ERROR_GRAPHICS_DDCCI_INVALID_MESSAGE_CHECKSUM 0xC026258B	This error occurred because the value in a DDC/CI message checksum field did not match the message's computed checksum value. This error implies that the data was corrupted while it was being transmitted from a monitor to a computer.
ERROR_GRAPHICS_PMEA_INVALID_MONITOR 0xC02625D6	The HMONITOR no longer exists, is not attached to the desktop, or corresponds to a mirroring device.
ERROR_GRAPHICS_PMEA_INVALID_D3D_DEVICE	The Direct3D (D3D) device's

Value	Meaning
0xC02625D7	GDI display device no longer exists, is not attached to the desktop, or is a mirroring display device.
ERROR_GRAPHICS_DDCCI_CURRENT_CURRENT_VALUE_GREATER_THAN_MAXIMUM_VALUE 0xC02625D8	A continuous VCP code's current value is greater than its maximum value. This error code indicates that a monitor returned an invalid value.
ERROR_GRAPHICS_MCA_INVALID_VCP_VERSION 0xC02625D9	The monitor's VCP Version (0xDF) VCP code returned an invalid version value.
ERROR_GRAPHICS_MCA_MONITOR_VIOLATES_MCCS_SPECIFICATION 0xC02625DA	The monitor does not comply with the Monitor Control Command Set (MCCS) specification it claims to support.
ERROR_GRAPHICS_MCA_MCCS_VERSION_MISMATCH 0xC02625DB	The MCCS version in a monitor's mccs_ver capability does not match the MCCS version the monitor reports when the VCP Version (0xDF) VCP code is used.
ERROR_GRAPHICS_MCA_UNSUPPORTED_MCCS_VERSION 0xC02625DC	The Monitor Configuration API only works with monitors that support the MCCS 1.0 specification, the MCCS 2.0 specification, or the MCCS 2.0 Revision 1 specification.
ERROR_GRAPHICS_MCA_INVALID_TECHNOLOGY_TYPE_RETURNED 0xC02625DE	The monitor returned an invalid monitor technology type. CRT, plasma, and LCD (TFT) are examples of monitor technology types. This error implies that the monitor violated the MCCS 2.0 or MCCS 2.0 Revision 1 specification.
ERROR_GRAPHICS_MCA_UNSUPPORTED_COLOR_TEMPERATURE 0xC02625DF	The SetMonitorColorTemperature() caller passed a color temperature to it that the current monitor did not support. CRT, plasma, and LCD (TFT) are examples of monitor technology types. This error implies that the monitor violated the MCCS 2.0 or MCCS 2.0 Revision 1 specification.

Value	Meaning
ERROR_GRAPHICS_ONLY_CONSOLE_SESSION_SUPPORTED 0xC02625E0	This function can be used only if a program is running in the local console session. It cannot be used if the program is running on a remote desktop session or on a terminal server session.

## 2.2 Win32 Error Codes

All Win32 error codes MUST be in the range 0x0000 to 0xFFFF, although Win32 error codes can be used both in 16-bit fields (such as within the HRESULT type specified in section [2.1](#)) as well as 32-bit fields. Most values also have a default message defined, which can be used to map the value to a human-readable text message; when this is done, the Win32 error code is also known as a message identifier.

Vendors SHOULD reuse the values in the following table with their indicated meanings. Choosing any other value runs the risk of a collision in the future. [<2>](#)

Note: In the following descriptions, a percentage sign followed by one or more alphanumeric characters (for example, "%1" or "%hs") indicates a variable that will be replaced by text at the time the value is returned.

Win32 error codes	Description
0x00000000 ERROR_SUCCESS	The operation completed successfully.
0x00000000 NERR_Success	The operation completed successfully.
0x00000001 ERROR_INVALID_FUNCTION	Incorrect function.
0x00000002 ERROR_FILE_NOT_FOUND	The system cannot find the file specified.
0x00000003 ERROR_PATH_NOT_FOUND	The system cannot find the path specified.
0x00000004 ERROR_TOO_MANY_OPEN_FILES	The system cannot open the file.
0x00000005 ERROR_ACCESS_DENIED	Access is denied.
0x00000006 ERROR_INVALID_HANDLE	The handle is invalid.
0x00000007 ERROR_ARENA_TRASHED	The storage control blocks were destroyed.
0x00000008 ERROR_NOT_ENOUGH_MEMORY	Not enough storage is available to process this command.

Win32 error codes	Description
0x00000009 ERROR_INVALID_BLOCK	The storage control block address is invalid.
0x0000000A ERROR_BAD_ENVIRONMENT	The environment is incorrect.
0x0000000B ERROR_BAD_FORMAT	An attempt was made to load a program with an incorrect format.
0x0000000C ERROR_INVALID_ACCESS	The access code is invalid.
0x0000000D ERROR_INVALID_DATA	The data is invalid.
0x0000000E ERROR_OUTOFMEMORY	Not enough storage is available to complete this operation.
0x0000000F ERROR_INVALID_DRIVE	The system cannot find the drive specified.
0x00000010 ERROR_CURRENT_DIRECTORY	The directory cannot be removed.
0x00000011 ERROR_NOT_SAME_DEVICE	The system cannot move the file to a different disk drive.
0x00000012 ERROR_NO_MORE_FILES	There are no more files.
0x00000013 ERROR_WRITE_PROTECT	The media is write-protected.
0x00000014 ERROR_BAD_UNIT	The system cannot find the device specified.
0x00000015 ERROR_NOT_READY	The device is not ready.
0x00000016 ERROR_BAD_COMMAND	The device does not recognize the command.
0x00000017 ERROR_CRC	Data error (cyclic redundancy check).
0x00000018 ERROR_BAD_LENGTH	The program issued a command but the command length is incorrect.
0x00000019 ERROR_SEEK	The drive cannot locate a specific area or track on the disk.
0x0000001A ERROR_NOT_DOS_DISK	The specified disk cannot be accessed.
0x0000001B ERROR_SECTOR_NOT_FOUND	The drive cannot find the sector requested.
0x0000001C	The printer is out of paper.

Win32 error codes	Description
ERROR_OUT_OF_PAPER	
0x0000001D ERROR_WRITE_FAULT	The system cannot write to the specified device.
0x0000001E ERROR_READ_FAULT	The system cannot read from the specified device.
0x0000001F ERROR_GEN_FAILURE	A device attached to the system is not functioning.
0x00000020 ERROR_SHARING_VIOLATION	The process cannot access the file because it is being used by another process.
0x00000021 ERROR_LOCK_VIOLATION	The process cannot access the file because another process has locked a portion of the file.
0x00000022 ERROR_WRONG_DISK	The wrong disk is in the drive. Insert %2 (Volume Serial Number: %3) into drive %1.
0x00000024 ERROR_SHARING_BUFFER_EXCEEDED	Too many files opened for sharing.
0x00000026 ERROR_HANDLE_EOF	Reached the end of the file.
0x00000027 ERROR_HANDLE_DISK_FULL	The disk is full.
0x00000032 ERROR_NOT_SUPPORTED	The request is not supported.
0x00000033 ERROR_REM_NOT_LIST	Windows cannot find the network path. Verify that the network path is correct and the destination computer is not busy or turned off. If Windows still cannot find the network path, contact your network administrator.
0x00000034 ERROR_DUP_NAME	You were not connected because a duplicate name exists on the network. Go to System in Control Panel to change the computer name, and then try again.
0x00000035 ERROR_BAD_NETPATH	The network path was not found.
0x00000036 ERROR_NETWORK_BUSY	The network is busy.
0x00000037 ERROR_DEV_NOT_EXIST	The specified network resource or device is no longer available.
0x00000038 ERROR_TOO_MANY_CMDS	The network BIOS command limit has been reached.
0x00000039 ERROR_ADAP_HDW_ERR	A network adapter hardware error occurred.

Win32 error codes	Description
0x0000003A ERROR_BAD_NET_RESP	The specified server cannot perform the requested operation.
0x0000003B ERROR_UNEXP_NET_ERR	An unexpected network error occurred.
0x0000003C ERROR_BAD_REM_ADAP	The remote adapter is not compatible.
0x0000003D ERROR_PRINTQ_FULL	The print queue is full.
0x0000003E ERROR_NO_SPOOL_SPACE	Space to store the file waiting to be printed is not available on the server.
0x0000003F ERROR_PRINT_CANCELLED	Your file waiting to be printed was deleted.
0x00000040 ERROR_NETNAME_DELETED	The specified network name is no longer available.
0x00000041 ERROR_NETWORK_ACCESS_DENIED	Network access is denied.
0x00000042 ERROR_BAD_DEV_TYPE	The network resource type is not correct.
0x00000043 ERROR_BAD_NET_NAME	The network name cannot be found.
0x00000044 ERROR_TOO_MANY_NAMES	The name limit for the local computer network adapter card was exceeded.
0x00000045 ERROR_TOO_MANY_SESS	The network BIOS session limit was exceeded.
0x00000046 ERROR_SHARING_PAUSED	The remote server has been paused or is in the process of being started.
0x00000047 ERROR_REQ_NOT_ACCEP	No more connections can be made to this remote computer at this time because the computer has accepted the maximum number of connections.
0x00000048 ERROR_REDIR_PAUSED	The specified printer or disk device has been paused.
0x00000050 ERROR_FILE_EXISTS	The file exists.
0x00000052 ERROR_CANNOT_MAKE	The directory or file cannot be created.
0x00000053 ERROR_FAIL_I24	Fail on INT 24.
0x00000054 ERROR_OUT_OF_STRUCTURES	Storage to process this request is not available.

Win32 error codes	Description
0x00000055 ERROR_ALREADY_ASSIGNED	The local device name is already in use.
0x00000056 ERROR_INVALID_PASSWORD	The specified network password is not correct.
0x00000057 ERROR_INVALID_PARAMETER	The parameter is incorrect.
0x00000058 ERROR_NET_WRITE_FAULT	A write fault occurred on the network.
0x00000059 ERROR_NO_PROC_SLOTS	The system cannot start another process at this time.
0x00000064 ERROR_TOO_MANY_SEMAPHORES	Cannot create another system semaphore.
0x00000065 ERROR_EXCL_SEM_ALREADY_OWNED	The exclusive semaphore is owned by another process.
0x00000066 ERROR_SEM_IS_SET	The semaphore is set and cannot be closed.
0x00000067 ERROR_TOO_MANY_SEM_REQUESTS	The semaphore cannot be set again.
0x00000068 ERROR_INVALID_AT_INTERRUPT_TIME	Cannot request exclusive semaphores at interrupt time.
0x00000069 ERROR_SEM_OWNER_DIED	The previous ownership of this semaphore has ended.
0x0000006A ERROR_SEM_USER_LIMIT	Insert the disk for drive %1.
0x0000006B ERROR_DISK_CHANGE	The program stopped because an alternate disk was not inserted.
0x0000006C ERROR_DRIVE_LOCKED	The disk is in use or locked by another process.
0x0000006D ERROR_BROKEN_PIPE	The pipe has been ended.
0x0000006E ERROR_OPEN_FAILED	The system cannot open the device or file specified.
0x0000006F ERROR_BUFFER_OVERFLOW	The file name is too long.
0x00000070 ERROR_DISK_FULL	There is not enough space on the disk.
0x00000071 ERROR_NO_MORE_SEARCH_HANDLES	No more internal file identifiers are available.
0x00000072	The target internal file identifier is incorrect.



Win32 error codes	Description
ERROR_INVALID_TARGET_HANDLE	
0x00000075 ERROR_INVALID_CATEGORY	The Input Output Control (IOCTL) call made by the application program is not correct.
0x00000076 ERROR_INVALID_VERIFY_SWITCH	The verify-on-write switch parameter value is not correct.
0x00000077 ERROR_BAD_DRIVER_LEVEL	The system does not support the command requested.
0x00000078 ERROR_CALL_NOT_IMPLEMENTED	This function is not supported on this system.
0x00000079 ERROR_SEM_TIMEOUT	The semaphore time-out period has expired.
0x0000007A ERROR_INSUFFICIENT_BUFFER	The data area passed to a system call is too small.
0x0000007B ERROR_INVALID_NAME	The file name, directory name, or volume label syntax is incorrect.
0x0000007C ERROR_INVALID_LEVEL	The system call level is not correct.
0x0000007D ERROR_NO_VOLUME_LABEL	The disk has no volume label.
0x0000007E ERROR_MOD_NOT_FOUND	The specified module could not be found.
0x0000007F ERROR_PROC_NOT_FOUND	The specified procedure could not be found.
0x00000080 ERROR_WAIT_NO_CHILDREN	There are no child processes to wait for.
0x00000081 ERROR_CHILD_NOT_COMPLETE	The %1 application cannot be run in Win32 mode.
0x00000082 ERROR_DIRECT_ACCESS_HANDLE	Attempt to use a file handle to an open disk partition for an operation other than raw disk I/O.
0x00000083 ERROR_NEGATIVE_SEEK	An attempt was made to move the file pointer before the beginning of the file.
0x00000084 ERROR_SEEK_ON_DEVICE	The file pointer cannot be set on the specified device or file.
0x00000085 ERROR_IS_JOIN_TARGET	A <b>JOIN</b> or <b>SUBST</b> command cannot be used for a drive that contains previously joined drives.
0x00000086 ERROR_IS_JOINED	An attempt was made to use a <b>JOIN</b> or <b>SUBST</b> command on a drive that has already been joined.

Win32 error codes	Description
0x00000087 ERROR_IS_SUBSTED	An attempt was made to use a <b>JOIN</b> or <b>SUBST</b> command on a drive that has already been substituted.
0x00000088 ERROR_NOT_JOINED	The system tried to delete the <b>JOIN</b> of a drive that is not joined.
0x00000089 ERROR_NOT_SUBSTED	The system tried to delete the substitution of a drive that is not substituted.
0x0000008A ERROR_JOIN_TO_JOIN	The system tried to join a drive to a directory on a joined drive.
0x0000008B ERROR_SUBST_TO_SUBST	The system tried to substitute a drive to a directory on a substituted drive.
0x0000008C ERROR_JOIN_TO_SUBST	The system tried to join a drive to a directory on a substituted drive.
0x0000008D ERROR_SUBST_TO_JOIN	The system tried to <b>SUBST</b> a drive to a directory on a joined drive.
0x0000008E ERROR_BUSY_DRIVE	The system cannot perform a <b>JOIN</b> or <b>SUBST</b> at this time.
0x0000008F ERROR_SAME_DRIVE	The system cannot join or substitute a drive to or for a directory on the same drive.
0x00000090 ERROR_DIR_NOT_ROOT	The directory is not a subdirectory of the root directory.
0x00000091 ERROR_DIR_NOT_EMPTY	The directory is not empty.
0x00000092 ERROR_IS_SUBST_PATH	The path specified is being used in a substitute.
0x00000093 ERROR_IS_JOIN_PATH	Not enough resources are available to process this command.
0x00000094 ERROR_PATH_BUSY	The path specified cannot be used at this time.
0x00000095 ERROR_IS_SUBST_TARGET	An attempt was made to join or substitute a drive for which a directory on the drive is the target of a previous substitute.
0x00000096 ERROR_SYSTEM_TRACE	System trace information was not specified in your CONFIG.SYS file, or tracing is disallowed.
0x00000097 ERROR_INVALID_EVENT_COUNT	The number of specified semaphore events for DosMuxSemWait is not correct.
0x00000098 ERROR_TOO_MANY_MUXWAITERS	DosMuxSemWait did not execute; too many semaphores are already set.
0x00000099 ERROR_INVALID_LIST_FORMAT	The DosMuxSemWait list is not correct.

Win32 error codes	Description
0x0000009A ERROR_LABEL_TOO_LONG	The volume label you entered exceeds the label character limit of the destination file system.
0x0000009B ERROR_TOO_MANY_TCBS	Cannot create another thread.
0x0000009C ERROR_SIGNAL_REFUSED	The recipient process has refused the signal.
0x0000009D ERROR_DISCARDED	The segment is already discarded and cannot be locked.
0x0000009E ERROR_NOT_LOCKED	The segment is already unlocked.
0x0000009F ERROR_BAD_THREADID_ADDR	The address for the thread ID is not correct.
0x000000A0 ERROR_BAD_ARGUMENTS	One or more arguments are not correct.
0x000000A1 ERROR_BAD_PATHNAME	The specified path is invalid.
0x000000A2 ERROR_SIGNAL_PENDING	A signal is already pending.
0x000000A4 ERROR_MAX_THRDS_REACHED	No more threads can be created in the system.
0x000000A7 ERROR_LOCK_FAILED	Unable to lock a region of a file.
0x000000AA ERROR_BUSY	The requested resource is in use.
0x000000AD ERROR_CANCEL_VIOLATION	A lock request was not outstanding for the supplied cancel region.
0x000000AE ERROR_ATOMIC_LOCKS_NOT_SUPPORTED	The file system does not support atomic changes to the lock type.
0x000000B4 ERROR_INVALID_SEGMENT_NUMBER	The system detected a segment number that was not correct.
0x000000B6 ERROR_INVALID_ORDINAL	The operating system cannot run %1.
0x000000B7 ERROR_ALREADY_EXISTS	Cannot create a file when that file already exists.
0x000000BA ERROR_INVALID_FLAG_NUMBER	The flag passed is not correct.
0x000000BB ERROR_SEM_NOT_FOUND	The specified system semaphore name was not found.
0x000000BC	The operating system cannot run %1.

Win32 error codes	Description
ERROR_INVALID_STARTING_CODESEG	
0x000000BD ERROR_INVALID_STACKSEG	The operating system cannot run %1.
0x000000BE ERROR_INVALID_MODULETYPE	The operating system cannot run %1.
0x000000BF ERROR_INVALID_EXE_SIGNATURE	Cannot run %1 in Win32 mode.
0x000000C0 ERROR_EXE_MARKED_INVALID	The operating system cannot run %1.
0x000000C1 ERROR_BAD_EXE_FORMAT	%1 is not a valid Win32 application.
0x000000C2 ERROR_ITERATED_DATA_EXCEEDS_64k	The operating system cannot run %1.
0x000000C3 ERROR_INVALID_MINALLOCSIZE	The operating system cannot run %1.
0x000000C4 ERROR_DYNLINK_FROM_INVALID_RING	The operating system cannot run this application program.
0x000000C5 ERROR_IOPL_NOT_ENABLED	The operating system is not presently configured to run this application.
0x000000C6 ERROR_INVALID_SEGDPL	The operating system cannot run %1.
0x000000C7 ERROR_AUTODATASEG_EXCEEDS_64k	The operating system cannot run this application program.
0x000000C8 ERROR_RING2SEG_MUST_BE_MOVABLE	The code segment cannot be greater than or equal to 64 KB.
0x000000C9 ERROR_RELOC_CHAIN_XEEDS_SEGLIM	The operating system cannot run %1.
0x000000CA ERROR_INFLOOP_IN_RELOC_CHAIN	The operating system cannot run %1.
0x000000CB ERROR_ENVVAR_NOT_FOUND	The system could not find the environment option that was entered.
0x000000CD ERROR_NO_SIGNAL_SENT	No process in the command subtree has a signal handler.
0x000000CE ERROR_FILENAME_EXCED_RANGE	The file name or extension is too long.
0x000000CF ERROR_RING2_STACK_IN_USE	The ring 2 stack is in use.
0x000000D0 ERROR_META_EXPANSION_TOO_LONG	The asterisk (*) or question mark (?) global file name characters are entered incorrectly, or too

Win32 error codes	Description
	many global file name characters are specified.
0x000000D1 ERROR_INVALID_SIGNAL_NUMBER	The signal being posted is not correct.
0x000000D2 ERROR_THREAD_1_INACTIVE	The signal handler cannot be set.
0x000000D4 ERROR_LOCKED	The segment is locked and cannot be reallocated.
0x000000D6 ERROR_TOO_MANY_MODULES	Too many dynamic-link modules are attached to this program or dynamic-link module.
0x000000D7 ERROR_NESTING_NOT_ALLOWED	Cannot nest calls to LoadModule.
0x000000D8 ERROR_EXE_MACHINE_TYPE_MISMATCH	This version of %1 is not compatible with the version of Windows you're running. Check your computer's system information to see whether you need an x86 (32-bit) or x64 (64-bit) version of the program, and then contact the software publisher.
0x000000D9 ERROR_EXE_CANNOT_MODIFY_SIGNED_BINARY	The image file %1 is signed, unable to modify.
0x000000DA ERROR_EXE_CANNOT_MODIFY_STRONG_SIGNED_BINARY	The image file %1 is strong signed, unable to modify.
0x000000DC ERROR_FILE_CHECKED_OUT	This file is checked out or locked for editing by another user.
0x000000DD ERROR_CHECKOUT_REQUIRED	The file must be checked out before saving changes.
0x000000DE ERROR_BAD_FILE_TYPE	The file type being saved or retrieved has been blocked.
0x000000DF ERROR_FILE_TOO_LARGE	The file size exceeds the limit allowed and cannot be saved.
0x000000E0 ERROR_FORMS_AUTH_REQUIRED	Access denied. Before opening files in this location, you must first browse to the Web site and select the option to sign in automatically.
0x000000E1 ERROR_VIRUS_INFECTED	Operation did not complete successfully because the file contains a virus.
0x000000E2 ERROR_VIRUS_DELETED	This file contains a virus and cannot be opened. Due to the nature of this virus, the file has been removed from this location.
0x000000E5 ERROR_PIPE_LOCAL	The pipe is local.
0x000000E6	The pipe state is invalid.

Win32 error codes	Description
ERROR_BAD_PIPE	
0x000000E7 ERROR_PIPE_BUSY	All pipe instances are busy.
0x000000E8 ERROR_NO_DATA	The pipe is being closed.
0x000000E9 ERROR_PIPE_NOT_CONNECTED	No process is on the other end of the pipe.
0x000000EA ERROR_MORE_DATA	More data is available.
0x000000F0 ERROR_VC_DISCONNECTED	The session was canceled.
0x000000FE ERROR_INVALID_EA_NAME	The specified extended attribute name was invalid.
0x000000FF ERROR_EA_LIST_INCONSISTENT	The extended attributes are inconsistent.
0x00000102 WAIT_TIMEOUT	The wait operation timed out.
0x00000103 ERROR_NO_MORE_ITEMS	No more data is available.
0x0000010A ERROR_CANNOT_COPY	The copy functions cannot be used.
0x0000010B ERROR_DIRECTORY	The directory name is invalid.
0x00000113 ERROR_EAS_DIDNT_FIT	The extended attributes did not fit in the buffer.
0x00000114 ERROR_EA_FILE_CORRUPT	The extended attribute file on the mounted file system is corrupt.
0x00000115 ERROR_EA_TABLE_FULL	The extended attribute table file is full.
0x00000116 ERROR_INVALID_EA_HANDLE	The specified extended attribute handle is invalid.
0x0000011A ERROR_EAS_NOT_SUPPORTED	The mounted file system does not support extended attributes.
0x00000120 ERROR_NOT_OWNER	Attempt to release mutex not owned by caller.
0x0000012A ERROR_TOO_MANY_POSTS	Too many posts were made to a semaphore.
0x0000012B ERROR_PARTIAL_COPY	Only part of a ReadProcessMemory or WriteProcessMemory request was completed.

Win32 error codes	Description
0x0000012C ERROR_OPLOCK_NOT_GRANTED	The oplock request is denied.
0x0000012D ERROR_INVALID_OPLOCK_PROTOCOL	An invalid oplock acknowledgment was received by the system.
0x0000012E ERROR_DISK_TOO_FRAGMENTED	The volume is too fragmented to complete this operation.
0x0000012F ERROR_DELETE_PENDING	The file cannot be opened because it is in the process of being deleted.
0x0000013D ERROR_MR_MID_NOT_FOUND	The system cannot find message text for message number 0x%1 in the message file for %2.
0x0000013E ERROR_SCOPE_NOT_FOUND	The scope specified was not found.
0x0000015E ERROR_FAIL_NOACTION_REBOOT	No action was taken because a system reboot is required.
0x0000015F ERROR_FAIL_SHUTDOWN	The shutdown operation failed.
0x00000160 ERROR_FAIL_RESTART	The restart operation failed.
0x00000161 ERROR_MAX_SESSIONS_REACHED	The maximum number of sessions has been reached.
0x00000190 ERROR_THREAD_MODE_ALREADY_BACKGROUND	The thread is already in background processing mode.
0x00000191 ERROR_THREAD_MODE_NOT_BACKGROUND	The thread is not in background processing mode.
0x00000192 ERROR_PROCESS_MODE_ALREADY_BACKGROUND	The process is already in background processing mode.
0x00000193 ERROR_PROCESS_MODE_NOT_BACKGROUND	The process is not in background processing mode.
0x000001E7 ERROR_INVALID_ADDRESS	Attempt to access invalid address.
0x000001F4 ERROR_USER_PROFILE_LOAD	User profile cannot be loaded.
0x00000216 ERROR_ARITHMETIC_OVERFLOW	Arithmetic result exceeded 32 bits.
0x00000217 ERROR_PIPE_CONNECTED	There is a process on the other end of the pipe.
0x00000218 ERROR_PIPE_LISTENING	Waiting for a process to open the other end of the pipe.

Win32 error codes	Description
0x00000219 ERROR_VERIFIER_STOP	Application verifier has found an error in the current process.
0x0000021A ERROR_ABIOS_ERROR	An error occurred in the ABIOS subsystem.
0x0000021B ERROR_WX86_WARNING	A warning occurred in the WX86 subsystem.
0x0000021C ERROR_WX86_ERROR	An error occurred in the WX86 subsystem.
0x0000021D ERROR_TIMER_NOT_CANCELED	An attempt was made to cancel or set a timer that has an associated asynchronous procedure call (APC) and the subject thread is not the thread that originally set the timer with an associated APC routine.
0x0000021E ERROR_UNWIND	Unwind exception code.
0x0000021F ERROR_BAD_STACK	An invalid or unaligned stack was encountered during an unwind operation.
0x00000220 ERROR_INVALID_UNWIND_TARGET	An invalid unwind target was encountered during an unwind operation.
0x00000221 ERROR_INVALID_PORT_ATTRIBUTES	Invalid object attributes specified to NtCreatePort or invalid port attributes specified to NtConnectPort.
0x00000222 ERROR_PORT_MESSAGE_TOO_LONG	Length of message passed to NtRequestPort or NtRequestWaitReplyPort was longer than the maximum message allowed by the port.
0x00000223 ERROR_INVALID_QUOTA_LOWER	An attempt was made to lower a quota limit below the current usage.
0x00000224 ERROR_DEVICE_ALREADY_ATTACHED	An attempt was made to attach to a device that was already attached to another device.
0x00000225 ERROR_INSTRUCTION_MISALIGNMENT	An attempt was made to execute an instruction at an unaligned address, and the host system does not support unaligned instruction references.
0x00000226 ERROR_PROFILING_NOT_STARTED	Profiling not started.
0x00000227 ERROR_PROFILING_NOT_STOPPED	Profiling not stopped.
0x00000228 ERROR_COULD_NOT_INTERPRET	The passed ACL did not contain the minimum required information.
0x00000229 ERROR_PROFILING_AT_LIMIT	The number of active profiling objects is at the maximum and no more may be started.



Win32 error codes	Description
0x0000022A ERROR_CANT_WAIT	Used to indicate that an operation cannot continue without blocking for I/O.
0x0000022B ERROR_CANT_TERMINATE_SELF	Indicates that a thread attempted to terminate itself by default (called NtTerminateThread with NULL) and it was the last thread in the current process.
0x0000022C ERROR_UNEXPECTED_MM_CREATE_ERR	If an MM error is returned that is not defined in the standard FsRtl filter, it is converted to one of the following errors that is guaranteed to be in the filter. In this case, information is lost; however, the filter correctly handles the exception.
0x0000022D ERROR_UNEXPECTED_MM_MAP_ERROR	If an MM error is returned that is not defined in the standard FsRtl filter, it is converted to one of the following errors that is guaranteed to be in the filter. In this case, information is lost; however, the filter correctly handles the exception.
0x0000022E ERROR_UNEXPECTED_MM_EXTEND_ERR	If an MM error is returned that is not defined in the standard FsRtl filter, it is converted to one of the following errors that is guaranteed to be in the filter. In this case, information is lost; however, the filter correctly handles the exception.
0x0000022F ERROR_BAD_FUNCTION_TABLE	A malformed function table was encountered during an unwind operation.
0x00000230 ERROR_NO_GUID_TRANSLATION	Indicates that an attempt was made to assign protection to a file system file or directory and one of the SIDs in the security descriptor could not be translated into a GUID that could be stored by the file system. This causes the protection attempt to fail, which may cause a file creation attempt to fail.
0x00000231 ERROR_INVALID_LDT_SIZE	Indicates that an attempt was made to grow a local domain table (LDT) by setting its size, or that the size was not an even number of selectors.
0x00000233 ERROR_INVALID_LDT_OFFSET	Indicates that the starting value for the LDT information was not an integral multiple of the selector size.
0x00000234 ERROR_INVALID_LDT_DESCRIPTOR	Indicates that the user supplied an invalid descriptor when trying to set up LDT descriptors.
0x00000235 ERROR_TOO_MANY_THREADS	Indicates a process has too many threads to perform the requested action. For example, assignment of a primary token may only be performed when a process has zero or one

Win32 error codes	Description
	threads.
0x00000236 ERROR_THREAD_NOT_IN_PROCESS	An attempt was made to operate on a thread within a specific process, but the thread specified is not in the process specified.
0x00000237 ERROR_PAGEFILE_QUOTA_EXCEEDED	Page file quota was exceeded.
0x00000238 ERROR_LOGON_SERVER_CONFLICT	The Netlogon service cannot start because another Netlogon service running in the domain conflicts with the specified role.
0x00000239 ERROR_SYNCHRONIZATION_REQUIRED	The Security Accounts Manager (SAM) database on a Windows Server is significantly out of synchronization with the copy on the domain controller. A complete synchronization is required.
0x0000023A ERROR_NET_OPEN_FAILED	The NtCreateFile API failed. This error should never be returned to an application, it is a place holder for the Windows LAN Manager Redirector to use in its internal error mapping routines.
0x0000023B ERROR_IO_PRIVILEGE_FAILED	{Privilege Failed} The I/O permissions for the process could not be changed.
0x0000023C ERROR_CONTROL_C_EXIT	{Application Exit by CTRL+C} The application terminated as a result of a CTRL+C.
0x0000023D ERROR_MISSING_SYSTEMFILE	{Missing System File} The required system file %hs is bad or missing.
0x0000023E ERROR_UNHANDLED_EXCEPTION	{Application Error} The exception %s (0x%08lx) occurred in the application at location 0x%08lx.
0x0000023F ERROR_APP_INIT_FAILURE	{Application Error} The application failed to initialize properly (0x%lx). Click OK to terminate the application.
0x00000240 ERROR_PAGEFILE_CREATE_FAILED	{Unable to Create Paging File} The creation of the paging file %hs failed (%lx). The requested size was %ld.
0x00000241 ERROR_INVALID_IMAGE_HASH	The hash for the image cannot be found in the system catalogs. The image is likely corrupt or the victim of tampering.
0x00000242 ERROR_NO_PAGEFILE	{No Paging File Specified} No paging file was specified in the system configuration.
0x00000243 ERROR_ILLEGAL_FLOAT_CONTEXT	{EXCEPTION} A real-mode application issued a floating-point instruction, and floating-point hardware is not present.
0x00000244	An event pair synchronization operation was

Win32 error codes	Description
ERROR_NO_EVENT_PAIR	performed using the thread-specific client/server event pair object, but no event pair object was associated with the thread.
0x00000245 ERROR_DOMAIN_CTRLR_CONFIG_ERROR	A Windows Server has an incorrect configuration.
0x00000246 ERROR_ILLEGAL_CHARACTER	An illegal character was encountered. For a multibyte character set, this includes a lead byte without a succeeding trail byte. For the Unicode character set, this includes the characters 0xFFFF and 0xFFFE.
0x00000247 ERROR_UNDEFINED_CHARACTER	The Unicode character is not defined in the Unicode character set installed on the system.
0x00000248 ERROR_FLOPPY_VOLUME	The paging file cannot be created on a floppy disk.
0x00000249 ERROR_BIOS_FAILED_TO_CONNECT_INTERRUPT	The system bios failed to connect a system interrupt to the device or bus for which the device is connected.
0x0000024A ERROR_BACKUP_CONTROLLER	This operation is only allowed for the primary domain controller (PDC) of the domain.
0x0000024B ERROR_MUTANT_LIMIT_EXCEEDED	An attempt was made to acquire a mutant such that its maximum count would have been exceeded.
0x0000024C ERROR_FS_DRIVER_REQUIRED	A volume has been accessed for which a file system driver is required that has not yet been loaded.
0x0000024D ERROR_CANNOT_LOAD_REGISTRY_FILE	{Registry File Failure} The registry cannot load the hive (file): %hs or its log or alternate. It is corrupt, absent, or not writable.
0x0000024E ERROR_DEBUG_ATTACH_FAILED	{Unexpected Failure in DebugActiveProcess} An unexpected failure occurred while processing a DebugActiveProcess API request. You may choose OK to terminate the process, or Cancel to ignore the error.
0x0000024F ERROR_SYSTEM_PROCESS_TERMINATED	{Fatal System Error} The %hs system process terminated unexpectedly with a status of 0x%08x (0x%08x 0x%08x). The system has been shut down.
0x00000250 ERROR_DATA_NOT_ACCEPTED	{Data Not Accepted} The transport driver interface (TDI) client could not handle the data received during an indication.
0x00000251 ERROR_VDM_HARD_ERROR	The NT Virtual DOS Machine (NTVDM) encountered a hard error.
0x00000252 ERROR_DRIVER_CANCEL_TIMEOUT	{Cancel Timeout} The driver %hs failed to complete a canceled I/O request in the allotted

Win32 error codes	Description
	time.
0x00000253 ERROR_REPLY_MESSAGE_MISMATCH	{Reply Message Mismatch} An attempt was made to reply to a local procedure call (LPC) message, but the thread specified by the client ID in the message was not waiting on that message.
0x00000254 ERROR_LOST_WRITEBEHIND_DATA	{Delayed Write Failed} Windows was unable to save all the data for the file %hs. The data has been lost. This error may be caused by a failure of your computer hardware or network connection. Try to save this file elsewhere.
0x00000255 ERROR_CLIENT_SERVER_PARAMETERS_INVALID	The parameters passed to the server in the client/server shared memory window were invalid. Too much data may have been put in the shared memory window.
0x00000256 ERROR_NOT_TINY_STREAM	The stream is not a tiny stream.
0x00000257 ERROR_STACK_OVERFLOW_READ	The request must be handled by the stack overflow code.
0x00000258 ERROR_CONVERT_TO_LARGE	Internal OFS status codes indicating how an allocation operation is handled. Either it is retried after the containing onode is moved or the extent stream is converted to a large stream.
0x00000259 ERROR_FOUND_OUT_OF_SCOPE	The attempt to find the object found an object matching by ID on the volume but it is out of the scope of the handle used for the operation.
0x0000025A ERROR_ALLOCATE_BUCKET	The bucket array must be grown. Retry transaction after doing so.
0x0000025B ERROR_MARSHALL_OVERFLOW	The user/kernel marshaling buffer has overflowed.
0x0000025C ERROR_INVALID_VARIANT	The supplied variant structure contains invalid data.
0x0000025D ERROR_BAD_COMPRESSION_BUFFER	The specified buffer contains ill-formed data.
0x0000025E ERROR_AUDIT_FAILED	{Audit Failed} An attempt to generate a security audit failed.
0x0000025F ERROR_TIMER_RESOLUTION_NOT_SET	The timer resolution was not previously set by the current process.
0x00000260 ERROR_INSUFFICIENT_LOGON_INFO	There is insufficient account information to log you on.
0x00000261 ERROR_BAD_DLL_ENTRYPOINT	{Invalid DLL Entrypoint} The dynamic link library %hs is not written correctly. The stack

Win32 error codes	Description
	pointer has been left in an inconsistent state. The entry point should be declared as WINAPI or STDCALL. Select YES to fail the DLL load. Select NO to continue execution. Selecting NO may cause the application to operate incorrectly.
0x00000262 ERROR_BAD_SERVICE_ENTRYPOINT	{Invalid Service Callback Entrypoint} The %hs service is not written correctly. The stack pointer has been left in an inconsistent state. The callback entry point should be declared as WINAPI or STDCALL. Selecting OK will cause the service to continue operation. However, the service process may operate incorrectly.
0x00000263 ERROR_IP_ADDRESS_CONFLICT1	There is an IP address conflict with another system on the network.
0x00000264 ERROR_IP_ADDRESS_CONFLICT2	There is an IP address conflict with another system on the network.
0x00000265 ERROR_REGISTRY_QUOTA_LIMIT	{Low On Registry Space} The system has reached the maximum size allowed for the system part of the registry. Additional storage requests will be ignored.
0x00000266 ERROR_NO_CALLBACK_ACTIVE	A callback return system service cannot be executed when no callback is active.
0x00000267 ERROR_PWD_TOO_SHORT	The password provided is too short to meet the policy of your user account. Choose a longer password.
0x00000268 ERROR_PWD_TOO_RECENT	The policy of your user account does not allow you to change passwords too frequently. This is done to prevent users from changing back to a familiar, but potentially discovered, password. If you feel your password has been compromised, contact your administrator immediately to have a new one assigned.
0x00000269 ERROR_PWD_HISTORY_CONFLICT	You have attempted to change your password to one that you have used in the past. The policy of your user account does not allow this. Select a password that you have not previously used.
0x0000026A ERROR_UNSUPPORTED_COMPRESSION	The specified compression format is unsupported.
0x0000026B ERROR_INVALID_HW_PROFILE	The specified hardware profile configuration is invalid.
0x0000026C ERROR_INVALID_PLUGPLAY_DEVICE_PATH	The specified Plug and Play registry device path is invalid.
0x0000026D ERROR_QUOTA_LIST_INCONSISTENT	The specified quota list is internally inconsistent with its descriptor.

Win32 error codes	Description
0x0000026E ERROR_EVALUATION_EXPIRATION	{Windows Evaluation Notification} The evaluation period for this installation of Windows has expired. This system will shut down in 1 hour. To restore access to this installation of Windows, upgrade this installation using a licensed distribution of this product.
0x0000026F ERROR_ILLEGAL_DLL_RELOCATION	{Illegal System DLL Relocation} The system DLL %hs was relocated in memory. The application will not run properly. The relocation occurred because the DLL %hs occupied an address range reserved for Windows system DLLs. The vendor supplying the DLL should be contacted for a new DLL.
0x00000270 ERROR_DLL_INIT_FAILED_LOGOFF	{DLL Initialization Failed} The application failed to initialize because the window station is shutting down.
0x00000271 ERROR_VALIDATE_CONTINUE	The validation process needs to continue on to the next step.
0x00000272 ERROR_NO_MORE_MATCHES	There are no more matches for the current index enumeration.
0x00000273 ERROR_RANGE_LIST_CONFLICT	The range could not be added to the range list because of a conflict.
0x00000274 ERROR_SERVER_SID_MISMATCH	The server process is running under a SID different than that required by the client.
0x00000275 ERROR_CANT_ENABLE_DENY_ONLY	A group marked use for deny only cannot be enabled.
0x00000276 ERROR_FLOAT_MULTIPLE_FAULTS	{EXCEPTION} Multiple floating point faults.
0x00000277 ERROR_FLOAT_MULTIPLE_TRAPS	{EXCEPTION} Multiple floating point traps.
0x00000278 ERROR_NOINTERFACE	The requested interface is not supported.
0x00000279 ERROR_DRIVER_FAILED_SLEEP	{System Standby Failed} The driver %hs does not support standby mode. Updating this driver may allow the system to go to standby mode.
0x0000027A ERROR_CORRUPT_SYSTEM_FILE	The system file %1 has become corrupt and has been replaced.
0x0000027B ERROR_COMMITMENT_MINIMUM	{Virtual Memory Minimum Too Low} Your system is low on virtual memory. Windows is increasing the size of your virtual memory paging file. During this process, memory requests for some applications may be denied. For more information, see Help.

Win32 error codes	Description
0x0000027C ERROR_PNP_RESTART_ENUMERATION	A device was removed so enumeration must be restarted.
0x0000027D ERROR_SYSTEM_IMAGE_BAD_SIGNATURE	{Fatal System Error} The system image %s is not properly signed. The file has been replaced with the signed file. The system has been shut down.
0x0000027E ERROR_PNP_REBOOT_REQUIRED	Device will not start without a reboot.
0x0000027F ERROR_INSUFFICIENT_POWER	There is not enough power to complete the requested operation.
0x00000280 ERROR_MULTIPLE_FAULT_VIOLATION	ERROR_MULTIPLE_FAULT_VIOLATION
0x00000281 ERROR_SYSTEM_SHUTDOWN	The system is in the process of shutting down.
0x00000282 ERROR_PORT_NOT_SET	An attempt to remove a process DebugPort was made, but a port was not already associated with the process.
0x00000283 ERROR_DS_VERSION_CHECK_FAILURE	This version of Windows is not compatible with the behavior version of directory forest, domain, or domain controller.
0x00000284 ERROR_RANGE_NOT_FOUND	The specified range could not be found in the range list.
0x00000286 ERROR_NOT_SAFE_MODE_DRIVER	The driver was not loaded because the system is booting into safe mode.
0x00000287 ERROR_FAILED_DRIVER_ENTRY	The driver was not loaded because it failed its initialization call.
0x00000288 ERROR_DEVICE_ENUMERATION_ERROR	The device encountered an error while applying power or reading the device configuration. This may be caused by a failure of your hardware or by a poor connection.
0x00000289 ERROR_MOUNT_POINT_NOT_RESOLVED	The create operation failed because the name contained at least one mount point that resolves to a volume to which the specified device object is not attached.
0x0000028A ERROR_INVALID_DEVICE_OBJECT_PARAMETER	The device object parameter is either not a valid device object or is not attached to the volume specified by the file name.
0x0000028B ERROR_MCA_OCCURED	A machine check error has occurred. Check the system event log for additional information.
0x0000028C ERROR_DRIVER_DATABASE_ERROR	There was an error [%2] processing the driver database.
0x0000028D	The system hive size has exceeded its limit.

Win32 error codes	Description
ERROR_SYSTEM_HIVE_TOO_LARGE	
0x0000028E ERROR_DRIVER_FAILED_PRIOR_UNLOAD	The driver could not be loaded because a previous version of the driver is still in memory.
0x0000028F ERROR_VOLSnap_PREPARE_HIBERNATE	{Volume Shadow Copy Service} Wait while the Volume Shadow Copy Service prepares volume %hs for hibernation.
0x00000290 ERROR_HIBERNATION_FAILURE	The system has failed to hibernate (the error code is %hs). Hibernation will be disabled until the system is restarted.
0x00000299 ERROR_FILE_SYSTEM_LIMITATION	The requested operation could not be completed due to a file system limitation.
0x0000029C ERROR_ASSERTION_FAILURE	An assertion failure has occurred.
0x0000029D ERROR_ACPI_ERROR	An error occurred in the Advanced Configuration and Power Interface (ACPI) subsystem.
0x0000029E ERROR_WOW_ASSERTION	WOW assertion error.
0x0000029F ERROR_PNP_BAD_MPS_TABLE	A device is missing in the system BIOS MultiProcessor Specification (MPS) table. This device will not be used. Contact your system vendor for system BIOS update.
0x000002A0 ERROR_PNP_TRANSLATION_FAILED	A translator failed to translate resources.
0x000002A1 ERROR_PNP_IRQ_TRANSLATION_FAILED	An interrupt request (IRQ) translator failed to translate resources.
0x000002A2 ERROR_PNP_INVALID_ID	Driver %2 returned invalid ID for a child device (%3).
0x000002A3 ERROR_WAKE_SYSTEM_DEBUGGER	{Kernel Debugger Awakened} the system debugger was awakened by an interrupt.
0x000002A4 ERROR_HANDLES_CLOSED	{Handles Closed} Handles to objects have been automatically closed because of the requested operation.
0x000002A5 ERROR_EXTRANEIOUS_INFORMATION	{Too Much Information} The specified ACL contained more information than was expected.
0x000002A6 ERROR_RXACT_COMMIT_NECESSARY	This warning level status indicates that the transaction state already exists for the registry subtree, but that a transaction commit was previously aborted. The commit has NOT been completed, but it has not been rolled back either (so it may still be committed if desired).



Win32 error codes	Description
0x000002A7 ERROR_MEDIA_CHECK	{Media Changed} The media may have changed.
0x000002A8 ERROR_GUID_SUBSTITUTION_MADE	{GUID Substitution} During the translation of a GUID to a Windows SID, no administratively defined GUID prefix was found. A substitute prefix was used, which will not compromise system security. However, this may provide more restrictive access than intended.
0x000002A9 ERROR_STOPPED_ON_SYMLINK	The create operation stopped after reaching a symbolic link.
0x000002AA ERROR_LONGJUMP	A long jump has been executed.
0x000002AB ERROR_PLUGPLAY_QUERY_VETOED	The Plug and Play query operation was not successful.
0x000002AC ERROR_UNWIND_CONSOLIDATE	A frame consolidation has been executed.
0x000002AD ERROR_REGISTRY_HIVE_RECOVERED	{Registry Hive Recovered} Registry hive (file): %hs was corrupted and it has been recovered. Some data might have been lost.
0x000002AE ERROR_DLL_MIGHT_BE_INSECURE	The application is attempting to run executable code from the module %hs. This may be insecure. An alternative, %hs, is available. Should the application use the secure module %hs?
0x000002AF ERROR_DLL_MIGHT_BE_INCOMPATIBLE	The application is loading executable code from the module %hs. This is secure, but may be incompatible with previous releases of the operating system. An alternative, %hs, is available. Should the application use the secure module %hs?
0x000002B0 ERROR_DBG_EXCEPTION_NOT_HANDLED	Debugger did not handle the exception.
0x000002B1 ERROR_DBG_REPLY_LATER	Debugger will reply later.
0x000002B2 ERROR_DBG_UNABLE_TO_PROVIDE_HANDLE	Debugger cannot provide handle.
0x000002B3 ERROR_DBG_TERMINATE_THREAD	Debugger terminated thread.
0x000002B4 ERROR_DBG_TERMINATE_PROCESS	Debugger terminated process.
0x000002B5 ERROR_DBG_CONTROL_C	Debugger got control C.
0x000002B6	Debugger printed exception on control C.

Win32 error codes	Description
ERROR_DBG_PRINTEXCEPTION_C	
0x000002B7 ERROR_DBG_RIPEXCEPTION	Debugger received Routing Information Protocol (RIP) exception.
0x000002B8 ERROR_DBG_CONTROL_BREAK	Debugger received control break.
0x000002B9 ERROR_DBG_COMMAND_EXCEPTION	Debugger command communication exception.
0x000002BA ERROR_OBJECT_NAME_EXISTS	{Object Exists} An attempt was made to create an object and the object name already existed.
0x000002BB ERROR_THREAD_WAS_SUSPENDED	{Thread Suspended} A thread termination occurred while the thread was suspended. The thread was resumed and termination proceeded.
0x000002BC ERROR_IMAGE_NOT_AT_BASE	{Image Relocated} An image file could not be mapped at the address specified in the image file. Local fixes must be performed on this image.
0x000002BD ERROR_RXACT_STATE_CREATED	This informational level status indicates that a specified registry subtree transaction state did not yet exist and had to be created.
0x000002BE ERROR_SEGMENT_NOTIFICATION	{Segment Load} A virtual DOS machine (VDM) is loading, unloading, or moving an MS-DOS or Win16 program segment image. An exception is raised so a debugger can load, unload, or track symbols and breakpoints within these 16-bit segments.
0x000002BF ERROR_BAD_CURRENT_DIRECTORY	{Invalid Current Directory} The process cannot switch to the startup current directory %hs. Select OK to set current directory to %hs, or select CANCEL to exit.
0x000002C0 ERROR_FT_READ_RECOVERY_FROM_BACKUP	{Redundant Read} To satisfy a read request, the NT fault-tolerant file system successfully read the requested data from a redundant copy. This was done because the file system encountered a failure on a member of the fault-tolerant volume, but it was unable to reassign the failing area of the device.
0x000002C1 ERROR_FT_WRITE_RECOVERY	{Redundant Write} To satisfy a write request, the Windows NT fault-tolerant file system successfully wrote a redundant copy of the information. This was done because the file system encountered a failure on a member of the fault-tolerant volume, but it was not able to reassign the failing area of the device.
0x000002C2 ERROR_IMAGE_MACHINE_TYPE_MISMATCH	{Machine Type Mismatch} The image file %hs is valid, but is for a machine type other than

Win32 error codes	Description
	the current machine. Select OK to continue, or CANCEL to fail the DLL load.
0x000002C3 ERROR_RECEIVE_PARTIAL	{Partial Data Received} The network transport returned partial data to its client. The remaining data will be sent later.
0x000002C4 ERROR_RECEIVE_EXPEDITED	{Expedited Data Received} The network transport returned data to its client that was marked as expedited by the remote system.
0x000002C5 ERROR_RECEIVE_PARTIAL_EXPEDITED	{Partial Expedited Data Received} The network transport returned partial data to its client and this data was marked as expedited by the remote system. The remaining data will be sent later.
0x000002C6 ERROR_EVENT_DONE	{TDI Event Done} The TDI indication has completed successfully.
0x000002C7 ERROR_EVENT_PENDING	{TDI Event Pending} The TDI indication has entered the pending state.
0x000002C8 ERROR_CHECKING_FILE_SYSTEM	Checking file system on %wZ.
0x000002C9 ERROR_FATAL_APP_EXIT	{Fatal Application Exit} %hs.
0x000002CA ERROR_PREDEFINED_HANDLE	The specified registry key is referenced by a predefined handle.
0x000002CB ERROR_WAS_UNLOCKED	{Page Unlocked} The page protection of a locked page was changed to 'No Access' and the page was unlocked from memory and from the process.
0x000002CC ERROR_SERVICE_NOTIFICATION	%hs
0x000002CD ERROR_WAS_LOCKED	{Page Locked} One of the pages to lock was already locked.
0x000002CE ERROR_LOG_HARD_ERROR	Application popup: %1 : %2
0x000002CF ERROR_ALREADY_WIN32	ERROR_ALREADY_WIN32
0x000002D0 ERROR_IMAGE_MACHINE_TYPE_MISMATCH_EXE	{Machine Type Mismatch} The image file %hs is valid, but is for a machine type other than the current machine.
0x000002D1 ERROR_NO_YIELD_PERFORMED	A yield execution was performed and no thread was available to run.
0x000002D2 ERROR_TIMER_RESUME_IGNORED	The resume flag to a timer API was ignored.

Win32 error codes	Description
0x000002D3 ERROR_ARBITRATION_UNHANDLED	The arbiter has deferred arbitration of these resources to its parent
0x000002D4 ERROR_CARDBUS_NOT_SUPPORTED	The inserted CardBus device cannot be started because of a configuration error on %hs".
0x000002D5 ERROR_MP_PROCESSOR_MISMATCH	The CPUs in this multiprocessor system are not all the same revision level. To use all processors the operating system restricts itself to the features of the least capable processor in the system. If problems occur with this system, contact the CPU manufacturer to see if this mix of processors is supported.
0x000002D6 ERROR_HIBERNATED	The system was put into hibernation.
0x000002D7 ERROR_RESUME_HIBERNATION	The system was resumed from hibernation.
0x000002D8 ERROR_FIRMWARE_UPDATED	Windows has detected that the system firmware (BIOS) was updated (previous firmware date = %2, current firmware date %3).
0x000002D9 ERROR_DRIVERS_LEAKING_LOCKED_PAGES	A device driver is leaking locked I/O pages, causing system degradation. The system has automatically enabled a tracking code to try and catch the culprit.
0x000002DA ERROR_WAKE_SYSTEM	The system has awoken.
0x000002DB ERROR_WAIT_1	ERROR_WAIT_1
0x000002DC ERROR_WAIT_2	ERROR_WAIT_2
0x000002DD ERROR_WAIT_3	ERROR_WAIT_3
0x000002DE ERROR_WAIT_63	ERROR_WAIT_63
0x000002DF ERROR_ABANDONED_WAIT_0	ERROR_ABANDONED_WAIT_0
0x000002E0 ERROR_ABANDONED_WAIT_63	ERROR_ABANDONED_WAIT_63
0x000002E1 ERROR_USER_APC	ERROR_USER_APC
0x000002E2 ERROR_KERNEL_APC	ERROR_KERNEL_APC
0x000002E3	ERROR_ALERTED

Win32 error codes	Description
ERROR_ALERTED	
0x000002E4 ERROR_ELEVATION_REQUIRED	The requested operation requires elevation.
0x000002E5 ERROR_REPARSE	A reparse should be performed by the object manager because the name of the file resulted in a symbolic link.
0x000002E6 ERROR_OPLOCK_BREAK_IN_PROGRESS	An open/create operation completed while an oplock break is underway.
0x000002E7 ERROR_VOLUME_MOUNTED	A new volume has been mounted by a file system.
0x000002E8 ERROR_RXACT_COMMITTED	This success level status indicates that the transaction state already exists for the registry subtree, but that a transaction commit was previously aborted. The commit has now been completed.
0x000002E9 ERROR_NOTIFY_CLEANUP	This indicates that a notify change request has been completed due to closing the handle which made the notify change request.
0x000002EA ERROR_PRIMARY_TRANSPORT_CONNECT_FAILED	{Connect Failure on Primary Transport} An attempt was made to connect to the remote server %hs on the primary transport, but the connection failed. The computer was able to connect on a secondary transport.
0x000002EB ERROR_PAGE_FAULT_TRANSITION	Page fault was a transition fault.
0x000002EC ERROR_PAGE_FAULT_DEMAND_ZERO	Page fault was a demand zero fault.
0x000002ED ERROR_PAGE_FAULT_COPY_ON_WRITE	Page fault was a demand zero fault.
0x000002EE ERROR_PAGE_FAULT_GUARD_PAGE	Page fault was a demand zero fault.
0x000002EF ERROR_PAGE_FAULT_PAGING_FILE	Page fault was satisfied by reading from a secondary storage device.
0x000002F0 ERROR_CACHE_PAGE_LOCKED	Cached page was locked during operation.
0x000002F1 ERROR_CRASH_DUMP	Crash dump exists in paging file.
0x000002F2 ERROR_BUFFER_ALL_ZEROS	Specified buffer contains all zeros.
0x000002F3 ERROR_REPARSE_OBJECT	A reparse should be performed by the object manager because the name of the file resulted in a symbolic link.

Win32 error codes	Description
0x000002F4 ERROR_RESOURCE_REQUIREMENTS_CHANGED	The device has succeeded a query-stop and its resource requirements have changed.
0x000002F5 ERROR_TRANSLATION_COMPLETE	The translator has translated these resources into the global space and no further translations should be performed.
0x000002F6 ERROR_NOTHING_TO_TERMINATE	A process being terminated has no threads to terminate.
0x000002F7 ERROR_PROCESS_NOT_IN_JOB	The specified process is not part of a job.
0x000002F8 ERROR_PROCESS_IN_JOB	The specified process is part of a job.
0x000002F9 ERROR_VOLSNAP_HIBERNATE_READY	{Volume Shadow Copy Service} The system is now ready for hibernation.
0x000002FA ERROR_FSFILTER_OP_COMPLETED_SUCCESSFULLY	A file system or file system filter driver has successfully completed an FsFilter operation.
0x000002FB ERROR_INTERRUPT_VECTOR_ALREADY_CONNECTED	The specified interrupt vector was already connected.
0x000002FC ERROR_INTERRUPT_STILL_CONNECTED	The specified interrupt vector is still connected.
0x000002FD ERROR_WAIT_FOR_OPLOCK	An operation is blocked waiting for an oplock.
0x000002FE ERROR_DBG_EXCEPTION_HANDLED	Debugger handled exception.
0x000002FF ERROR_DBG_CONTINUE	Debugger continued.
0x00000300 ERROR_CALLBACK_POP_STACK	An exception occurred in a user mode callback and the kernel callback frame should be removed.
0x00000301 ERROR_COMPRESSION_DISABLED	Compression is disabled for this volume.
0x00000302 ERROR_CANTFETCHBACKWARDS	The data provider cannot fetch backward through a result set.
0x00000303 ERROR_CANTSCROLLBACKWARDS	The data provider cannot scroll backward through a result set.
0x00000304 ERROR_ROWSNOTRELEASED	The data provider requires that previously fetched data is released before asking for more data.
0x00000305 ERROR_BAD_ACCESSOR_FLAGS	The data provider was not able to interpret the flags set for a column binding in an accessor.
0x00000306	One or more errors occurred while processing

Win32 error codes	Description
ERROR_ERRORS_ENCOUNTERED	the request.
0x00000307 ERROR_NOT_CAPABLE	The implementation is not capable of performing the request.
0x00000308 ERROR_REQUEST_OUT_OF_SEQUENCE	The client of a component requested an operation that is not valid given the state of the component instance.
0x00000309 ERROR_VERSION_PARSE_ERROR	A version number could not be parsed.
0x0000030A ERROR_BADSTARTPOSITION	The iterator's start position is invalid.
0x0000030B ERROR_MEMORY_HARDWARE	The hardware has reported an uncorrectable memory error.
0x0000030C ERROR_DISK_REPAIR_DISABLED	The attempted operation required self-healing to be enabled.
0x0000030D ERROR_INSUFFICIENT_RESOURCE_FOR_SPECIFIED_SHARED_SECTION_SIZE	The Desktop heap encountered an error while allocating session memory. There is more information in the system event log.
0x0000030E ERROR_SYSTEM_POWERSTATE_TRANSITION	The system power state is transitioning from %2 to %3.
0x0000030F ERROR_SYSTEM_POWERSTATE_COMPLEX_TRANSITION	The system power state is transitioning from %2 to %3 but could enter %4.
0x00000310 ERROR_MCA_EXCEPTION	A thread is getting dispatched with MCA EXCEPTION because of MCA.
0x00000311 ERROR_ACCESS_AUDIT_BY_POLICY	Access to %1 is monitored by policy rule %2.
0x00000312 ERROR_ACCESS_DISABLED_NO_SAFER_UI_BY_POLICY	Access to %1 has been restricted by your administrator by policy rule %2.
0x00000313 ERROR_ABANDON_HIBERFILE	A valid hibernation file has been invalidated and should be abandoned.
0x00000314 ERROR_LOST_WRITEBEHIND_DATA_NETWORK_DISCONNECTED	{Delayed Write Failed} Windows was unable to save all the data for the file %hs; the data has been lost. This error may be caused by network connectivity issues. Try to save this file elsewhere.
0x00000315 ERROR_LOST_WRITEBEHIND_DATA_NETWORK_SERVER_ERROR	{Delayed Write Failed} Windows was unable to save all the data for the file %hs; the data has been lost. This error was returned by the server on which the file exists. Try to save this file elsewhere.
0x00000316	{Delayed Write Failed} Windows was unable to

Win32 error codes	Description
ERROR_LOST_WRITEBEHIND_DATA_LOCAL_DISK_ERROR	save all the data for the file %hs; the data has been lost. This error may be caused if the device has been removed or the media is write-protected.
0x000003E2 ERROR_EA_ACCESS_DENIED	Access to the extended attribute was denied.
0x000003E3 ERROR_OPERATION_ABORTED	The I/O operation has been aborted because of either a thread exit or an application request.
0x000003E4 ERROR_IO_INCOMPLETE	Overlapped I/O event is not in a signaled state.
0x000003E5 ERROR_IO_PENDING	Overlapped I/O operation is in progress.
0x000003E6 ERROR_NOACCESS	Invalid access to memory location.
0x000003E7 ERROR_SWAPERROR	Error performing in-page operation.
0x000003E9 ERROR_STACK_OVERFLOW	Recursion too deep; the stack overflowed.
0x000003EA ERROR_INVALID_MESSAGE	The window cannot act on the sent message.
0x000003EB ERROR_CAN_NOT_COMPLETE	Cannot complete this function.
0x000003EC ERROR_INVALID_FLAGS	Invalid flags.
0x000003ED ERROR_UNRECOGNIZED_VOLUME	The volume does not contain a recognized file system. Be sure that all required file system drivers are loaded and that the volume is not corrupted.
0x000003EE ERROR_FILE_INVALID	The volume for a file has been externally altered so that the opened file is no longer valid.
0x000003EF ERROR_FULLSCREEN_MODE	The requested operation cannot be performed in full-screen mode.
0x000003F0 ERROR_NO_TOKEN	An attempt was made to reference a token that does not exist.
0x000003F1 ERROR_BADDB	The configuration registry database is corrupt.
0x000003F2 ERROR_BADKEY	The configuration registry key is invalid.
0x000003F3 ERROR_CANTOPEN	The configuration registry key could not be opened.



Win32 error codes	Description
0x000003F4 ERROR_CANTREAD	The configuration registry key could not be read.
0x000003F5 ERROR_CANTWRITE	The configuration registry key could not be written.
0x000003F6 ERROR_REGISTRY_RECOVERED	One of the files in the registry database had to be recovered by use of a log or alternate copy. The recovery was successful.
0x000003F7 ERROR_REGISTRY_CORRUPT	The registry is corrupted. The structure of one of the files containing registry data is corrupted, or the system's memory image of the file is corrupted, or the file could not be recovered because the alternate copy or log was absent or corrupted.
0x000003F8 ERROR_REGISTRY_IO_FAILED	An I/O operation initiated by the registry failed and cannot be recovered. The registry could not read in, write out, or flush one of the files that contain the system's image of the registry.
0x000003F9 ERROR_NOT_REGISTRY_FILE	The system attempted to load or restore a file into the registry, but the specified file is not in a registry file format.
0x000003FA ERROR_KEY_DELETED	Illegal operation attempted on a registry key that has been marked for deletion.
0x000003FB ERROR_NO_LOG_SPACE	System could not allocate the required space in a registry log.
0x000003FC ERROR_KEY_HAS_CHILDREN	Cannot create a symbolic link in a registry key that already has subkeys or values.
0x000003FD ERROR_CHILD_MUST_BE_VOLATILE	Cannot create a stable subkey under a volatile parent key.
0x000003FE ERROR_NOTIFY_ENUM_DIR	A notify change request is being completed and the information is not being returned in the caller's buffer. The caller now needs to enumerate the files to find the changes.
0x0000041B ERROR_DEPENDENT_SERVICES_RUNNING	A stop control has been sent to a service that other running services are dependent on.
0x0000041C ERROR_INVALID_SERVICE_CONTROL	The requested control is not valid for this service.
0x0000041D ERROR_SERVICE_REQUEST_TIMEOUT	The service did not respond to the start or control request in a timely fashion.
0x0000041E ERROR_SERVICE_NO_THREAD	A thread could not be created for the service.
0x0000041F ERROR_SERVICE_DATABASE_LOCKED	The service database is locked.

Win32 error codes	Description
0x00000420 ERROR_SERVICE_ALREADY_RUNNING	An instance of the service is already running.
0x00000421 ERROR_INVALID_SERVICE_ACCOUNT	The account name is invalid or does not exist, or the password is invalid for the account name specified.
0x00000422 ERROR_SERVICE_DISABLED	The service cannot be started, either because it is disabled or because it has no enabled devices associated with it.
0x00000423 ERROR_CIRCULAR_DEPENDENCY	Circular service dependency was specified.
0x00000424 ERROR_SERVICE_DOES_NOT_EXIST	The specified service does not exist as an installed service.
0x00000425 ERROR_SERVICE_CANNOT_ACCEPT_CTRL	The service cannot accept control messages at this time.
0x00000426 ERROR_SERVICE_NOT_ACTIVE	The service has not been started.
0x00000427 ERROR_FAILED_SERVICE_CONTROLLER_CONNECT	The service process could not connect to the service controller.
0x00000428 ERROR_EXCEPTION_IN_SERVICE	An exception occurred in the service when handling the control request.
0x00000429 ERROR_DATABASE_DOES_NOT_EXIST	The database specified does not exist.
0x0000042A ERROR_SERVICE_SPECIFIC_ERROR	The service has returned a service-specific error code.
0x0000042B ERROR_PROCESS_ABORTED	The process terminated unexpectedly.
0x0000042C ERROR_SERVICE_DEPENDENCY_FAIL	The dependency service or group failed to start.
0x0000042D ERROR_SERVICE_LOGON_FAILED	The service did not start due to a logon failure.
0x0000042E ERROR_SERVICE_START_HANG	After starting, the service hung in a start-pending state.
0x0000042F ERROR_INVALID_SERVICE_LOCK	The specified service database lock is invalid.
0x00000430 ERROR_SERVICE_MARKED_FOR_DELETE	The specified service has been marked for deletion.
0x00000431 ERROR_SERVICE_EXISTS	The specified service already exists.
0x00000432 ERROR_ALREADY_RUNNING_LKG	The system is currently running with the last-known-good configuration.

Win32 error codes	Description
0x00000433 ERROR_SERVICE_DEPENDENCY_DELETED	The dependency service does not exist or has been marked for deletion.
0x00000434 ERROR_BOOT_ALREADY_ACCEPTED	The current boot has already been accepted for use as the last-known-good control set.
0x00000435 ERROR_SERVICE_NEVER_STARTED	No attempts to start the service have been made since the last boot.
0x00000436 ERROR_DUPLICATE_SERVICE_NAME	The name is already in use as either a service name or a service display name.
0x00000437 ERROR_DIFFERENT_SERVICE_ACCOUNT	The account specified for this service is different from the account specified for other services running in the same process.
0x00000438 ERROR_CANNOT_DETECT_DRIVER_FAILURE	Failure actions can only be set for Win32 services, not for drivers.
0x00000439 ERROR_CANNOT_DETECT_PROCESS_ABORT	This service runs in the same process as the service control manager. Therefore, the service control manager cannot take action if this service's process terminates unexpectedly.
0x0000043A ERROR_NO_RECOVERY_PROGRAM	No recovery program has been configured for this service.
0x0000043B ERROR_SERVICE_NOT_IN_EXE	The executable program that this service is configured to run in does not implement the service.
0x0000043C ERROR_NOT_SAFEBOOT_SERVICE	This service cannot be started in Safe Mode.
0x0000044C ERROR_END_OF_MEDIA	The physical end of the tape has been reached.
0x0000044D ERROR_FILEMARK_DETECTED	A tape access reached a filemark.
0x0000044E ERROR_BEGINNING_OF_MEDIA	The beginning of the tape or a partition was encountered.
0x0000044F ERROR_SETMARK_DETECTED	A tape access reached the end of a set of files.
0x00000450 ERROR_NO_DATA_DETECTED	No more data is on the tape.
0x00000451 ERROR_PARTITION_FAILURE	Tape could not be partitioned.
0x00000452 ERROR_INVALID_BLOCK_LENGTH	When accessing a new tape of a multivolume partition, the current block size is incorrect.
0x00000453 ERROR_DEVICE_NOT_PARTITIONED	Tape partition information could not be found when loading a tape.

Win32 error codes	Description
0x00000454 ERROR_UNABLE_TO_LOCK_MEDIA	Unable to lock the media eject mechanism.
0x00000455 ERROR_UNABLE_TO_UNLOAD_MEDIA	Unable to unload the media.
0x00000456 ERROR_MEDIA_CHANGED	The media in the drive may have changed.
0x00000457 ERROR_BUS_RESET	The I/O bus was reset.
0x00000458 ERROR_NO_MEDIA_IN_DRIVE	No media in drive.
0x00000459 ERROR_NO_UNICODE_TRANSLATION	No mapping for the Unicode character exists in the target multibyte code page.
0x0000045A ERROR_DLL_INIT_FAILED	A DLL initialization routine failed.
0x0000045B ERROR_SHUTDOWN_IN_PROGRESS	A system shutdown is in progress.
0x0000045C ERROR_NO_SHUTDOWN_IN_PROGRESS	Unable to abort the system shutdown because no shutdown was in progress.
0x0000045D ERROR_IO_DEVICE	The request could not be performed because of an I/O device error.
0x0000045E ERROR_SERIAL_NO_DEVICE	No serial device was successfully initialized. The serial driver will unload.
0x0000045F ERROR_IRQ_BUSY	Unable to open a device that was sharing an IRQ with other devices. At least one other device that uses that IRQ was already opened.
0x00000460 ERROR_MORE_WRITES	A serial I/O operation was completed by another write to the serial port. (The IOCTL_SERIAL_XOFF_COUNTER reached zero.)
0x00000461 ERROR_COUNTER_TIMEOUT	A serial I/O operation completed because the time-out period expired. (The IOCTL_SERIAL_XOFF_COUNTER did not reach zero.)
0x00000462 ERROR_FLOPPY_ID_MARK_NOT_FOUND	No ID address mark was found on the floppy disk.
0x00000463 ERROR_FLOPPY_WRONG_CYLINDER	Mismatch between the floppy disk sector ID field and the floppy disk controller track address.
0x00000464 ERROR_FLOPPY_UNKNOWN_ERROR	The floppy disk controller reported an error that is not recognized by the floppy disk driver.
0x00000465 ERROR_FLOPPY_BAD_REGISTERS	The floppy disk controller returned inconsistent results in its registers.

Win32 error codes	Description
0x00000466 ERROR_DISK_RECALIBRATE_FAILED	While accessing the hard disk, a recalibrate operation failed, even after retries.
0x00000467 ERROR_DISK_OPERATION_FAILED	While accessing the hard disk, a disk operation failed even after retries.
0x00000468 ERROR_DISK_RESET_FAILED	While accessing the hard disk, a disk controller reset was needed, but that also failed.
0x00000469 ERROR_EOM_OVERFLOW	Physical end of tape encountered.
0x0000046A ERROR_NOT_ENOUGH_SERVER_MEMORY	Not enough server storage is available to process this command.
0x0000046B ERROR_POSSIBLE_DEADLOCK	A potential deadlock condition has been detected.
0x0000046C ERROR_MAPPED_ALIGNMENT	The base address or the file offset specified does not have the proper alignment.
0x00000474 ERROR_SET_POWER_STATE_VETOED	An attempt to change the system power state was vetoed by another application or driver.
0x00000475 ERROR_SET_POWER_STATE_FAILED	The system BIOS failed an attempt to change the system power state.
0x00000476 ERROR_TOO_MANY_LINKS	An attempt was made to create more links on a file than the file system supports.
0x0000047E ERROR_OLD_WIN_VERSION	The specified program requires a newer version of Windows.
0x0000047F ERROR_APP_WRONG_OS	The specified program is not a Windows or MS-DOS program.
0x00000480 ERROR_SINGLE_INSTANCE_APP	Cannot start more than one instance of the specified program.
0x00000481 ERROR_RMODE_APP	The specified program was written for an earlier version of Windows.
0x00000482 ERROR_INVALID_DLL	One of the library files needed to run this application is damaged.
0x00000483 ERROR_NO_ASSOCIATION	No application is associated with the specified file for this operation.
0x00000484 ERROR_DDE_FAIL	An error occurred in sending the command to the application.
0x00000485 ERROR_DLL_NOT_FOUND	One of the library files needed to run this application cannot be found.
0x00000486 ERROR_NO_MORE_USER_HANDLES	The current process has used all of its system allowance of handles for Windows manager objects.

Win32 error codes	Description
0x00000487 ERROR_MESSAGE_SYNC_ONLY	The message can be used only with synchronous operations.
0x00000488 ERROR_SOURCE_ELEMENT_EMPTY	The indicated source element has no media.
0x00000489 ERROR_DESTINATION_ELEMENT_FULL	The indicated destination element already contains media.
0x0000048A ERROR_ILLEGAL_ELEMENT_ADDRESS	The indicated element does not exist.
0x0000048B ERROR_MAGAZINE_NOT_PRESENT	The indicated element is part of a magazine that is not present.
0x0000048C ERROR_DEVICE_REINITIALIZATION_NEEDED	The indicated device requires re-initialization due to hardware errors.
0x0000048D ERROR_DEVICE_REQUIRES_CLEANING	The device has indicated that cleaning is required before further operations are attempted.
0x0000048E ERROR_DEVICE_DOOR_OPEN	The device has indicated that its door is open.
0x0000048F ERROR_DEVICE_NOT_CONNECTED	The device is not connected.
0x00000490 ERROR_NOT_FOUND	Element not found.
0x00000491 ERROR_NO_MATCH	There was no match for the specified key in the index.
0x00000492 ERROR_SET_NOT_FOUND	The property set specified does not exist on the object.
0x00000493 ERROR_POINT_NOT_FOUND	The point passed to GetMouseMovePoints is not in the buffer.
0x00000494 ERROR_NO_TRACKING_SERVICE	The tracking (workstation) service is not running.
0x00000495 ERROR_NO_VOLUME_ID	The volume ID could not be found.
0x00000497 ERROR_UNABLE_TO_REMOVE_REPLACED	Unable to remove the file to be replaced.
0x00000498 ERROR_UNABLE_TO_MOVE_REPLACEMENT	Unable to move the replacement file to the file to be replaced. The file to be replaced has retained its original name.
0x00000499 ERROR_UNABLE_TO_MOVE_REPLACEMENT_2	Unable to move the replacement file to the file to be replaced. The file to be replaced has been renamed using the backup name.
0x0000049A	The volume change journal is being deleted.

Win32 error codes	Description
ERROR_JOURNAL_DELETE_IN_PROGRESS	
0x0000049B ERROR_JOURNAL_NOT_ACTIVE	The volume change journal is not active.
0x0000049C ERROR_POTENTIAL_FILE_FOUND	A file was found, but it may not be the correct file.
0x0000049D ERROR_JOURNAL_ENTRY_DELETED	The journal entry has been deleted from the journal.
0x000004A6 ERROR_SHUTDOWN_IS_SCHEDULED	A system shutdown has already been scheduled.
0x000004A7 ERROR_SHUTDOWN_USERS_LOGGED_ON	The system shutdown cannot be initiated because there are other users logged on to the computer.
0x000004B0 ERROR_BAD_DEVICE	The specified device name is invalid.
0x000004B1 ERROR_CONNECTION_UNAVAIL	The device is not currently connected but it is a remembered connection.
0x000004B2 ERROR_DEVICE_ALREADY_REMEMBERED	The local device name has a remembered connection to another network resource.
0x000004B3 ERROR_NO_NET_OR_BAD_PATH	The network path was either typed incorrectly, does not exist, or the network provider is not currently available. Try retyping the path or contact your network administrator.
0x000004B4 ERROR_BAD_PROVIDER	The specified network provider name is invalid.
0x000004B5 ERROR_CANNOT_OPEN_PROFILE	Unable to open the network connection profile.
0x000004B6 ERROR_BAD_PROFILE	The network connection profile is corrupted.
0x000004B7 ERROR_NOT_CONTAINER	Cannot enumerate a noncontainer.
0x000004B8 ERROR_EXTENDED_ERROR	An extended error has occurred.
0x000004B9 ERROR_INVALID_GROUPNAME	The format of the specified group name is invalid.
0x000004BA ERROR_INVALID_COMPUTERNAME	The format of the specified computer name is invalid.
0x000004BB ERROR_INVALID_EVENTNAME	The format of the specified event name is invalid.
0x000004BC ERROR_INVALID_DOMAINNAME	The format of the specified domain name is invalid.

Win32 error codes	Description
0x000004BD ERROR_INVALID_SERVICENAME	The format of the specified service name is invalid.
0x000004BE ERROR_INVALID_NETNAME	The format of the specified network name is invalid.
0x000004BF ERROR_INVALID_SHARENAME	The format of the specified share name is invalid.
0x000004C0 ERROR_INVALID_PASSWORDNAME	The format of the specified password is invalid.
0x000004C1 ERROR_INVALID_MESSAGE_NAME	The format of the specified message name is invalid.
0x000004C2 ERROR_INVALID_MESSAGEDEST	The format of the specified message destination is invalid.
0x000004C3 ERROR_SESSION_CREDENTIAL_CONFLICT	Multiple connections to a server or shared resource by the same user, using more than one user name, are not allowed. Disconnect all previous connections to the server or shared resource and try again.
0x000004C4 ERROR_REMOTE_SESSION_LIMIT_EXCEEDED	An attempt was made to establish a session to a network server, but there are already too many sessions established to that server.
0x000004C5 ERROR_DUP_DOMAINNAME	The workgroup or domain name is already in use by another computer on the network.
0x000004C6 ERROR_NO_NETWORK	The network is not present or not started.
0x000004C7 ERROR_CANCELLED	The operation was canceled by the user.
0x000004C8 ERROR_USER_MAPPED_FILE	The requested operation cannot be performed on a file with a user-mapped section open.
0x000004C9 ERROR_CONNECTION_REFUSED	The remote system refused the network connection.
0x000004CA ERROR_GRACEFUL_DISCONNECT	The network connection was gracefully closed.
0x000004CB ERROR_ADDRESS_ALREADY_ASSOCIATED	The network transport endpoint already has an address associated with it.
0x000004CC ERROR_ADDRESS_NOT_ASSOCIATED	An address has not yet been associated with the network endpoint.
0x000004CD ERROR_CONNECTION_INVALID	An operation was attempted on a nonexistent network connection.
0x000004CE ERROR_CONNECTION_ACTIVE	An invalid operation was attempted on an active network connection.



Win32 error codes	Description
0x000004CF ERROR_NETWORK_UNREACHABLE	The network location cannot be reached. For information about network troubleshooting, see Windows Help.
0x000004D0 ERROR_HOST_UNREACHABLE	The network location cannot be reached. For information about network troubleshooting, see Windows Help.
0x000004D1 ERROR_PROTOCOL_UNREACHABLE	The network location cannot be reached. For information about network troubleshooting, see Windows Help.
0x000004D2 ERROR_PORT_UNREACHABLE	No service is operating at the destination network endpoint on the remote system.
0x000004D3 ERROR_REQUEST_ABORTED	The request was aborted.
0x000004D4 ERROR_CONNECTION_ABORTED	The network connection was aborted by the local system.
0x000004D5 ERROR_RETRY	The operation could not be completed. A retry should be performed.
0x000004D6 ERROR_CONNECTION_COUNT_LIMIT	A connection to the server could not be made because the limit on the number of concurrent connections for this account has been reached.
0x000004D7 ERROR_LOGIN_TIME_RESTRICTION	Attempting to log on during an unauthorized time of day for this account.
0x000004D8 ERROR_LOGIN_WKSTA_RESTRICTION	The account is not authorized to log on from this station.
0x000004D9 ERROR_INCORRECT_ADDRESS	The network address could not be used for the operation requested.
0x000004DA ERROR_ALREADY_REGISTERED	The service is already registered.
0x000004DB ERROR_SERVICE_NOT_FOUND	The specified service does not exist.
0x000004DC ERROR_NOT_AUTHENTICATED	The operation being requested was not performed because the user has not been authenticated.
0x000004DD ERROR_NOT_LOGGED_ON	The operation being requested was not performed because the user has not logged on to the network. The specified service does not exist.
0x000004DE ERROR_CONTINUE	Continue with work in progress.
0x000004DF ERROR_ALREADY_INITIALIZED	An attempt was made to perform an initialization operation when initialization has already been completed.

Win32 error codes	Description
0x000004E0 ERROR_NO_MORE_DEVICES	No more local devices.
0x000004E1 ERROR_NO_SUCH_SITE	The specified site does not exist.
0x000004E2 ERROR_DOMAIN_CONTROLLER_EXISTS	A domain controller with the specified name already exists.
0x000004E3 ERROR_ONLY_IF_CONNECTED	This operation is supported only when you are connected to the server.
0x000004E4 ERROR_OVERRIDE_NOCHANGES	The group policy framework should call the extension even if there are no changes.
0x000004E5 ERROR_BAD_USER_PROFILE	The specified user does not have a valid profile.
0x000004E6 ERROR_NOT_SUPPORTED_ON_SBS	This operation is not supported on a computer running Windows Server 2003 for Small Business Server.
0x000004E7 ERROR_SERVER_SHUTDOWN_IN_PROGRESS	The server machine is shutting down.
0x000004E8 ERROR_HOST_DOWN	The remote system is not available. For information about network troubleshooting, see Windows Help.
0x000004E9 ERROR_NON_ACCOUNT_SID	The security identifier provided is not from an account domain.
0x000004EA ERROR_NON_DOMAIN_SID	The security identifier provided does not have a domain component.
0x000004EB ERROR_APPHELP_BLOCK	AppHelp dialog canceled, thus preventing the application from starting.
0x000004EC ERROR_ACCESS_DISABLED_BY_POLICY	This program is blocked by Group Policy. For more information, contact your system administrator.
0x000004ED ERROR_REG_NAT_CONSUMPTION	A program attempt to use an invalid register value. Normally caused by an uninitialized register. This error is Itanium specific.
0x000004EE ERROR_CSCSHARE_OFFLINE	The share is currently offline or does not exist.
0x000004EF ERROR_PKINIT_FAILURE	The Kerberos protocol encountered an error while validating the KDC certificate during smartcard logon. There is more information in the system event log.
0x000004F0 ERROR_SMARTCARD_SUBSYSTEM_FAILURE	The Kerberos protocol encountered an error while attempting to utilize the smartcard subsystem.

Win32 error codes	Description
0x000004F1 ERROR_DOWNGRADE_DETECTED	The system detected a possible attempt to compromise security. Ensure that you can contact the server that authenticated you.
0x000004F7 ERROR_MACHINE_LOCKED	The machine is locked and cannot be shut down without the force option.
0x000004F9 ERROR_CALLBACK_SUPPLIED_INVALID_DATA	An application-defined callback gave invalid data when called.
0x000004FA ERROR_SYNC_FOREGROUND_REFRESH_REQUIRED	The Group Policy framework should call the extension in the synchronous foreground policy refresh.
0x000004FB ERROR_DRIVER_BLOCKED	This driver has been blocked from loading.
0x000004FC ERROR_INVALID_IMPORT_OF_NON_DLL	A DLL referenced a module that was neither a DLL nor the process's executable image.
0x000004FD ERROR_ACCESS_DISABLED_WEBBLADE	Windows cannot open this program because it has been disabled.
0x000004FE ERROR_ACCESS_DISABLED_WEBBLADE_TAMPER	Windows cannot open this program because the license enforcement system has been tampered with or become corrupted.
0x000004FF ERROR_RECOVERY_FAILURE	A transaction recover failed.
0x00000500 ERROR_ALREADY_FIBER	The current thread has already been converted to a fiber.
0x00000501 ERROR_ALREADY_THREAD	The current thread has already been converted from a fiber.
0x00000502 ERROR_STACK_BUFFER_OVERRUN	The system detected an overrun of a stack-based buffer in this application. This overrun could potentially allow a malicious user to gain control of this application.
0x00000503 ERROR_PARAMETER_QUOTA_EXCEEDED	Data present in one of the parameters is more than the function can operate on.
0x00000504 ERROR_DEBUGGER_INACTIVE	An attempt to perform an operation on a debug object failed because the object is in the process of being deleted.
0x00000505 ERROR_DELAY_LOAD_FAILED	An attempt to delay-load a .dll or get a function address in a delay-loaded .dll failed.
0x00000506 ERROR_VDM_DISALLOWED	%1 is a 16-bit application. You do not have permissions to execute 16-bit applications. Check your permissions with your system administrator.
0x00000507 ERROR_UNIDENTIFIED_ERROR	Insufficient information exists to identify the cause of failure.

Win32 error codes	Description
0x00000508 ERROR_INVALID_CRUNTIME_PARAMETER	The parameter passed to a <b>C</b> runtime function is incorrect.
0x00000509 ERROR_BEYOND_VDL	The operation occurred beyond the valid data length of the file.
0x0000050A ERROR_INCOMPATIBLE_SERVICE_SID_TYPE	The service start failed because one or more services in the same process have an incompatible service SID type setting. A service with a restricted service SID type can only coexist in the same process with other services with a restricted SID type.
0x0000050B ERROR_DRIVER_PROCESS_TERMINATED	The process hosting the driver for this device has been terminated.
0x0000050C ERROR_IMPLEMENTATION_LIMIT	An operation attempted to exceed an implementation-defined limit.
0x0000050D ERROR_PROCESS_IS_PROTECTED	Either the target process, or the target thread's containing process, is a protected process.
0x0000050E ERROR_SERVICE_NOTIFY_CLIENT_LAGGING	The service notification client is lagging too far behind the current state of services in the machine.
0x0000050F ERROR_DISK_QUOTA_EXCEEDED	An operation failed because the storage quota was exceeded.
0x00000510 ERROR_CONTENT_BLOCKED	An operation failed because the content was blocked.
0x00000511 ERROR_INCOMPATIBLE_SERVICE_PRIVILEGE	A privilege that the service requires to function properly does not exist in the service account configuration. You may use the Services Microsoft Management Console (MMC) snap-in (Services.msc) and the Local Security Settings MMC snap-in (Secpol.msc) to view the service configuration and the account configuration.
0x00000513 ERROR_INVALID_LABEL	Indicates a particular SID may not be assigned as the label of an object.
0x00000514 ERROR_NOT_ALL_ASSIGNED	Not all privileges or groups referenced are assigned to the caller.
0x00000515 ERROR_SOME_NOT_MAPPED	Some mapping between account names and SIDs was not done.
0x00000516 ERROR_NO_QUOTAS_FOR_ACCOUNT	No system quota limits are specifically set for this account.
0x00000517 ERROR_LOCAL_USER_SESSION_KEY	No encryption key is available. A well-known encryption key was returned.
0x00000518 ERROR_NULL_LM_PASSWORD	The password is too complex to be converted to a LAN Manager password. The LAN Manager password returned is a null string.

Win32 error codes	Description
0x00000519 ERROR_UNKNOWN_REVISION	The revision level is unknown.
0x0000051A ERROR_REVISION_MISMATCH	Indicates two revision levels are incompatible.
0x0000051B ERROR_INVALID_OWNER	This SID may not be assigned as the owner of this object.
0x0000051C ERROR_INVALID_PRIMARY_GROUP	This SID may not be assigned as the primary group of an object.
0x0000051D ERROR_NO_IMPERSONATION_TOKEN	An attempt has been made to operate on an impersonation token by a thread that is not currently impersonating a client.
0x0000051E ERROR_CANT_DISABLE_MANDATORY	The group may not be disabled.
0x0000051F ERROR_NO_LOGON_SERVERS	There are currently no logon servers available to service the logon request.
0x00000520 ERROR_NO_SUCH_LOGON_SESSION	A specified logon session does not exist. It may already have been terminated.
0x00000521 ERROR_NO_SUCH_PRIVILEGE	A specified privilege does not exist.
0x00000522 ERROR_PRIVILEGE_NOT_HELD	A required privilege is not held by the client.
0x00000523 ERROR_INVALID_ACCOUNT_NAME	The name provided is not a properly formed account name.
0x00000524 ERROR_USER_EXISTS	The specified account already exists.
0x00000525 ERROR_NO_SUCH_USER	The specified account does not exist.
0x00000526 ERROR_GROUP_EXISTS	The specified group already exists.
0x00000527 ERROR_NO_SUCH_GROUP	The specified group does not exist.
0x00000528 ERROR_MEMBER_IN_GROUP	Either the specified user account is already a member of the specified group, or the specified group cannot be deleted because it contains a member.
0x00000529 ERROR_MEMBER_NOT_IN_GROUP	The specified user account is not a member of the specified group account.
0x0000052A ERROR_LAST_ADMIN	The last remaining administration account cannot be disabled or deleted.
0x0000052B	Unable to update the password. The value

Win32 error codes	Description
ERROR_WRONG_PASSWORD	provided as the current password is incorrect.
0x0000052C ERROR_ILL_FORMED_PASSWORD	Unable to update the password. The value provided for the new password contains values that are not allowed in passwords.
0x0000052D ERROR_PASSWORD_RESTRICTION	Unable to update the password. The value provided for the new password does not meet the length, complexity, or history requirements of the domain.
0x0000052E ERROR_LOGON_FAILURE	Logon failure: Unknown user name or bad password.
0x0000052F ERROR_ACCOUNT_RESTRICTION	Logon failure: User account restriction. Possible reasons are blank passwords not allowed, logon hour restrictions, or a policy restriction has been enforced.
0x00000530 ERROR_INVALID_LOGON_HOURS	Logon failure: Account logon time restriction violation.
0x00000531 ERROR_INVALID_WORKSTATION	Logon failure: User not allowed to log on to this computer.
0x00000532 ERROR_PASSWORD_EXPIRED	Logon failure: The specified account password has expired.
0x00000533 ERROR_ACCOUNT_DISABLED	Logon failure: Account currently disabled.
0x00000534 ERROR_NONE_MAPPED	No mapping between account names and SIDs was done.
0x00000535 ERROR_TOO_MANY_LUIDS_REQUESTED	Too many local user identifiers (LUIDs) were requested at one time.
0x00000536 ERROR_LUIDS_EXHAUSTED	No more LUIDs are available.
0x00000537 ERROR_INVALID_SUB_AUTHORITY	The sub-authority part of an SID is invalid for this particular use.
0x00000538 ERROR_INVALID_ACL	The ACL structure is invalid.
0x00000539 ERROR_INVALID_SID	The SID structure is invalid.
0x0000053A ERROR_INVALID_SECURITY_DESCR	The security descriptor structure is invalid.
0x0000053C ERROR_BAD_INHERITANCE_ACL	The inherited ACL or ACE could not be built.
0x0000053D ERROR_SERVER_DISABLED	The server is currently disabled.

Win32 error codes	Description
0x0000053E ERROR_SERVER_NOT_DISABLED	The server is currently enabled.
0x0000053F ERROR_INVALID_ID_AUTHORITY	The value provided was an invalid value for an identifier authority.
0x00000540 ERROR_ALLOTTED_SPACE_EXCEEDED	No more memory is available for security information updates.
0x00000541 ERROR_INVALID_GROUP_ATTRIBUTES	The specified attributes are invalid, or incompatible with the attributes for the group as a whole.
0x00000542 ERROR_BAD_IMPERSONATION_LEVEL	Either a required impersonation level was not provided, or the provided impersonation level is invalid.
0x00000543 ERROR_CANT_OPEN_ANONYMOUS	Cannot open an anonymous level security token.
0x00000544 ERROR_BAD_VALIDATION_CLASS	The validation information class requested was invalid.
0x00000545 ERROR_BAD_TOKEN_TYPE	The type of the token is inappropriate for its attempted use.
0x00000546 ERROR_NO_SECURITY_ON_OBJECT	Unable to perform a security operation on an object that has no associated security.
0x00000547 ERROR_CANT_ACCESS_DOMAIN_INFO	Configuration information could not be read from the domain controller, either because the machine is unavailable, or access has been denied.
0x00000548 ERROR_INVALID_SERVER_STATE	The SAM or local security authority (LSA) server was in the wrong state to perform the security operation.
0x00000549 ERROR_INVALID_DOMAIN_STATE	The domain was in the wrong state to perform the security operation.
0x0000054A ERROR_INVALID_DOMAIN_ROLE	This operation is only allowed for the PDC of the domain.
0x0000054B ERROR_NO_SUCH_DOMAIN	The specified domain either does not exist or could not be contacted.
0x0000054C ERROR_DOMAIN_EXISTS	The specified domain already exists.
0x0000054D ERROR_DOMAIN_LIMIT_EXCEEDED	An attempt was made to exceed the limit on the number of domains per server.
0x0000054E ERROR_INTERNAL_DB_CORRUPTION	Unable to complete the requested operation because of either a catastrophic media failure or a data structure corruption on the disk.
0x0000054F	An internal error occurred.

Win32 error codes	Description
ERROR_INTERNAL_ERROR	
0x00000550 ERROR_GENERIC_NOT_MAPPED	Generic access types were contained in an access mask that should already be mapped to nongeneric types.
0x00000551 ERROR_BAD_DESCRIPTOR_FORMAT	A security descriptor is not in the right format (absolute or self-relative).
0x00000552 ERROR_NOT_LOGON_PROCESS	The requested action is restricted for use by logon processes only. The calling process has not registered as a logon process.
0x00000553 ERROR_LOGON_SESSION_EXISTS	Cannot start a new logon session with an ID that is already in use.
0x00000554 ERROR_NO_SUCH_PACKAGE	A specified authentication package is unknown.
0x00000555 ERROR_BAD_LOGON_SESSION_STATE	The logon session is not in a state that is consistent with the requested operation.
0x00000556 ERROR_LOGON_SESSION_COLLISION	The logon session ID is already in use.
0x00000557 ERROR_INVALID_LOGON_TYPE	A logon request contained an invalid logon type value.
0x00000558 ERROR_CANNOT_IMPERSONATE	Unable to impersonate using a named pipe until data has been read from that pipe.
0x00000559 ERROR_RXACT_INVALID_STATE	The transaction state of a registry subtree is incompatible with the requested operation.
0x0000055A ERROR_RXACT_COMMIT_FAILURE	An internal security database corruption has been encountered.
0x0000055B ERROR_SPECIAL_ACCOUNT	Cannot perform this operation on built-in accounts.
0x0000055C ERROR_SPECIAL_GROUP	Cannot perform this operation on this built-in special group.
0x0000055D ERROR_SPECIAL_USER	Cannot perform this operation on this built-in special user.
0x0000055E ERROR_MEMBERS_PRIMARY_GROUP	The user cannot be removed from a group because the group is currently the user's primary group.
0x0000055F ERROR_TOKEN_ALREADY_IN_USE	The token is already in use as a primary token.
0x00000560 ERROR_NO_SUCH_ALIAS	The specified local group does not exist.
0x00000561 ERROR_MEMBER_NOT_IN_ALIAS	The specified account name is not a member of the group.



Win32 error codes	Description
0x00000562 ERROR_MEMBER_IN_ALIAS	The specified account name is already a member of the group.
0x00000563 ERROR_ALIAS_EXISTS	The specified local group already exists.
0x00000564 ERROR_LOGON_NOT_GRANTED	Logon failure: The user has not been granted the requested logon type at this computer.
0x00000565 ERROR_TOO_MANY_SECRETS	The maximum number of secrets that may be stored in a single system has been exceeded.
0x00000566 ERROR_SECRET_TOO_LONG	The length of a secret exceeds the maximum length allowed.
0x00000567 ERROR_INTERNAL_DB_ERROR	The local security authority database contains an internal inconsistency.
0x00000568 ERROR_TOO_MANY_CONTEXT_IDS	During a logon attempt, the user's security context accumulated too many SIDs.
0x00000569 ERROR_LOGON_TYPE_NOT_GRANTED	Logon failure: The user has not been granted the requested logon type at this computer.
0x0000056A ERROR_NT_CROSS_ENCRYPTION_REQUIRED	A cross-encrypted password is necessary to change a user password.
0x0000056B ERROR_NO_SUCH_MEMBER	A member could not be added to or removed from the local group because the member does not exist.
0x0000056C ERROR_INVALID_MEMBER	A new member could not be added to a local group because the member has the wrong account type.
0x0000056D ERROR_TOO_MANY_SIDS	Too many SIDs have been specified.
0x0000056E ERROR_LM_CROSS_ENCRYPTION_REQUIRED	A cross-encrypted password is necessary to change this user password.
0x0000056F ERROR_NO_INHERITANCE	Indicates an ACL contains no inheritable components.
0x00000570 ERROR_FILE_CORRUPT	The file or directory is corrupted and unreadable.
0x00000571 ERROR_DISK_CORRUPT	The disk structure is corrupted and unreadable.
0x00000572 ERROR_NO_USER_SESSION_KEY	There is no user session key for the specified logon session.
0x00000573 ERROR_LICENSE_QUOTA_EXCEEDED	The service being accessed is licensed for a particular number of connections. No more connections can be made to the service at this time because the service has accepted the maximum number of connections.

Win32 error codes	Description
0x00000574 ERROR_WRONG_TARGET_NAME	Logon failure: The target account name is incorrect.
0x00000575 ERROR_MUTUAL_AUTH_FAILED	Mutual authentication failed. The server's password is out of date at the domain controller.
0x00000576 ERROR_TIME_SKEW	There is a time and/or date difference between the client and server.
0x00000577 ERROR_CURRENT_DOMAIN_NOT_ALLOWED	This operation cannot be performed on the current domain.
0x00000578 ERROR_INVALID_WINDOW_HANDLE	Invalid window handle.
0x00000579 ERROR_INVALID_MENU_HANDLE	Invalid menu handle.
0x0000057A ERROR_INVALID_CURSOR_HANDLE	Invalid cursor handle.
0x0000057B ERROR_INVALID_ACCEL_HANDLE	Invalid accelerator table handle.
0x0000057C ERROR_INVALID_HOOK_HANDLE	Invalid hook handle.
0x0000057D ERROR_INVALID_DWP_HANDLE	Invalid handle to a multiple-window position structure.
0x0000057E ERROR_TLW_WITH_WSCHILD	Cannot create a top-level child window.
0x0000057F ERROR_CANNOT_FIND_WND_CLASS	Cannot find window class.
0x00000580 ERROR_WINDOW_OF_OTHER_THREAD	Invalid window; it belongs to other thread.
0x00000581 ERROR_HOTKEY_ALREADY_REGISTERED	Hot key is already registered.
0x00000582 ERROR_CLASS_ALREADY_EXISTS	Class already exists.
0x00000583 ERROR_CLASS_DOES_NOT_EXIST	Class does not exist.
0x00000584 ERROR_CLASS_HAS_WINDOWS	Class still has open windows.
0x00000585 ERROR_INVALID_INDEX	Invalid index.
0x00000586 ERROR_INVALID_ICON_HANDLE	Invalid icon handle.

Win32 error codes	Description
0x00000587 ERROR_PRIVATE_DIALOG_INDEX	Using private DIALOG window words.
0x00000588 ERROR_LISTBOX_ID_NOT_FOUND	The list box identifier was not found.
0x00000589 ERROR_NO_WILDCARD_CHARACTERS	No wildcards were found.
0x0000058A ERROR_CLIPBOARD_NOT_OPEN	Thread does not have a clipboard open.
0x0000058B ERROR_HOTKEY_NOT_REGISTERED	Hot key is not registered.
0x0000058C ERROR_WINDOW_NOT_DIALOG	The window is not a valid dialog window.
0x0000058D ERROR_CONTROL_ID_NOT_FOUND	Control ID not found.
0x0000058E ERROR_INVALID_COMBOBOX_MESSAGE	Invalid message for a combo box because it does not have an edit control.
0x0000058F ERROR_WINDOW_NOT_COMBOBOX	The window is not a combo box.
0x00000590 ERROR_INVALID_EDIT_HEIGHT	Height must be less than 256.
0x00000591 ERROR_DC_NOT_FOUND	Invalid device context (DC) handle.
0x00000592 ERROR_INVALID_HOOK_FILTER	Invalid hook procedure type.
0x00000593 ERROR_INVALID_FILTER_PROC	Invalid hook procedure.
0x00000594 ERROR_HOOK_NEEDS_HMOD	Cannot set nonlocal hook without a module handle.
0x00000595 ERROR_GLOBAL_ONLY_HOOK	This hook procedure can only be set globally.
0x00000596 ERROR_JOURNAL_HOOK_SET	The journal hook procedure is already installed.
0x00000597 ERROR_HOOK_NOT_INSTALLED	The hook procedure is not installed.
0x00000598 ERROR_INVALID_LB_MESSAGE	Invalid message for single-selection list box.
0x00000599 ERROR_SETCOUNT_ON_BAD_LB	LB_SETCOUNT sent to non-lazy list box.
0x0000059A	This list box does not support tab stops.

Win32 error codes	Description
ERROR_LB_WITHOUT_TABSTOPS	
0x0000059B ERROR_DESTROY_OBJECT_OF_OTHER_THREAD	Cannot destroy object created by another thread.
0x0000059C ERROR_CHILD_WINDOW_MENU	Child windows cannot have menus.
0x0000059D ERROR_NO_SYSTEM_MENU	The window does not have a system menu.
0x0000059E ERROR_INVALID_MSGBOX_STYLE	Invalid message box style.
0x0000059F ERROR_INVALID_SPI_VALUE	Invalid system-wide (SPI_*) parameter.
0x000005A0 ERROR_SCREEN_ALREADY_LOCKED	Screen already locked.
0x000005A1 ERROR_HWNDS_HAVE_DIFF_PARENT	All handles to windows in a multiple-window position structure must have the same parent.
0x000005A2 ERROR_NOT_CHILD_WINDOW	The window is not a child window.
0x000005A3 ERROR_INVALID_GW_COMMAND	Invalid GW_* command.
0x000005A4 ERROR_INVALID_THREAD_ID	Invalid thread identifier.
0x000005A5 ERROR_NON_MDICHILD_WINDOW	Cannot process a message from a window that is not a multiple document interface (MDI) window.
0x000005A6 ERROR_POPUP_ALREADY_ACTIVE	Pop-up menu already active.
0x000005A7 ERROR_NO_SCROLLBARS	The window does not have scroll bars.
0x000005A8 ERROR_INVALID_SCROLLBAR_RANGE	Scroll bar range cannot be greater than MAXLONG.
0x000005A9 ERROR_INVALID_SHOWWIN_COMMAND	Cannot show or remove the window in the way specified.
0x000005AA ERROR_NO_SYSTEM_RESOURCES	Insufficient system resources exist to complete the requested service.
0x000005AB ERROR_NONPAGED_SYSTEM_RESOURCES	Insufficient system resources exist to complete the requested service.
0x000005AC ERROR_PAGED_SYSTEM_RESOURCES	Insufficient system resources exist to complete the requested service.
0x000005AD	Insufficient quota to complete the requested

Win32 error codes	Description
ERROR_WORKING_SET_QUOTA	service.
0x000005AE ERROR_PAGEFILE_QUOTA	Insufficient quota to complete the requested service.
0x000005AF ERROR_COMMITMENT_LIMIT	The paging file is too small for this operation to complete.
0x000005B0 ERROR_MENU_ITEM_NOT_FOUND	A menu item was not found.
0x000005B1 ERROR_INVALID_KEYBOARD_HANDLE	Invalid keyboard layout handle.
0x000005B2 ERROR_HOOK_TYPE_NOT_ALLOWED	Hook type not allowed.
0x000005B3 ERROR_REQUIRES_INTERACTIVE_WINDOWSTATION	This operation requires an interactive window station.
0x000005B4 ERROR_TIMEOUT	This operation returned because the time-out period expired.
0x000005B5 ERROR_INVALID_MONITOR_HANDLE	Invalid monitor handle.
0x000005B6 ERROR_INCORRECT_SIZE	Incorrect size argument.
0x000005B7 ERROR_SYMLINK_CLASS_DISABLED	The symbolic link cannot be followed because its type is disabled.
0x000005B8 ERROR_SYMLINK_NOT_SUPPORTED	This application does not support the current operation on symbolic links.
0x000005DC ERROR_EVENTLOG_FILE_CORRUPT	The event log file is corrupted.
0x000005DD ERROR_EVENTLOG_CANT_START	No event log file could be opened, so the event logging service did not start.
0x000005DE ERROR_LOG_FILE_FULL	The event log file is full.
0x000005DF ERROR_EVENTLOG_FILE_CHANGED	The event log file has changed between read operations.
0x0000060E ERROR_INVALID_TASK_NAME	The specified task name is invalid.
0x0000060F ERROR_INVALID_TASK_INDEX	The specified task index is invalid.
0x00000610 ERROR_THREAD_ALREADY_IN_TASK	The specified thread is already joining a task.
0x00000641 ERROR_INSTALL_SERVICE_FAILURE	The Windows Installer service could not be accessed. This can occur if the Windows

Win32 error codes	Description
	Installer is not correctly installed. Contact your support personnel for assistance.
0x00000642 ERROR_INSTALL_USEREXIT	User canceled installation.
0x00000643 ERROR_INSTALL_FAILURE	Fatal error during installation.
0x00000644 ERROR_INSTALL_SUSPEND	Installation suspended, incomplete.
0x00000645 ERROR_UNKNOWN_PRODUCT	This action is valid only for products that are currently installed.
0x00000646 ERROR_UNKNOWN_FEATURE	Feature ID not registered.
0x00000647 ERROR_UNKNOWN_COMPONENT	Component ID not registered.
0x00000648 ERROR_UNKNOWN_PROPERTY	Unknown property.
0x00000649 ERROR_INVALID_HANDLE_STATE	Handle is in an invalid state.
0x0000064A ERROR_BAD_CONFIGURATION	The configuration data for this product is corrupt. Contact your support personnel.
0x0000064B ERROR_INDEX_ABSENT	Component qualifier not present.
0x0000064C ERROR_INSTALL_SOURCE_ABSENT	The installation source for this product is not available. Verify that the source exists and that you can access it.
0x0000064D ERROR_INSTALL_PACKAGE_VERSION	This installation package cannot be installed by the Windows Installer service. You must install a Windows service pack that contains a newer version of the Windows Installer service.
0x0000064E ERROR_PRODUCT_UNINSTALLED	Product is uninstalled.
0x0000064F ERROR_BAD_QUERY_SYNTAX	SQL query syntax invalid or unsupported.
0x00000650 ERROR_INVALID_FIELD	Record field does not exist.
0x00000651 ERROR_DEVICE_REMOVED	The device has been removed.
0x00000652 ERROR_INSTALL_ALREADY_RUNNING	Another installation is already in progress. Complete that installation before proceeding with this install.

Win32 error codes	Description
0x00000653 ERROR_INSTALL_PACKAGE_OPEN_FAILED	This installation package could not be opened. Verify that the package exists and that you can access it, or contact the application vendor to verify that this is a valid Windows Installer package.
0x00000654 ERROR_INSTALL_PACKAGE_INVALID	This installation package could not be opened. Contact the application vendor to verify that this is a valid Windows Installer package.
0x00000655 ERROR_INSTALL_UI_FAILURE	There was an error starting the Windows Installer service user interface. Contact your support personnel.
0x00000656 ERROR_INSTALL_LOG_FAILURE	Error opening installation log file. Verify that the specified log file location exists and that you can write to it.
0x00000657 ERROR_INSTALL_LANGUAGE_UNSUPPORTED	The language of this installation package is not supported by your system.
0x00000658 ERROR_INSTALL_TRANSFORM_FAILURE	Error applying transforms. Verify that the specified transform paths are valid.
0x00000659 ERROR_INSTALL_PACKAGE_REJECTED	This installation is forbidden by system policy. Contact your system administrator.
0x0000065A ERROR_FUNCTION_NOT_CALLED	Function could not be executed.
0x0000065B ERROR_FUNCTION_FAILED	Function failed during execution.
0x0000065C ERROR_INVALID_TABLE	Invalid or unknown table specified.
0x0000065D ERROR_DATATYPE_MISMATCH	Data supplied is of wrong type.
0x0000065E ERROR_UNSUPPORTED_TYPE	Data of this type is not supported.
0x0000065F ERROR_CREATE_FAILED	The Windows Installer service failed to start. Contact your support personnel.
0x00000660 ERROR_INSTALL_TEMP_UNWRITABLE	The Temp folder is on a drive that is full or is inaccessible. Free up space on the drive or verify that you have write permission on the Temp folder.
0x00000661 ERROR_INSTALL_PLATFORM_UNSUPPORTED	This installation package is not supported by this processor type. Contact your product vendor.
0x00000662 ERROR_INSTALL_NOTUSED	Component not used on this computer.
0x00000663	This update package could not be opened.

Win32 error codes	Description
ERROR_PATCH_PACKAGE_OPEN_FAILED	Verify that the update package exists and that you can access it, or contact the application vendor to verify that this is a valid Windows Installer update package.
0x00000664 ERROR_PATCH_PACKAGE_INVALID	This update package could not be opened. Contact the application vendor to verify that this is a valid Windows Installer update package.
0x00000665 ERROR_PATCH_PACKAGE_UNSUPPORTED	This update package cannot be processed by the Windows Installer service. You must install a Windows service pack that contains a newer version of the Windows Installer service.
0x00000666 ERROR_PRODUCT_VERSION	Another version of this product is already installed. Installation of this version cannot continue. To configure or remove the existing version of this product, use Add/Remove Programs in Control Panel.
0x00000667 ERROR_INVALID_COMMAND_LINE	Invalid command-line argument. Consult the Windows Installer SDK for detailed command line help.
0x00000668 ERROR_INSTALL_REMOTE_DISALLOWED	Only administrators have permission to add, remove, or configure server software during a Terminal Services remote session. If you want to install or configure software on the server, contact your network administrator.
0x00000669 ERROR_SUCCESS_REBOOT_INITIATED	The requested operation completed successfully. The system will be restarted so the changes can take effect.
0x0000066A ERROR_PATCH_TARGET_NOT_FOUND	The upgrade cannot be installed by the Windows Installer service because the program to be upgraded may be missing, or the upgrade may update a different version of the program. Verify that the program to be upgraded exists on your computer and that you have the correct upgrade.
0x0000066B ERROR_PATCH_PACKAGE_REJECTED	The update package is not permitted by a software restriction policy.
0x0000066C ERROR_INSTALL_TRANSFORM_REJECTED	One or more customizations are not permitted by a software restriction policy.
0x0000066D ERROR_INSTALL_REMOTE_PROHIBITED	The Windows Installer does not permit installation from a Remote Desktop Connection.
0x0000066E ERROR_PATCH_REMOVAL_UNSUPPORTED	Uninstallation of the update package is not supported.
0x0000066F ERROR_UNKNOWN_PATCH	The update is not applied to this product.



Win32 error codes	Description
0x00000670 ERROR_PATCH_NO_SEQUENCE	No valid sequence could be found for the set of updates.
0x00000671 ERROR_PATCH_REMOVAL_DISALLOWED	Update removal was disallowed by policy.
0x00000672 ERROR_INVALID_PATCH_XML	The XML update data is invalid.
0x00000673 ERROR_PATCH_MANAGED_ADVERTISED_PRODUCT	Windows Installer does not permit updating of managed advertised products. At least one feature of the product must be installed before applying the update.
0x00000674 ERROR_INSTALL_SERVICE_SAFEBOOT	The Windows Installer service is not accessible in Safe Mode. Try again when your computer is not in Safe Mode or you can use System Restore to return your machine to a previous good state.
0x000006A4 RPC_S_INVALID_STRING_BINDING	The string binding is invalid.
0x000006A5 RPC_S_WRONG_KIND_OF_BINDING	The binding handle is not the correct type.
0x000006A6 RPC_S_INVALID_BINDING	The binding handle is invalid.
0x000006A7 RPC_S_PROTSEQ_NOT_SUPPORTED	The RPC protocol sequence is not supported.
0x000006A8 RPC_S_INVALID_RPC_PROTSEQ	The RPC protocol sequence is invalid.
0x000006A9 RPC_S_INVALID_STRING_UUID	The string UUID is invalid.
0x000006AA RPC_S_INVALID_ENDPOINT_FORMAT	The endpoint format is invalid.
0x000006AB RPC_S_INVALID_NET_ADDR	The network address is invalid.
0x000006AC RPC_S_NO_ENDPOINT_FOUND	No endpoint was found.
0x000006AD RPC_S_INVALID_TIMEOUT	The time-out value is invalid.
0x000006AE RPC_S_OBJECT_NOT_FOUND	The object UUID) was not found.
0x000006AF RPC_S_ALREADY_REGISTERED	The object UUID) has already been registered.
0x000006B0 RPC_S_TYPE_ALREADY_REGISTERED	The type UUID has already been registered.

Win32 error codes	Description
0x000006B1 RPC_S_ALREADY_LISTENING	The RPC server is already listening.
0x000006B2 RPC_S_NO_PROTSEQS_REGISTERED	No protocol sequences have been registered.
0x000006B3 RPC_S_NOT_LISTENING	The RPC server is not listening.
0x000006B4 RPC_S_UNKNOWN_MGR_TYPE	The manager type is unknown.
0x000006B5 RPC_S_UNKNOWN_IF	The interface is unknown.
0x000006B6 RPC_S_NO_BINDINGS	There are no bindings.
0x000006B7 RPC_S_NO_PROTSEQS	There are no protocol sequences.
0x000006B8 RPC_S_CANT_CREATE_ENDPOINT	The endpoint cannot be created.
0x000006B9 RPC_S_OUT_OF_RESOURCES	Not enough resources are available to complete this operation.
0x000006BA RPC_S_SERVER_UNAVAILABLE	The RPC server is unavailable.
0x000006BB RPC_S_SERVER_TOO_BUSY	The RPC server is too busy to complete this operation.
0x000006BC RPC_S_INVALID_NETWORK_OPTIONS	The network options are invalid.
0x000006BD RPC_S_NO_CALL_ACTIVE	There are no RPCs active on this thread.
0x000006BE RPC_S_CALL_FAILED	The RPC failed.
0x000006BF RPC_S_CALL_FAILED_DNE	The RPC failed and did not execute.
0x000006C0 RPC_S_PROTOCOL_ERROR	An RPC protocol error occurred.
0x000006C1 RPC_S_PROXY_ACCESS_DENIED	Access to the HTTP proxy is denied.
0x000006C2 RPC_S_UNSUPPORTED_TRANS_SYN	The transfer syntax is not supported by the RPC server.
0x000006C4 RPC_S_UNSUPPORTED_TYPE	The UUID type is not supported.
0x000006C5	The tag is invalid.

Win32 error codes	Description
RPC_S_INVALID_TAG	
0x000006C6 RPC_S_INVALID_BOUND	The array bounds are invalid.
0x000006C7 RPC_S_NO_ENTRY_NAME	The binding does not contain an entry name.
0x000006C8 RPC_S_INVALID_NAME_SYNTAX	The name syntax is invalid.
0x000006C9 RPC_S_UNSUPPORTED_NAME_SYNTAX	The name syntax is not supported.
0x000006CB RPC_S_UUID_NO_ADDRESS	No network address is available to use to construct a UUID.
0x000006CC RPC_S_DUPLICATE_ENDPOINT	The endpoint is a duplicate.
0x000006CD RPC_S_UNKNOWN_AUTHN_TYPE	The authentication type is unknown.
0x000006CE RPC_S_MAX_CALLS_TOO_SMALL	The maximum number of calls is too small.
0x000006CF RPC_S_STRING_TOO_LONG	The string is too long.
0x000006D0 RPC_S_PROTSEQ_NOT_FOUND	The RPC protocol sequence was not found.
0x000006D1 RPC_S_PROCNUM_OUT_OF_RANGE	The procedure number is out of range.
0x000006D2 RPC_S_BINDING_HAS_NO_AUTH	The binding does not contain any authentication information.
0x000006D3 RPC_S_UNKNOWN_AUTHN_SERVICE	The authentication service is unknown.
0x000006D4 RPC_S_UNKNOWN_AUTHN_LEVEL	The authentication level is unknown.
0x000006D5 RPC_S_INVALID_AUTH_IDENTITY	The security context is invalid.
0x000006D6 RPC_S_UNKNOWN_AUTHZ_SERVICE	The authorization service is unknown.
0x000006D7 EPT_S_INVALID_ENTRY	The entry is invalid.
0x000006D8 EPT_S_CANT_PERFORM_OP	The server endpoint cannot perform the operation.
0x000006D9 EPT_S_NOT_REGISTERED	There are no more endpoints available from the endpoint mapper.

Win32 error codes	Description
0x000006DA RPC_S_NOTHING_TO_EXPORT	No interfaces have been exported.
0x000006DB RPC_S_INCOMPLETE_NAME	The entry name is incomplete.
0x000006DC RPC_S_INVALID_VERS_OPTION	The version option is invalid.
0x000006DD RPC_S_NO_MORE_MEMBERS	There are no more members.
0x000006DE RPC_S_NOT_ALL_OBJS_UNEXPORTED	There is nothing to unexport.
0x000006DF RPC_S_INTERFACE_NOT_FOUND	The interface was not found.
0x000006E0 RPC_S_ENTRY_ALREADY_EXISTS	The entry already exists.
0x000006E1 RPC_S_ENTRY_NOT_FOUND	The entry is not found.
0x000006E2 RPC_S_NAME_SERVICE_UNAVAILABLE	The name service is unavailable.
0x000006E3 RPC_S_INVALID_NAF_ID	The network address family is invalid.
0x000006E4 RPC_S_CANNOT_SUPPORT	The requested operation is not supported.
0x000006E5 RPC_S_NO_CONTEXT_AVAILABLE	No security context is available to allow impersonation.
0x000006E6 RPC_S_INTERNAL_ERROR	An internal error occurred in an RPC.
0x000006E7 RPC_S_ZERO_DIVIDE	The RPC server attempted an integer division by zero.
0x000006E8 RPC_S_ADDRESS_ERROR	An addressing error occurred in the RPC server.
0x000006E9 RPC_S_FP_DIV_ZERO	A floating-point operation at the RPC server caused a division by zero.
0x000006EA RPC_S_FP_UNDERFLOW	A floating-point underflow occurred at the RPC server.
0x000006EB RPC_S_FP_OVERFLOW	A floating-point overflow occurred at the RPC server.
0x000006EC RPC_X_NO_MORE_ENTRIES	The list of RPC servers available for the binding of auto handles has been exhausted.
0x000006ED	Unable to open the character translation table

Win32 error codes	Description
RPC_X_SS_CHAR_TRANS_OPEN_FAIL	file.
0x000006EE RPC_X_SS_CHAR_TRANS_SHORT_FILE	The file containing the character translation table has fewer than 512 bytes.
0x000006EF RPC_X_SS_IN_NULL_CONTEXT	A null context handle was passed from the client to the host during an RPC.
0x000006F1 RPC_X_SS_CONTEXT_DAMAGED	The context handle changed during an RPC.
0x000006F2 RPC_X_SS_HANDLES_MISMATCH	The binding handles passed to an RPC do not match.
0x000006F3 RPC_X_SS_CANNOT_GET_CALL_HANDLE	The stub is unable to get the RPC handle.
0x000006F4 RPC_X_NULL_REF_POINTER	A null reference pointer was passed to the stub.
0x000006F5 RPC_X_ENUM_VALUE_OUT_OF_RANGE	The enumeration value is out of range.
0x000006F6 RPC_X_BYTE_COUNT_TOO_SMALL	The byte count is too small.
0x000006F7 RPC_X_BAD_STUB_DATA	The stub received bad data.
0x000006F8 ERROR_INVALID_USER_BUFFER	The supplied user buffer is not valid for the requested operation.
0x000006F9 ERROR_UNRECOGNIZED_MEDIA	The disk media is not recognized. It may not be formatted.
0x000006FA ERROR_NO_TRUST_LSA_SECRET	The workstation does not have a trust secret.
0x000006FB ERROR_NO_TRUST_SAM_ACCOUNT	The security database on the server does not have a computer account for this workstation trust relationship.
0x000006FC ERROR_TRUSTED_DOMAIN_FAILURE	The trust relationship between the primary domain and the trusted domain failed.
0x000006FD ERROR_TRUSTED_RELATIONSHIP_FAILURE	The trust relationship between this workstation and the primary domain failed.
0x000006FE ERROR_TRUST_FAILURE	The network logon failed.
0x000006FF RPC_S_CALL_IN_PROGRESS	An RPC is already in progress for this thread.
0x00000700 ERROR_NETLOGON_NOT_STARTED	An attempt was made to log on, but the network logon service was not started.
0x00000701	The user's account has expired.

Win32 error codes	Description
ERROR_ACCOUNT_EXPIRED	
0x00000702 ERROR_REDIRECTOR_HAS_OPEN_HANDLES	The redirector is in use and cannot be unloaded.
0x00000703 ERROR_PRINTER_DRIVER_ALREADY_INSTALLED	The specified printer driver is already installed.
0x00000704 ERROR_UNKNOWN_PORT	The specified port is unknown.
0x00000705 ERROR_UNKNOWN_PRINTER_DRIVER	The printer driver is unknown.
0x00000706 ERROR_UNKNOWN_PRINTPROCESSOR	The print processor is unknown.
0x00000707 ERROR_INVALID_SEPARATOR_FILE	The specified separator file is invalid.
0x00000708 ERROR_INVALID_PRIORITY	The specified priority is invalid.
0x00000709 ERROR_INVALID_PRINTER_NAME	The printer name is invalid.
0x0000070A ERROR_PRINTER_ALREADY_EXISTS	The printer already exists.
0x0000070B ERROR_INVALID_PRINTER_COMMAND	The printer command is invalid.
0x0000070C ERROR_INVALID_DATATYPE	The specified data type is invalid.
0x0000070D ERROR_INVALID_ENVIRONMENT	The environment specified is invalid.
0x0000070E RPC_S_NO_MORE_BINDINGS	There are no more bindings.
0x0000070F ERROR_NOLOGON_INTERDOMAIN_TRUST_ACCOUNT	The account used is an interdomain trust account. Use your global user account or local user account to access this server.
0x00000710 ERROR_NOLOGON_WORKSTATION_TRUST_ACCOUNT	The account used is a computer account. Use your global user account or local user account to access this server.
0x00000711 ERROR_NOLOGON_SERVER_TRUST_ACCOUNT	The account used is a server trust account. Use your global user account or local user account to access this server.
0x00000712 ERROR_DOMAIN_TRUST_INCONSISTENT	The name or SID of the domain specified is inconsistent with the trust information for that domain.
0x00000713	The server is in use and cannot be unloaded.

Win32 error codes	Description
ERROR_SERVER_HAS_OPEN_HANDLES	
0x00000714 ERROR_RESOURCE_DATA_NOT_FOUND	The specified image file did not contain a resource section.
0x00000715 ERROR_RESOURCE_TYPE_NOT_FOUND	The specified resource type cannot be found in the image file.
0x00000716 ERROR_RESOURCE_NAME_NOT_FOUND	The specified resource name cannot be found in the image file.
0x00000717 ERROR_RESOURCE_LANG_NOT_FOUND	The specified resource language ID cannot be found in the image file.
0x00000718 ERROR_NOT_ENOUGH_QUOTA	Not enough quota is available to process this command.
0x00000719 RPC_S_NO_INTERFACES	No interfaces have been registered.
0x0000071A RPC_S_CALL_CANCELLED	The RPC was canceled.
0x0000071B RPC_S_BINDING_INCOMPLETE	The binding handle does not contain all the required information.
0x0000071C RPC_S_COMM_FAILURE	A communications failure occurred during an RPC.
0x0000071D RPC_S_UNSUPPORTED_AUTHN_LEVEL	The requested authentication level is not supported.
0x0000071E RPC_S_NO_PRINC_NAME	No principal name is registered.
0x0000071F RPC_S_NOT_RPC_ERROR	The error specified is not a valid Windows RPC error code.
0x00000720 RPC_S_UUID_LOCAL_ONLY	A UUID that is valid only on this computer has been allocated.
0x00000721 RPC_S_SEC_PKG_ERROR	A security package-specific error occurred.
0x00000722 RPC_S_NOT_CANCELLED	The thread is not canceled.
0x00000723 RPC_X_INVALID_ES_ACTION	Invalid operation on the encoding/decoding handle.
0x00000724 RPC_X_WRONG_ES_VERSION	Incompatible version of the serializing package.
0x00000725 RPC_X_WRONG_STUB_VERSION	Incompatible version of the RPC stub.
0x00000726 RPC_X_INVALID_PIPE_OBJECT	The RPC pipe object is invalid or corrupted.

Win32 error codes	Description
0x00000727 RPC_X_WRONG_PIPE_ORDER	An invalid operation was attempted on an RPC pipe object.
0x00000728 RPC_X_WRONG_PIPE_VERSION	Unsupported RPC pipe version.
0x0000076A RPC_S_GROUP_MEMBER_NOT_FOUND	The group member was not found.
0x0000076B EPT_S_CANT_CREATE	The endpoint mapper database entry could not be created.
0x0000076C RPC_S_INVALID_OBJECT	The object UUID is the nil UUID.
0x0000076D ERROR_INVALID_TIME	The specified time is invalid.
0x0000076E ERROR_INVALID_FORM_NAME	The specified form name is invalid.
0x0000076F ERROR_INVALID_FORM_SIZE	The specified form size is invalid.
0x00000770 ERROR_ALREADY_WAITING	The specified printer handle is already being waited on.
0x00000771 ERROR_PRINTER_DELETED	The specified printer has been deleted.
0x00000772 ERROR_INVALID_PRINTER_STATE	The state of the printer is invalid.
0x00000773 ERROR_PASSWORD_MUST_CHANGE	The user's password must be changed before logging on the first time.
0x00000774 ERROR_DOMAIN_CONTROLLER_NOT_FOUND	Could not find the domain controller for this domain.
0x00000775 ERROR_ACCOUNT_LOCKED_OUT	The referenced account is currently locked out and may not be logged on to.
0x00000776 OR_INVALID_OXID	The object exporter specified was not found.
0x00000777 OR_INVALID_OID	The object specified was not found.
0x00000778 OR_INVALID_SET	The object set specified was not found.
0x00000779 RPC_S_SEND_INCOMPLETE	Some data remains to be sent in the request buffer.
0x0000077A RPC_S_INVALID_ASYNC_HANDLE	Invalid asynchronous RPC handle.
0x0000077B	Invalid asynchronous RPC call handle for this



Win32 error codes	Description
RPC_S_INVALID_ASYNC_CALL	operation.
0x0000077C RPC_X_PIPE_CLOSED	The RPC pipe object has already been closed.
0x0000077D RPC_X_PIPE_DISCIPLINE_ERROR	The RPC call completed before all pipes were processed.
0x0000077E RPC_X_PIPE_EMPTY	No more data is available from the RPC pipe.
0x0000077F ERROR_NO_SITENAME	No site name is available for this machine.
0x00000780 ERROR_CANT_ACCESS_FILE	The file cannot be accessed by the system.
0x00000781 ERROR_CANT_RESOLVE_FILENAME	The name of the file cannot be resolved by the system.
0x00000782 RPC_S_ENTRY_TYPE_MISMATCH	The entry is not of the expected type.
0x00000783 RPC_S_NOT_ALL_OBJS_EXPORTED	Not all object UUIDs could be exported to the specified entry.
0x00000784 RPC_S_INTERFACE_NOT_EXPORTED	The interface could not be exported to the specified entry.
0x00000785 RPC_S_PROFILE_NOT_ADDED	The specified profile entry could not be added.
0x00000786 RPC_S_PRF_ELT_NOT_ADDED	The specified profile element could not be added.
0x00000787 RPC_S_PRF_ELT_NOT_REMOVED	The specified profile element could not be removed.
0x00000788 RPC_S_GRP_ELT_NOT_ADDED	The group element could not be added.
0x00000789 RPC_S_GRP_ELT_NOT_REMOVED	The group element could not be removed.
0x0000078A ERROR_KM_DRIVER_BLOCKED	The printer driver is not compatible with a policy enabled on your computer that blocks Windows NT 4.0 drivers.
0x0000078B ERROR_CONTEXT_EXPIRED	The context has expired and can no longer be used.
0x0000078C ERROR_PER_USER_TRUST_QUOTA_EXCEEDED	The current user's delegated trust creation quota has been exceeded.
0x0000078D ERROR_ALL_USER_TRUST_QUOTA_EXCEEDED	The total delegated trust creation quota has been exceeded.
0x0000078E	The current user's delegated trust deletion

Win32 error codes	Description
ERROR_USER_DELETE_TRUST_QUOTA_EXCEEDED	quota has been exceeded.
0x0000078F ERROR_AUTHENTICATION_FIREWALL_FAILED	Logon failure: The machine you are logging on to is protected by an authentication firewall. The specified account is not allowed to authenticate to the machine.
0x00000790 ERROR_REMOTE_PRINT_CONNECTIONS_BLOCKED	Remote connections to the Print Spooler are blocked by a policy set on your machine.
0x000007D0 ERROR_INVALID_PIXEL_FORMAT	The pixel format is invalid.
0x000007D1 ERROR_BAD_DRIVER	The specified driver is invalid.
0x000007D2 ERROR_INVALID_WINDOW_STYLE	The window style or class attribute is invalid for this operation.
0x000007D3 ERROR_METAFILE_NOT_SUPPORTED	The requested metafile operation is not supported.
0x000007D4 ERROR_TRANSFORM_NOT_SUPPORTED	The requested transformation operation is not supported.
0x000007D5 ERROR_CLIPPING_NOT_SUPPORTED	The requested clipping operation is not supported.
0x000007DA ERROR_INVALID_CMM	The specified color management module is invalid.
0x000007DB ERROR_INVALID_PROFILE	The specified color profile is invalid.
0x000007DC ERROR_TAG_NOT_FOUND	The specified tag was not found.
0x000007DD ERROR_TAG_NOT_PRESENT	A required tag is not present.
0x000007DE ERROR_DUPLICATE_TAG	The specified tag is already present.
0x000007DF ERROR_PROFILE_NOT_ASSOCIATED_WITH_DEVICE	The specified color profile is not associated with any device.
0x000007E0 ERROR_PROFILE_NOT_FOUND	The specified color profile was not found.
0x000007E1 ERROR_INVALID_COLORSPACE	The specified color space is invalid.
0x000007E2 ERROR_ICM_NOT_ENABLED	Image Color Management is not enabled.
0x000007E3 ERROR_DELETING_ICM_XFORM	There was an error while deleting the color transform.

Win32 error codes	Description
0x000007E4 ERROR_INVALID_TRANSFORM	The specified color transform is invalid.
0x000007E5 ERROR_COLORSPACE_MISMATCH	The specified transform does not match the bitmap's color space.
0x000007E6 ERROR_INVALID_COLORINDEX	The specified named color index is not present in the profile.
0x000007E7 ERROR_PROFILE_DOES_NOT_MATCH_DEVICE	The specified profile is intended for a device of a different type than the specified device.
0x00000836 NERR_NetNotStarted	The workstation driver is not installed.
0x00000837 NERR_UnknownServer	The server could not be located.
0x00000838 NERR_ShareMem	An internal error occurred. The network cannot access a shared memory segment.
0x00000839 NERR_NoNetworkResource	A network resource shortage occurred.
0x0000083A NERR_RemoteOnly	This operation is not supported on workstations.
0x0000083B NERR_DevNotRedirected	The device is not connected.
0x0000083C ERROR_CONNECTED_OTHER_PASSWORD	The network connection was made successfully, but the user had to be prompted for a password other than the one originally specified.
0x0000083D ERROR_CONNECTED_OTHER_PASSWORD_DEFAULT	The network connection was made successfully using default credentials.
0x00000842 NERR_ServerNotStarted	The Server service is not started.
0x00000843 NERR_ItemNotFound	The queue is empty.
0x00000844 NERR_UnknownDevDir	The device or directory does not exist.
0x00000845 NERR_RedirectedPath	The operation is invalid on a redirected resource.
0x00000846 NERR_DuplicateShare	The name has already been shared.
0x00000847 NERR_NoRoom	The server is currently out of the requested resource.
0x00000849 NERR_TooManyItems	Requested addition of items exceeds the maximum allowed.

Win32 error codes	Description
0x0000084A NERR_InvalidMaxUsers	The Peer service supports only two simultaneous users.
0x0000084B NERR_BufTooSmall	The API return buffer is too small.
0x0000084F NERR_RemoteErr	A remote API error occurred.
0x00000853 NERR_LanmanIniError	An error occurred when opening or reading the configuration file.
0x00000858 NERR_NetworkError	A general network error occurred.
0x00000859 NERR_WkstaInconsistentState	The Workstation service is in an inconsistent state. Restart the computer before restarting the Workstation service.
0x0000085A NERR_WkstaNotStarted	The Workstation service has not been started.
0x0000085B NERR_BrowserNotStarted	The requested information is not available.
0x0000085C NERR_InternalError	An internal error occurred.
0x0000085D NERR_BadTransactConfig	The server is not configured for transactions.
0x0000085E NERR_InvalidAPI	The requested API is not supported on the remote server.
0x0000085F NERR_BadEventName	The event name is invalid.
0x00000860 NERR_DupNameReboot	The computer name already exists on the network. Change it and reboot the computer.
0x00000862 NERR_CfgCompNotFound	The specified component could not be found in the configuration information.
0x00000863 NERR_CfgParamNotFound	The specified parameter could not be found in the configuration information.
0x00000865 NERR_LineTooLong	A line in the configuration file is too long.
0x00000866 NERR_QNotFound	The printer does not exist.
0x00000867 NERR_JobNotFound	The print job does not exist.
0x00000868 NERR_DestNotFound	The printer destination cannot be found.

Win32 error codes	Description
0x00000869 NERR_DestExists	The printer destination already exists.
0x0000086A NERR_QExists	The print queue already exists.
0x0000086B NERR_QNoRoom	No more printers can be added.
0x0000086C NERR_JobNoRoom	No more print jobs can be added.
0x0000086D NERR_DestNoRoom	No more printer destinations can be added.
0x0000086E NERR_DestIdle	This printer destination is idle and cannot accept control operations.
0x0000086F NERR_DestInvalidOp	This printer destination request contains an invalid control function.
0x00000870 NERR_ProcNoRespond	The print processor is not responding.
0x00000871 NERR_SpoolerNotLoaded	The spooler is not running.
0x00000872 NERR_DestInvalidState	This operation cannot be performed on the print destination in its current state.
0x00000873 NERR_QinvalidState	This operation cannot be performed on the print queue in its current state.
0x00000874 NERR_JobInvalidState	This operation cannot be performed on the print job in its current state.
0x00000875 NERR_SpoolNoMemory	A spooler memory allocation failure occurred.
0x00000876 NERR_DriverNotFound	The device driver does not exist.
0x00000877 NERR_DataTypeInvalid	The data type is not supported by the print processor.
0x00000878 NERR_ProcNotFound	The print processor is not installed.
0x00000884 NERR_ServiceTableLocked	The service database is locked.
0x00000885 NERR_ServiceTableFull	The service table is full.
0x00000886 NERR_ServiceInstalled	The requested service has already been started.
0x00000887	The service does not respond to control

Win32 error codes	Description
NERR_ServiceEntryLocked	actions.
0x00000888 NERR_ServiceNotInstalled	The service has not been started.
0x00000889 NERR_BadServiceName	The service name is invalid.
0x0000088A NERR_ServiceCtlTimeout	The service is not responding to the control function.
0x0000088B NERR_ServiceCtlBusy	The service control is busy.
0x0000088C NERR_BadServiceProgName	The configuration file contains an invalid service program name.
0x0000088D NERR_ServiceNotCtrl	The service could not be controlled in its present state.
0x0000088E NERR_ServiceKillProc	The service ended abnormally.
0x0000088F NERR_ServiceCtlNotValid	The requested pause or stop is not valid for this service.
0x00000890 NERR_NotInDispatchTbl	The service control dispatcher could not find the service name in the dispatch table.
0x00000891 NERR_BadControlRecv	The service control dispatcher pipe read failed.
0x00000892 NERR_ServiceNotStarting	A thread for the new service could not be created.
0x00000898 NERR_AlreadyLoggedIn	This workstation is already logged on to the LAN.
0x00000899 NERR_NotLoggedIn	The workstation is not logged on to the LAN.
0x0000089A NERR_BadUsername	The user name or group name parameter is invalid.
0x0000089B NERR_BadPassword	The password parameter is invalid.
0x0000089C NERR_UnableToAddName_W	The logon processor did not add the message alias.
0x0000089D NERR_UnableToAddName_F	The logon processor did not add the message alias.
0x0000089E NERR_UnableToDelName_W	@W The logoff processor did not delete the message alias.
0x0000089F NERR_UnableToDelName_F	The logoff processor did not delete the message alias.

Win32 error codes	Description
0x000008A1 NERR_LogonsPaused	Network logons are paused.
0x000008A2 NERR_LogonServerConflict	A centralized logon server conflict occurred.
0x000008A3 NERR_LogonNoUserPath	The server is configured without a valid user path.
0x000008A4 NERR_LogonScriptError	An error occurred while loading or running the logon script.
0x000008A6 NERR_StandaloneLogon	The logon server was not specified. The computer will be logged on as STANDALONE.
0x000008A7 NERR_LogonServerNotFound	The logon server could not be found.
0x000008A8 NERR_LogonDomainExists	There is already a logon domain for this computer.
0x000008A9 NERR_NonValidatedLogon	The logon server could not validate the logon.
0x000008AB NERR_ACFNotFound	The security database could not be found.
0x000008AC NERR_GroupNotFound	The group name could not be found.
0x000008AD NERR_UserNotFound	The user name could not be found.
0x000008AE NERR_ResourceNotFound	The resource name could not be found.
0x000008AF NERR_GroupExists	The group already exists.
0x000008B0 NERR_UserExists	The user account already exists.
0x000008B1 NERR_ResourceExists	The resource permission list already exists.
0x000008B2 NERR_NotPrimary	This operation is allowed only on the PDC of the domain.
0x000008B3 NERR_ACFNotLoaded	The security database has not been started.
0x000008B4 NERR_ACFNoRoom	There are too many names in the user accounts database.
0x000008B5 NERR_ACFFileIOFail	A disk I/O failure occurred.
0x000008B6	The limit of 64 entries per resource was

Win32 error codes	Description
NERR_ACFTooManyLists	exceeded.
0x000008B7 NERR_UserLogon	Deleting a user with a session is not allowed.
0x000008B8 NERR_ACFNoParent	The parent directory could not be located.
0x000008B9 NERR_CanNotGrowSegment	Unable to add to the security database session cache segment.
0x000008BA NERR_SpeGroupOp	This operation is not allowed on this special group.
0x000008BB NERR_NotInCache	This user is not cached in the user accounts database session cache.
0x000008BC NERR_UserInGroup	The user already belongs to this group.
0x000008BD NERR_UserNotInGroup	The user does not belong to this group.
0x000008BE NERR_AccountUndefined	This user account is undefined.
0x000008BF NERR_AccountExpired	This user account has expired.
0x000008C0 NERR_InvalidWorkstation	The user is not allowed to log on from this workstation.
0x000008C1 NERR_InvalidLogonHours	The user is not allowed to log on at this time.
0x000008C2 NERR_PasswordExpired	The password of this user has expired.
0x000008C3 NERR_PasswordCantChange	The password of this user cannot change.
0x000008C4 NERR_PasswordHistConflict	This password cannot be used now.
0x000008C5 NERR_PasswordTooShort	The password does not meet the password policy requirements. Check the minimum password length, password complexity, and password history requirements.
0x000008C6 NERR_PasswordTooRecent	The password of this user is too recent to change.
0x000008C7 NERR_InvalidDatabase	The security database is corrupted.
0x000008C8 NERR_DatabaseUpToDate	No updates are necessary to this replicant network or local security database.



Win32 error codes	Description
0x000008C9 NERR_SyncRequired	This replicant database is outdated; synchronization is required.
0x000008CA NERR_UseNotFound	The network connection could not be found.
0x000008CB NERR_BadAsgType	This asg_type is invalid.
0x000008CC NERR_DeviceIsShared	This device is currently being shared.
0x000008DE NERR_NoComputerName	The computer name could not be added as a message alias. The name may already exist on the network.
0x000008DF NERR_MsgAlreadyStarted	The Messenger service is already started.
0x000008E0 NERR_MsgInitFailed	The Messenger service failed to start.
0x000008E1 NERR_NameNotFound	The message alias could not be found on the network.
0x000008E2 NERR_AlreadyForwarded	This message alias has already been forwarded.
0x000008E3 NERR_AddForwarded	This message alias has been added but is still forwarded.
0x000008E4 NERR_AlreadyExists	This message alias already exists locally.
0x000008E5 NERR_TooManyNames	The maximum number of added message aliases has been exceeded.
0x000008E6 NERR_DelComputerName	The computer name could not be deleted.
0x000008E7 NERR_LocalForward	Messages cannot be forwarded back to the same workstation.
0x000008E8 NERR_GrpMsgProcessor	An error occurred in the domain message processor.
0x000008E9 NERR_PausedRemote	The message was sent, but the recipient has paused the Messenger service.
0x000008EA NERR_BadReceive	The message was sent but not received.
0x000008EB NERR_NameInUse	The message alias is currently in use. Try again later.
0x000008EC NERR_MsgNotStarted	The Messenger service has not been started.

Win32 error codes	Description
0x000008ED NERR_NotLocalName	The name is not on the local computer.
0x000008EE NERR_NoForwardName	The forwarded message alias could not be found on the network.
0x000008EF NERR_RemoteFull	The message alias table on the remote station is full.
0x000008F0 NERR_NameNotForwarded	Messages for this alias are not currently being forwarded.
0x000008F1 NERR_TruncatedBroadcast	The broadcast message was truncated.
0x000008F6 NERR_InvalidDevice	This is an invalid device name.
0x000008F7 NERR_WriteFault	A write fault occurred.
0x000008F9 NERR_DuplicateName	A duplicate message alias exists on the network.
0x000008FA NERR_DeleteLater	This message alias will be deleted later.
0x000008FB NERR_IncompleteDel	The message alias was not successfully deleted from all networks.
0x000008FC NERR_MultipleNets	This operation is not supported on computers with multiple networks.
0x00000906 NERR_NetNameNotFound	This shared resource does not exist.
0x00000907 NERR_DeviceNotShared	This device is not shared.
0x00000908 NERR_ClientNameNotFound	A session does not exist with that computer name.
0x0000090A NERR_FileIdNotFound	There is not an open file with that identification number.
0x0000090B NERR_ExecFailure	A failure occurred when executing a remote administration command.
0x0000090C NERR_TmpFile	A failure occurred when opening a remote temporary file.
0x0000090D NERR_TooMuchData	The data returned from a remote administration command has been truncated to 64 KB.
0x0000090E NERR_DeviceShareConflict	This device cannot be shared as both a spooled and a nonspooled resource.

Win32 error codes	Description
0x0000090F NERR_BrowserTableIncomplete	The information in the list of servers may be incorrect.
0x00000910 NERR_NotLocalDomain	The computer is not active in this domain.
0x00000911 NERR_IsDfsShare	The share must be removed from the Distributed File System (DFS) before it can be deleted.
0x0000091B NERR_DevInvalidOpCode	The operation is invalid for this device.
0x0000091C NERR_DevNotFound	This device cannot be shared.
0x0000091D NERR_DevNotOpen	This device was not open.
0x0000091E NERR_BadQueueDevString	This device name list is invalid.
0x0000091F NERR_BadQueuePriority	The queue priority is invalid.
0x00000921 NERR_NoCommDevs	There are no shared communication devices.
0x00000922 NERR_QueueNotFound	The queue you specified does not exist.
0x00000924 NERR_BadDevString	This list of devices is invalid.
0x00000925 NERR_BadDev	The requested device is invalid.
0x00000926 NERR_InUseBySpooler	This device is already in use by the spooler.
0x00000927 NERR_CommDevInUse	This device is already in use as a communication device.
0x0000092F NERR_InvalidComputer	This computer name is invalid.
0x00000932 NERR_MaxLenExceeded	The string and prefix specified are too long.
0x00000934 NERR_BadComponent	This path component is invalid.
0x00000935 NERR_CantType	Could not determine the type of input.
0x0000093A NERR_TooManyEntries	The buffer for types is not big enough.

Win32 error codes	Description
0x00000942 NERR_ProfileFileTooBig	Profile files cannot exceed 64 KB.
0x00000943 NERR_ProfileOffset	The start offset is out of range.
0x00000944 NERR_ProfileCleanup	The system cannot delete current connections to network resources.
0x00000945 NERR_ProfileUnknownCmd	The system was unable to parse the command line in this file.
0x00000946 NERR_ProfileLoadErr	An error occurred while loading the profile file.
0x00000947 NERR_ProfileSaveErr	Errors occurred while saving the profile file. The profile was partially saved.
0x00000949 NERR_LogOverflow	Log file %1 is full.
0x0000094A NERR_LogFileChanged	This log file has changed between reads.
0x0000094B NERR_LogFileCorrupt	Log file %1 is corrupt.
0x0000094C NERR_SourceIsDir	The source path cannot be a directory.
0x0000094D NERR_BadSource	The source path is illegal.
0x0000094E NERR_BadDest	The destination path is illegal.
0x0000094F NERR_DifferentServers	The source and destination paths are on different servers.
0x00000951 NERR_RunSrvPaused	The Run server you requested is paused.
0x00000955 NERR_ErrCommRunSrv	An error occurred when communicating with a Run server.
0x00000957 NERR_ErrorExecingGhost	An error occurred when starting a background process.
0x00000958 NERR_ShareNotFound	The shared resource you are connected to could not be found.
0x00000960 NERR_InvalidLana	The LAN adapter number is invalid.
0x00000961 NERR_OpenFiles	There are open files on the connection.
0x00000962	Active connections still exist.

Win32 error codes	Description
NERR_ActiveConns	
0x00000963 NERR_BadPasswordCore	This share name or password is invalid.
0x00000964 NERR_DevInUse	The device is being accessed by an active process.
0x00000965 NERR_LocalDrive	The drive letter is in use locally.
0x0000097E NERR_AlertExists	The specified client is already registered for the specified event.
0x0000097F NERR_TooManyAlerts	The alert table is full.
0x00000980 NERR_NoSuchAlert	An invalid or nonexistent alert name was raised.
0x00000981 NERR_BadRecipient	The alert recipient is invalid.
0x00000982 NERR_AcctLimitExceeded	A user's session with this server has been deleted.
0x00000988 NERR_InvalidLogSeek	The log file does not contain the requested record number.
0x00000992 NERR_BadUasConfig	The user accounts database is not configured correctly.
0x00000993 NERR_InvalidUASOp	This operation is not permitted when the Net Logon service is running.
0x00000994 NERR_LastAdmin	This operation is not allowed on the last administrative account.
0x00000995 NERR_DCNotFound	Could not find the domain controller for this domain.
0x00000996 NERR_LogonTrackingError	Could not set logon information for this user.
0x00000997 NERR_NetlogonNotStarted	The Net Logon service has not been started.
0x00000998 NERR_CanNotGrowUASFile	Unable to add to the user accounts database.
0x00000999 NERR_TimeDiffAtDC	This server's clock is not synchronized with the PDC's clock.
0x0000099A NERR_PasswordMismatch	A password mismatch has been detected.
0x0000099C NERR_NoSuchServer	The server identification does not specify a valid server.

Win32 error codes	Description
0x0000099D NERR_NoSuchSession	The session identification does not specify a valid session.
0x0000099E NERR_NoSuchConnection	The connection identification does not specify a valid connection.
0x0000099F NERR_TooManyServers	There is no space for another entry in the table of available servers.
0x000009A0 NERR_TooManySessions	The server has reached the maximum number of sessions it supports.
0x000009A1 NERR_TooManyConnections	The server has reached the maximum number of connections it supports.
0x000009A2 NERR_TooManyFiles	The server cannot open more files because it has reached its maximum number.
0x000009A3 NERR_NoAlternateServers	There are no alternate servers registered on this server.
0x000009A6 NERR_TryDownLevel	Try the down-level (remote admin protocol) version of API instead.
0x000009B0 NERR_UPSDriverNotStarted	The uninterruptible power supply (UPS) driver could not be accessed by the UPS service.
0x000009B1 NERR_UPSInvalidConfig	The UPS service is not configured correctly.
0x000009B2 NERR_UPSInvalidCommPort	The UPS service could not access the specified Comm Port.
0x000009B3 NERR_UPSSignalAsserted	The UPS indicated a line fail or low battery situation. Service not started.
0x000009B4 NERR_UPSShutdownFailed	The UPS service failed to perform a system shut down.
0x000009C4 NERR_BadDosRetCode	The program below returned an MS-DOS error code.
0x000009C5 NERR_ProgNeedsExtraMem	The program below needs more memory.
0x000009C6 NERR_BadDosFunction	The program below called an unsupported MS-DOS function.
0x000009C7 NERR_RemoteBootFailed	The workstation failed to boot.
0x000009C8 NERR_BadFileChecksum	The file below is corrupt.
0x000009C9 NERR_NoRplBootSystem	No loader is specified in the boot-block definition file.
0x000009CA	NetBIOS returned an error: The network

Win32 error codes	Description
NERR_RplLoadrNetBiosErr	control blocks (NCBs) and Server Message Block (SMB) are dumped above.
0x000009CB NERR_RplLoadrDiskErr	A disk I/O error occurred.
0x000009CC NERR_ImageParamErr	Image parameter substitution failed.
0x000009CD NERR_TooManyImageParams	Too many image parameters cross disk sector boundaries.
0x000009CE NERR_NonDosFloppyUsed	The image was not generated from an MS-DOS disk formatted with /S.
0x000009CF NERR_RplBootRestart	Remote boot will be restarted later.
0x000009D0 NERR_RplSrvrCallFailed	The call to the Remoteboot server failed.
0x000009D1 NERR_CantConnectRplSrvr	Cannot connect to the Remoteboot server.
0x000009D2 NERR_CantOpenImageFile	Cannot open image file on the Remoteboot server.
0x000009D3 NERR_CallingRplSrvr	Connecting to the Remoteboot server.
0x000009D4 NERR_StartingRplBoot	Connecting to the Remoteboot server.
0x000009D5 NERR_RplBootServiceTerm	Remote boot service was stopped, check the error log for the cause of the problem.
0x000009D6 NERR_RplBootStartFailed	Remote boot startup failed; check the error log for the cause of the problem.
0x000009D7 NERR_RPL_CONNECTED	A second connection to a Remoteboot resource is not allowed.
0x000009F6 NERR_BrowserConfiguredToNotRun	The browser service was configured with MaintainServerList=No.
0x00000A32 NERR_RplNoAdaptersStarted	Service failed to start because none of the network adapters started with this service.
0x00000A33 NERR_RplBadRegistry	Service failed to start due to bad startup information in the registry.
0x00000A34 NERR_RplBadDatabase	Service failed to start because its database is absent or corrupt.
0x00000A35 NERR_RplRplfilesShare	Service failed to start because the RPLFILES share is absent.
0x00000A36	Service failed to start because the RPLUSER

Win32 error codes	Description
NERR_RplNotRplServer	group is absent.
0x00000A37 NERR_RplCannotEnum	Cannot enumerate service records.
0x00000A38 NERR_RplWkstaInfoCorrupted	Workstation record information has been corrupted.
0x00000A39 NERR_RplWkstaNotFound	Workstation record was not found.
0x00000A3A NERR_RplWkstaNameUnavailable	Workstation name is in use by some other workstation.
0x00000A3B NERR_RplProfileInfoCorrupted	Profile record information has been corrupted.
0x00000A3C NERR_RplProfileNotFound	Profile record was not found.
0x00000A3D NERR_RplProfileNameUnavailable	Profile name is in use by some other profile.
0x00000A3E NERR_RplProfileNotEmpty	There are workstations using this profile.
0x00000A3F NERR_RplConfigInfoCorrupted	Configuration record information has been corrupted.
0x00000A40 NERR_RplConfigNotFound	Configuration record was not found.
0x00000A41 NERR_RplAdapterInfoCorrupted	Adapter ID record information has been corrupted.
0x00000A42 NERR_RplInternal	An internal service error has occurred.
0x00000A43 NERR_RplVendorInfoCorrupted	Vendor ID record information has been corrupted.
0x00000A44 NERR_RplBootInfoCorrupted	Boot block record information has been corrupted.
0x00000A45 NERR_RplWkstaNeedsUserAcct	The user account for this workstation record is missing.
0x00000A46 NERR_RplNeedsRPLUSERAcct	The RPLUSER local group could not be found.
0x00000A47 NERR_RplBootNotFound	Boot block record was not found.
0x00000A48 NERR_RplIncompatibleProfile	Chosen profile is incompatible with this workstation.
0x00000A49 NERR_RplAdapterNameUnavailable	Chosen network adapter ID is in use by some other workstation.



Win32 error codes	Description
0x00000A4A NERR_RplConfigNotEmpty	There are profiles using this configuration.
0x00000A4B NERR_RplBootInUse	There are workstations, profiles, or configurations using this boot block.
0x00000A4C NERR_RplBackupDatabase	Service failed to back up the Remoteboot database.
0x00000A4D NERR_RplAdapterNotFound	Adapter record was not found.
0x00000A4E NERR_RplVendorNotFound	Vendor record was not found.
0x00000A4F NERR_RplVendorNameUnavailable	Vendor name is in use by some other vendor record.
0x00000A50 NERR_RplBootNameUnavailable	The boot name or vendor ID is in use by some other boot block record.
0x00000A51 NERR_RplConfigNameUnavailable	The configuration name is in use by some other configuration.
0x00000A64 NERR_DfsInternalCorruption	The internal database maintained by the DFS service is corrupt.
0x00000A65 NERR_DfsVolumeDataCorrupt	One of the records in the internal DFS database is corrupt.
0x00000A66 NERR_DfsNoSuchVolume	There is no DFS name whose entry path matches the input entry path.
0x00000A67 NERR_DfsVolumeAlreadyExists	A root or link with the given name already exists.
0x00000A68 NERR_DfsAlreadyShared	The server share specified is already shared in the DFS.
0x00000A69 NERR_DfsNoSuchShare	The indicated server share does not support the indicated DFS namespace.
0x00000A6A NERR_DfsNotALeafVolume	The operation is not valid in this portion of the namespace.
0x00000A6B NERR_DfsLeafVolume	The operation is not valid in this portion of the namespace.
0x00000A6C NERR_DfsVolumeHasMultipleServers	The operation is ambiguous because the link has multiple servers.
0x00000A6D NERR_DfsCantCreateJunctionPoint	Unable to create a link.
0x00000A6E NERR_DfsServerNotDfsAware	The server is not DFS-aware.
0x00000A6F	The specified rename target path is invalid.

Win32 error codes	Description
NERR_DfsBadRenamePath	
0x00000A70 NERR_DfsVolumeIsOffline	The specified DFS link is offline.
0x00000A71 NERR_DfsNoSuchServer	The specified server is not a server for this link.
0x00000A72 NERR_DfsCyclicalName	A cycle in the DFS name was detected.
0x00000A73 NERR_DfsNotSupportedInServerDfs	The operation is not supported on a server-based DFS.
0x00000A74 NERR_DfsDuplicateService	This link is already supported by the specified server share.
0x00000A75 NERR_DfsCantRemoveLastServerShare	Cannot remove the last server share supporting this root or link.
0x00000A76 NERR_DfsVolumeIsInterDfs	The operation is not supported for an inter-DFS link.
0x00000A77 NERR_DfsInconsistent	The internal state of the DFS Service has become inconsistent.
0x00000A78 NERR_DfsServerUpgraded	The DFS Service has been installed on the specified server.
0x00000A79 NERR_DfsDataIsIdentical	The DFS data being reconciled is identical.
0x00000A7A NERR_DfsCantRemoveDfsRoot	The DFS root cannot be deleted. Uninstall DFS if required.
0x00000A7B NERR_DfsChildOrParentInDfs	A child or parent directory of the share is already in a DFS.
0x00000A82 NERR_DfsInternalError	DFS internal error.
0x00000A83 NERR_SetupAlreadyJoined	This machine is already joined to a domain.
0x00000A84 NERR_SetupNotJoined	This machine is not currently joined to a domain.
0x00000A85 NERR_SetupDomainController	This machine is a domain controller and cannot be unjoined from a domain.
0x00000A86 NERR_DefaultJoinRequired	The destination domain controller does not support creating machine accounts in organizational units (OUs).
0x00000A87 NERR_InvalidWorkgroupName	The specified workgroup name is invalid.
0x00000A88	The specified computer name is incompatible

Win32 error codes	Description
NERR_NameUsesIncompatibleCodePage	with the default language used on the domain controller.
0x00000A89 NERR_ComputerAccountNotFound	The specified computer account could not be found.
0x00000A8A NERR_PersonalSku	This version of Windows cannot be joined to a domain.
0x00000A8D NERR_PasswordMustChange	The password must change at the next logon.
0x00000A8E NERR_AccountLockedOut	The account is locked out.
0x00000A8F NERR_PasswordTooLong	The password is too long.
0x00000A90 NERR_PasswordNotComplexEnough	The password does not meet the complexity policy.
0x00000A91 NERR_PasswordFilterError	The password does not meet the requirements of the password filter DLLs.
0x00000BB8 ERROR_UNKNOWN_PRINT_MONITOR	The specified print monitor is unknown.
0x00000BB9 ERROR_PRINTER_DRIVER_IN_USE	The specified printer driver is currently in use.
0x00000BBA ERROR_SPOOL_FILE_NOT_FOUND	The spool file was not found.
0x00000BBB ERROR_SPL_NO_STARTDOC	A StartDocPrinter call was not issued.
0x00000BBC ERROR_SPL_NO_ADDJOB	An AddJob call was not issued.
0x00000BBE ERROR_PRINT_PROCESSOR_ALREADY_INSTALLED	The specified print processor has already been installed.
0x00000BBE ERROR_PRINT_MONITOR_ALREADY_INSTALLED	The specified print monitor has already been installed.
0x00000BBF ERROR_INVALID_PRINT_MONITOR	The specified print monitor does not have the required functions.
0x00000BC0 ERROR_PRINT_MONITOR_IN_USE	The specified print monitor is currently in use.
0x00000BC1 ERROR_PRINTER_HAS_JOBS_QUEUED	The requested operation is not allowed when there are jobs queued to the printer.
0x00000BC2 ERROR_SUCCESS_REBOOT_REQUIRED	The requested operation is successful. Changes will not be effective until the system is rebooted.

Win32 error codes	Description
0x00000BC3 ERROR_SUCCESS_RESTART_REQUIRED	The requested operation is successful. Changes will not be effective until the service is restarted.
0x00000BC4 ERROR_PRINTER_NOT_FOUND	No printers were found.
0x00000BC5 ERROR_PRINTER_DRIVER_WARNED	The printer driver is known to be unreliable.
0x00000BC6 ERROR_PRINTER_DRIVER_BLOCKED	The printer driver is known to harm the system.
0x00000BC7 ERROR_PRINTER_DRIVER_PACKAGE_IN_USE	The specified printer driver package is currently in use.
0x00000BC8 ERROR_CORE_DRIVER_PACKAGE_NOT_FOUND	Unable to find a core driver package that is required by the printer driver package.
0x00000BC9 ERROR_FAIL_REBOOT_REQUIRED	The requested operation failed. A system reboot is required to roll back changes made.
0x00000BCA ERROR_FAIL_REBOOT_INITIATED	The requested operation failed. A system reboot has been initiated to roll back changes made.
0x00000F6E ERROR_IO_REISSUE_AS_CACHED	Reissue the given operation as a cached I/O operation
0x00000FA0 ERROR_WINS_INTERNAL	Windows Internet Name Service (WINS) encountered an error while processing the command.
0x00000FA1 ERROR_CAN_NOT_DEL_LOCAL_WINS	The local WINS cannot be deleted.
0x00000FA2 ERROR_STATIC_INIT	The importation from the file failed.
0x00000FA3 ERROR_INC_BACKUP	The backup failed. Was a full backup done before?
0x00000FA4 ERROR_FULL_BACKUP	The backup failed. Check the directory to which you are backing the database.
0x00000FA5 ERROR_REC_NON_EXISTENT	The name does not exist in the WINS database.
0x00000FA6 ERROR_RPL_NOT_ALLOWED	Replication with a nonconfigured partner is not allowed.
0x00001004 ERROR_DHCP_ADDRESS_CONFLICT	The Dynamic Host Configuration Protocol (DHCP) client has obtained an IP address that is already in use on the network. The local interface will be disabled until the DHCP client can obtain a new address.
0x00001068	The GUID passed was not recognized as valid

Win32 error codes	Description
ERROR_WMI_GUID_NOT_FOUND	by a WMI data provider.
0x00001069 ERROR_WMI_INSTANCE_NOT_FOUND	The instance name passed was not recognized as valid by a WMI data provider.
0x0000106A ERROR_WMI_ITEMID_NOT_FOUND	The data item ID passed was not recognized as valid by a WMI data provider.
0x0000106B ERROR_WMI_TRY_AGAIN	The WMI request could not be completed and should be retried.
0x0000106C ERROR_WMI_DP_NOT_FOUND	The WMI data provider could not be located.
0x0000106D ERROR_WMI_UNRESOLVED_INSTANCE_REF	The WMI data provider references an instance set that has not been registered.
0x0000106E ERROR_WMI_ALREADY_ENABLED	The WMI data block or event notification has already been enabled.
0x0000106F ERROR_WMI_GUID_DISCONNECTED	The WMI data block is no longer available.
0x00001070 ERROR_WMI_SERVER_UNAVAILABLE	The WMI data service is not available.
0x00001071 ERROR_WMI_DP_FAILED	The WMI data provider failed to carry out the request.
0x00001072 ERROR_WMI_INVALID_MOF	The WMI Managed Object Format (MOF) information is not valid.
0x00001073 ERROR_WMI_INVALID_REGINFO	The WMI registration information is not valid.
0x00001074 ERROR_WMI_ALREADY_DISABLED	The WMI data block or event notification has already been disabled.
0x00001075 ERROR_WMI_READ_ONLY	The WMI data item or data block is read-only.
0x00001076 ERROR_WMI_SET_FAILURE	The WMI data item or data block could not be changed.
0x000010CC ERROR_INVALID_MEDIA	The media identifier does not represent a valid medium.
0x000010CD ERROR_INVALID_LIBRARY	The library identifier does not represent a valid library.
0x000010CE ERROR_INVALID_MEDIA_POOL	The media pool identifier does not represent a valid media pool.
0x000010CF ERROR_DRIVE_MEDIA_MISMATCH	The drive and medium are not compatible, or they exist in different libraries.
0x000010D0 ERROR_MEDIA_OFFLINE	The medium currently exists in an offline library and must be online to perform this

Win32 error codes	Description
	operation.
0x000010D1 ERROR_LIBRARY_OFFLINE	The operation cannot be performed on an offline library.
0x000010D2 ERROR_EMPTY	The library, drive, or media pool is empty.
0x000010D3 ERROR_NOT_EMPTY	The library, drive, or media pool must be empty to perform this operation.
0x000010D4 ERROR_MEDIA_UNAVAILABLE	No media is currently available in this media pool or library.
0x000010D5 ERROR_RESOURCE_DISABLED	A resource required for this operation is disabled.
0x000010D6 ERROR_INVALID_CLEANER	The media identifier does not represent a valid cleaner.
0x000010D7 ERROR_UNABLE_TO_CLEAN	The drive cannot be cleaned or does not support cleaning.
0x000010D8 ERROR_OBJECT_NOT_FOUND	The object identifier does not represent a valid object.
0x000010D9 ERROR_DATABASE_FAILURE	Unable to read from or write to the database.
0x000010DA ERROR_DATABASE_FULL	The database is full.
0x000010DB ERROR_MEDIA_INCOMPATIBLE	The medium is not compatible with the device or media pool.
0x000010DC ERROR_RESOURCE_NOT_PRESENT	The resource required for this operation does not exist.
0x000010DD ERROR_INVALID_OPERATION	The operation identifier is not valid.
0x000010DE ERROR_MEDIA_NOT_AVAILABLE	The media is not mounted or ready for use.
0x000010DF ERROR_DEVICE_NOT_AVAILABLE	The device is not ready for use.
0x000010E0 ERROR_REQUEST_REFUSED	The operator or administrator has refused the request.
0x000010E1 ERROR_INVALID_DRIVE_OBJECT	The drive identifier does not represent a valid drive.
0x000010E2 ERROR_LIBRARY_FULL	Library is full. No slot is available for use.
0x000010E3 ERROR_MEDIUM_NOT_ACCESSIBLE	The transport cannot access the medium.

Win32 error codes	Description
0x000010E4 ERROR_UNABLE_TO_LOAD_MEDIUM	Unable to load the medium into the drive.
0x000010E5 ERROR_UNABLE_TO_INVENTORY_DRIVE	Unable to retrieve the drive status.
0x000010E6 ERROR_UNABLE_TO_INVENTORY_SLOT	Unable to retrieve the slot status.
0x000010E7 ERROR_UNABLE_TO_INVENTORY_TRANSPORT	Unable to retrieve status about the transport.
0x000010E8 ERROR_TRANSPORT_FULL	Cannot use the transport because it is already in use.
0x000010E9 ERROR_CONTROLLING_IEPORT	Unable to open or close the inject/eject port.
0x000010EA ERROR_UNABLE_TO_EJECT_MOUNTED_MEDIA	Unable to eject the medium because it is in a drive.
0x000010EB ERROR_CLEANER_SLOT_SET	A cleaner slot is already reserved.
0x000010EC ERROR_CLEANER_SLOT_NOT_SET	A cleaner slot is not reserved.
0x000010ED ERROR_CLEANER_CARTRIDGE_SPENT	The cleaner cartridge has performed the maximum number of drive cleanings.
0x000010EE ERROR_UNEXPECTED_OMID	Unexpected on-medium identifier.
0x000010EF ERROR_CANT_DELETE_LAST_ITEM	The last remaining item in this group or resource cannot be deleted.
0x000010F0 ERROR_MESSAGE_EXCEEDS_MAX_SIZE	The message provided exceeds the maximum size allowed for this parameter.
0x000010F1 ERROR_VOLUME_CONTAINS_SYS_FILES	The volume contains system or paging files.
0x000010F2 ERROR_INDIGENOUS_TYPE	The media type cannot be removed from this library because at least one drive in the library reports it can support this media type.
0x000010F3 ERROR_NO_SUPPORTING_DRIVES	This offline media cannot be mounted on this system because no enabled drives are present that can be used.
0x000010F4 ERROR_CLEANER_CARTRIDGE_INSTALLED	A cleaner cartridge is present in the tape library.
0x000010F5 ERROR_IEPORT_FULL	Cannot use the IEport because it is not empty.
0x000010FE ERROR_FILE_OFFLINE	The remote storage service was not able to recall the file.

Win32 error codes	Description
0x000010FF ERROR_REMOTE_STORAGE_NOT_ACTIVE	The remote storage service is not operational at this time.
0x00001100 ERROR_REMOTE_STORAGE_MEDIA_ERROR	The remote storage service encountered a media error.
0x00001126 ERROR_NOT_A_REPARSE_POINT	The file or directory is not a reparse point.
0x00001127 ERROR_REPARSE_ATTRIBUTE_CONFLICT	The reparse point attribute cannot be set because it conflicts with an existing attribute.
0x00001128 ERROR_INVALID_REPARSE_DATA	The data present in the reparse point buffer is invalid.
0x00001129 ERROR_REPARSE_TAG_INVALID	The tag present in the reparse point buffer is invalid.
0x0000112A ERROR_REPARSE_TAG_MISMATCH	There is a mismatch between the tag specified in the request and the tag present in the reparse point.
0x00001194 ERROR_VOLUME_NOT_SIS_ENABLED	Single Instance Storage (SIS) is not available on this volume.
0x00001389 ERROR_DEPENDENT_RESOURCE_EXISTS	The operation cannot be completed because other resources depend on this resource.
0x0000138A ERROR_DEPENDENCY_NOT_FOUND	The cluster resource dependency cannot be found.
0x0000138B ERROR_DEPENDENCY_ALREADY_EXISTS	The cluster resource cannot be made dependent on the specified resource because it is already dependent.
0x0000138C ERROR_RESOURCE_NOT_ONLINE	The cluster resource is not online.
0x0000138D ERROR_HOST_NODE_NOT_AVAILABLE	A cluster node is not available for this operation.
0x0000138E ERROR_RESOURCE_NOT_AVAILABLE	The cluster resource is not available.
0x0000138F ERROR_RESOURCE_NOT_FOUND	The cluster resource could not be found.
0x00001390 ERROR_SHUTDOWN_CLUSTER	The cluster is being shut down.
0x00001391 ERROR_CANT_EVICT_ACTIVE_NODE	A cluster node cannot be evicted from the cluster unless the node is down or it is the last node.
0x00001392 ERROR_OBJECT_ALREADY_EXISTS	The object already exists.
0x00001393	The object is already in the list.



Win32 error codes	Description
ERROR_OBJECT_IN_LIST	
0x00001394 ERROR_GROUP_NOT_AVAILABLE	The cluster group is not available for any new requests.
0x00001395 ERROR_GROUP_NOT_FOUND	The cluster group could not be found.
0x00001396 ERROR_GROUP_NOT_ONLINE	The operation could not be completed because the cluster group is not online.
0x00001397 ERROR_HOST_NODE_NOT_RESOURCE_OWNER	The operation failed because either the specified cluster node is not the owner of the resource, or the node is not a possible owner of the resource.
0x00001398 ERROR_HOST_NODE_NOT_GROUP_OWNER	The operation failed because either the specified cluster node is not the owner of the group, or the node is not a possible owner of the group.
0x00001399 ERROR_RESMON_CREATE_FAILED	The cluster resource could not be created in the specified resource monitor.
0x0000139A ERROR_RESMON_ONLINE_FAILED	The cluster resource could not be brought online by the resource monitor.
0x0000139B ERROR_RESOURCE_ONLINE	The operation could not be completed because the cluster resource is online.
0x0000139C ERROR_QUORUM_RESOURCE	The cluster resource could not be deleted or brought offline because it is the quorum resource.
0x0000139D ERROR_NOT_QUORUM_CAPABLE	The cluster could not make the specified resource a quorum resource because it is not capable of being a quorum resource.
0x0000139E ERROR_CLUSTER_SHUTTING_DOWN	The cluster software is shutting down.
0x0000139F ERROR_INVALID_STATE	The group or resource is not in the correct state to perform the requested operation.
0x000013A0 ERROR_RESOURCE_PROPERTIES_STORED	The properties were stored but not all changes will take effect until the next time the resource is brought online.
0x000013A1 ERROR_NOT_QUORUM_CLASS	The cluster could not make the specified resource a quorum resource because it does not belong to a shared storage class.
0x000013A2 ERROR_CORE_RESOURCE	The cluster resource could not be deleted because it is a core resource.
0x000013A3 ERROR_QUORUM_RESOURCE_ONLINE_FAILED	The quorum resource failed to come online.

Win32 error codes	Description
0x000013A4 ERROR_QUORUMLOG_OPEN_FAILED	The quorum log could not be created or mounted successfully.
0x000013A5 ERROR_CLUSTERLOG_CORRUPT	The cluster log is corrupt.
0x000013A6 ERROR_CLUSTERLOG_RECORD_EXCEEDS_MAXSIZE	The record could not be written to the cluster log because it exceeds the maximum size.
0x000013A7 ERROR_CLUSTERLOG_EXCEEDS_MAXSIZE	The cluster log exceeds its maximum size.
0x000013A8 ERROR_CLUSTERLOG_CHKPOINT_NOT_FOUND	No checkpoint record was found in the cluster log.
0x000013A9 ERROR_CLUSTERLOG_NOT_ENOUGH_SPACE	The minimum required disk space needed for logging is not available.
0x000013AA ERROR_QUORUM_OWNER_ALIVE	The cluster node failed to take control of the quorum resource because the resource is owned by another active node.
0x000013AB ERROR_NETWORK_NOT_AVAILABLE	A cluster network is not available for this operation.
0x000013AC ERROR_NODE_NOT_AVAILABLE	A cluster node is not available for this operation.
0x000013AD ERROR_ALL_NODES_NOT_AVAILABLE	All cluster nodes must be running to perform this operation.
0x000013AE ERROR_RESOURCE_FAILED	A cluster resource failed.
0x000013AF ERROR_CLUSTER_INVALID_NODE	The cluster node is not valid.
0x000013B0 ERROR_CLUSTER_NODE_EXISTS	The cluster node already exists.
0x000013B1 ERROR_CLUSTER_JOIN_IN_PROGRESS	A node is in the process of joining the cluster.
0x000013B2 ERROR_CLUSTER_NODE_NOT_FOUND	The cluster node was not found.
0x000013B3 ERROR_CLUSTER_LOCAL_NODE_NOT_FOUND	The cluster local node information was not found.
0x000013B4 ERROR_CLUSTER_NETWORK_EXISTS	The cluster network already exists.
0x000013B5 ERROR_CLUSTER_NETWORK_NOT_FOUND	The cluster network was not found.
0x000013B6 ERROR_CLUSTER_NETINTERFACE_EXISTS	The cluster network interface already exists.

Win32 error codes	Description
0x000013B7 ERROR_CLUSTER_NETINTERFACE_NOT_FOUND	The cluster network interface was not found.
0x000013B8 ERROR_CLUSTER_INVALID_REQUEST	The cluster request is not valid for this object.
0x000013B9 ERROR_CLUSTER_INVALID_NETWORK_PROVIDER	The cluster network provider is not valid.
0x000013BA ERROR_CLUSTER_NODE_DOWN	The cluster node is down.
0x000013BB ERROR_CLUSTER_NODE_UNREACHABLE	The cluster node is not reachable.
0x000013BC ERROR_CLUSTER_NODE_NOT_MEMBER	The cluster node is not a member of the cluster.
0x000013BD ERROR_CLUSTER_JOIN_NOT_IN_PROGRESS	A cluster join operation is not in progress.
0x000013BE ERROR_CLUSTER_INVALID_NETWORK	The cluster network is not valid.
0x000013C0 ERROR_CLUSTER_NODE_UP	The cluster node is up.
0x000013C1 ERROR_CLUSTER_IPADDR_IN_USE	The cluster IP address is already in use.
0x000013C2 ERROR_CLUSTER_NODE_NOT_PAUSED	The cluster node is not paused.
0x000013C3 ERROR_CLUSTER_NO_SECURITY_CONTEXT	No cluster security context is available.
0x000013C4 ERROR_CLUSTER_NETWORK_NOT_INTERNAL	The cluster network is not configured for internal cluster communication.
0x000013C5 ERROR_CLUSTER_NODE_ALREADY_UP	The cluster node is already up.
0x000013C6 ERROR_CLUSTER_NODE_ALREADY_DOWN	The cluster node is already down.
0x000013C7 ERROR_CLUSTER_NETWORK_ALREADY_ONLINE	The cluster network is already online.
0x000013C8 ERROR_CLUSTER_NETWORK_ALREADY_OFFLINE	The cluster network is already offline.
0x000013C9 ERROR_CLUSTER_NODE_ALREADY_MEMBER	The cluster node is already a member of the cluster.
0x000013CA ERROR_CLUSTER_LAST_INTERNAL_NETWORK	The cluster network is the only one configured for internal cluster communication between two or more active cluster nodes. The internal communication capability cannot be removed

Win32 error codes	Description
	from the network.
0x000013CB ERROR_CLUSTER_NETWORK_HAS_DEPENDENTS	One or more cluster resources depend on the network to provide service to clients. The client access capability cannot be removed from the network.
0x000013CC ERROR_INVALID_OPERATION_ON_QUORUM	This operation cannot be performed on the cluster resource because it is the quorum resource. You may not bring the quorum resource offline or modify its possible owners list.
0x000013CD ERROR_DEPENDENCY_NOT_ALLOWED	The cluster quorum resource is not allowed to have any dependencies.
0x000013CE ERROR_CLUSTER_NODE_PAUSED	The cluster node is paused.
0x000013CF ERROR_NODE_CANT_HOST_RESOURCE	The cluster resource cannot be brought online. The owner node cannot run this resource.
0x000013D0 ERROR_CLUSTER_NODE_NOT_READY	The cluster node is not ready to perform the requested operation.
0x000013D1 ERROR_CLUSTER_NODE_SHUTTING_DOWN	The cluster node is shutting down.
0x000013D2 ERROR_CLUSTER_JOIN_ABORTED	The cluster join operation was aborted.
0x000013D3 ERROR_CLUSTER_INCOMPATIBLE_VERSIONS	The cluster join operation failed due to incompatible software versions between the joining node and its sponsor.
0x000013D4 ERROR_CLUSTER_MAXNUM_OF_RESOURCES_EXCEEDED	This resource cannot be created because the cluster has reached the limit on the number of resources it can monitor.
0x000013D5 ERROR_CLUSTER_SYSTEM_CONFIG_CHANGED	The system configuration changed during the cluster join or form operation. The join or form operation was aborted.
0x000013D6 ERROR_CLUSTER_RESOURCE_TYPE_NOT_FOUND	The specified resource type was not found.
0x000013D7 ERROR_CLUSTER_RESTYPE_NOT_SUPPORTED	The specified node does not support a resource of this type. This may be due to version inconsistencies or due to the absence of the resource DLL on this node.
0x000013D8 ERROR_CLUSTER_RESNAME_NOT_FOUND	The specified resource name is not supported by this resource DLL. This may be due to a bad (or changed) name supplied to the resource DLL.
0x000013D9 ERROR_CLUSTER_NO_RPC_PACKAGES_REGISTERED	No authentication package could be registered with the RPC server.

Win32 error codes	Description
0x000013DA ERROR_CLUSTER_OWNER_NOT_IN_PREFLIST	You cannot bring the group online because the owner of the group is not in the preferred list for the group. To change the owner node for the group, move the group.
0x000013DB ERROR_CLUSTER_DATABASE_SEQMISMATCH	The join operation failed because the cluster database sequence number has changed or is incompatible with the locker node. This may happen during a join operation if the cluster database was changing during the join.
0x000013DC ERROR_RESMON_INVALID_STATE	The resource monitor will not allow the fail operation to be performed while the resource is in its current state. This may happen if the resource is in a pending state.
0x000013DD ERROR_CLUSTER_GUM_NOT_LOCKER	A non-locker code received a request to reserve the lock for making global updates.
0x000013DE ERROR_QUORUM_DISK_NOT_FOUND	The quorum disk could not be located by the cluster service.
0x000013DF ERROR_DATABASE_BACKUP_CORRUPT	The backed-up cluster database is possibly corrupt.
0x000013E0 ERROR_CLUSTER_NODE_ALREADY_HAS_DFS_ROOT	A DFS root already exists in this cluster node.
0x000013E1 ERROR_RESOURCE_PROPERTY_UNCHANGEABLE	An attempt to modify a resource property failed because it conflicts with another existing property.
0x00001702 ERROR_CLUSTER_MEMBERSHIP_INVALID_STATE	An operation was attempted that is incompatible with the current membership state of the node.
0x00001703 ERROR_CLUSTER_QUORUMLOG_NOT_FOUND	The quorum resource does not contain the quorum log.
0x00001704 ERROR_CLUSTER_MEMBERSHIP_HALT	The membership engine requested shutdown of the cluster service on this node.
0x00001705 ERROR_CLUSTER_INSTANCE_ID_MISMATCH	The join operation failed because the cluster instance ID of the joining node does not match the cluster instance ID of the sponsor node.
0x00001706 ERROR_CLUSTER_NETWORK_NOT_FOUND_FOR_IP	A matching cluster network for the specified IP address could not be found.
0x00001707 ERROR_CLUSTER_PROPERTY_DATA_TYPE_MISMATCH	The actual data type of the property did not match the expected data type of the property.
0x00001708 ERROR_CLUSTER_EVICT_WITHOUT_CLEANUP	The cluster node was evicted from the cluster successfully, but the node was not cleaned up. To determine what clean-up steps failed and how to recover, see the Failover Clustering application event log using Event Viewer.

Win32 error codes	Description
0x00001709 ERROR_CLUSTER_PARAMETER_MISMATCH	Two or more parameter values specified for a resource's properties are in conflict.
0x0000170A ERROR_NODE_CANNOT_BE_CLUSTERED	This computer cannot be made a member of a cluster.
0x0000170B ERROR_CLUSTER_WRONG_OS_VERSION	This computer cannot be made a member of a cluster because it does not have the correct version of Windows installed.
0x0000170C ERROR_CLUSTER_CANT_CREATE_DUP_CLUSTER_NAME	A cluster cannot be created with the specified cluster name because that cluster name is already in use. Specify a different name for the cluster.
0x0000170D ERROR_CLUSCFG_ALREADY_COMMITTED	The cluster configuration action has already been committed.
0x0000170E ERROR_CLUSCFG_ROLLBACK_FAILED	The cluster configuration action could not be rolled back.
0x0000170F ERROR_CLUSCFG_SYSTEM_DISK_DRIVE_LETTER_CONFLICT	The drive letter assigned to a system disk on one node conflicted with the drive letter assigned to a disk on another node.
0x00001710 ERROR_CLUSTER_OLD_VERSION	One or more nodes in the cluster are running a version of Windows that does not support this operation.
0x00001711 ERROR_CLUSTER_MISMATCHED_COMPUTER_ACCT_NAME	The name of the corresponding computer account does not match the network name for this resource.
0x00001712 ERROR_CLUSTER_NO_NET_ADAPTERS	No network adapters are available.
0x00001713 ERROR_CLUSTER_POISONED	The cluster node has been poisoned.
0x00001714 ERROR_CLUSTER_GROUP_MOVING	The group is unable to accept the request because it is moving to another node.
0x00001715 ERROR_CLUSTER_RESOURCE_TYPE_BUSY	The resource type cannot accept the request because it is too busy performing another operation.
0x00001716 ERROR_RESOURCE_CALL_TIMED_OUT	The call to the cluster resource DLL timed out.
0x00001717 ERROR_INVALID_CLUSTER_IPV6_ADDRESS	The address is not valid for an IPv6 Address resource. A global IPv6 address is required, and it must match a cluster network. Compatibility addresses are not permitted.
0x00001718 ERROR_CLUSTER_INTERNAL_INVALID_FUNCTION	An internal cluster error occurred. A call to an invalid function was attempted.
0x00001719	A parameter value is out of acceptable range.

Win32 error codes	Description
ERROR_CLUSTER_PARAMETER_OUT_OF_BOUNDS	
0x0000171A ERROR_CLUSTER_PARTIAL_SEND	A network error occurred while sending data to another node in the cluster. The number of bytes transmitted was less than required.
0x0000171B ERROR_CLUSTER_REGISTRY_INVALID_FUNCTION	An invalid cluster registry operation was attempted.
0x0000171C ERROR_CLUSTER_INVALID_STRING_TERMINATION	An input string of characters is not properly terminated.
0x0000171D ERROR_CLUSTER_INVALID_STRING_FORMAT	An input string of characters is not in a valid format for the data it represents.
0x0000171E ERROR_CLUSTER_DATABASE_TRANSACTION_IN_PROGRESS	An internal cluster error occurred. A cluster database transaction was attempted while a transaction was already in progress.
0x0000171F ERROR_CLUSTER_DATABASE_TRANSACTION_NOT_IN_PROGRESS	An internal cluster error occurred. There was an attempt to commit a cluster database transaction while no transaction was in progress.
0x00001720 ERROR_CLUSTER_NULL_DATA	An internal cluster error occurred. Data was not properly initialized.
0x00001721 ERROR_CLUSTER_PARTIAL_READ	An error occurred while reading from a stream of data. An unexpected number of bytes was returned.
0x00001722 ERROR_CLUSTER_PARTIAL_WRITE	An error occurred while writing to a stream of data. The required number of bytes could not be written.
0x00001723 ERROR_CLUSTER_CANT_DESERIALIZE_DATA	An error occurred while deserializing a stream of cluster data.
0x00001724 ERROR_DEPENDENT_RESOURCE_PROPERTY_CONFLICT	One or more property values for this resource are in conflict with one or more property values associated with its dependent resources.
0x00001725 ERROR_CLUSTER_NO_QUORUM	A quorum of cluster nodes was not present to form a cluster.
0x00001726 ERROR_CLUSTER_INVALID_IPV6_NETWORK	The cluster network is not valid for an IPv6 address resource, or it does not match the configured address.
0x00001727 ERROR_CLUSTER_INVALID_IPV6_TUNNEL_NETWORK	The cluster network is not valid for an IPv6 tunnel resource. Check the configuration of the IP Address resource on which the IPv6 tunnel resource depends.
0x00001728 ERROR_QUORUM_NOT_ALLOWED_IN_THIS_GROUP	Quorum resource cannot reside in the available storage group.
0x00001770	The specified file could not be encrypted.

Win32 error codes	Description
ERROR_ENCRYPTION_FAILED	
0x00001771 ERROR_DECRYPTION_FAILED	The specified file could not be decrypted.
0x00001772 ERROR_FILE_ENCRYPTED	The specified file is encrypted and the user does not have the ability to decrypt it.
0x00001773 ERROR_NO_RECOVERY_POLICY	There is no valid encryption recovery policy configured for this system.
0x00001774 ERROR_NO_EFS	The required encryption driver is not loaded for this system.
0x00001775 ERROR_WRONG_EFS	The file was encrypted with a different encryption driver than is currently loaded.
0x00001776 ERROR_NO_USER_KEYS	There are no Encrypting File System (EFS) keys defined for the user.
0x00001777 ERROR_FILE_NOT_ENCRYPTED	The specified file is not encrypted.
0x00001778 ERROR_NOT_EXPORT_FORMAT	The specified file is not in the defined EFS export format.
0x00001779 ERROR_FILE_READ_ONLY	The specified file is read-only.
0x0000177A ERROR_DIR_EFS_DISALLOWED	The directory has been disabled for encryption.
0x0000177B ERROR_EFS_SERVER_NOT_TRUSTED	The server is not trusted for remote encryption operation.
0x0000177C ERROR_BAD_RECOVERY_POLICY	Recovery policy configured for this system contains invalid recovery certificate.
0x0000177D ERROR_EFS_ALG_BLOB_TOO_BIG	The encryption algorithm used on the source file needs a bigger key buffer than the one on the destination file.
0x0000177E ERROR_VOLUME_NOT_SUPPORT_EFS	The disk partition does not support file encryption.
0x0000177F ERROR_EFS_DISABLED	This machine is disabled for file encryption.
0x00001780 ERROR_EFS_VERSION_NOT_SUPPORT	A newer system is required to decrypt this encrypted file.
0x00001781 ERROR_CS_ENCRYPTION_INVALID_SERVER_RESPONSE	The remote server sent an invalid response for a file being opened with client-side encryption.
0x00001782 ERROR_CS_ENCRYPTION_UNSUPPORTED_SERVER	Client-side encryption is not supported by the remote server even though it claims to support it.



Win32 error codes	Description
0x00001783 ERROR_CS_ENCRYPTION_EXISTING_ENCRYPTED_FILE	File is encrypted and should be opened in client-side encryption mode.
0x00001784 ERROR_CS_ENCRYPTION_NEW_ENCRYPTED_FILE	A new encrypted file is being created and a \$EFS needs to be provided.
0x00001785 ERROR_CS_ENCRYPTION_FILE_NOT_CSE	The SMB client requested a client-side extension (CSE) file system control (FSCTL) on a non-CSE file.
0x000017E6 ERROR_NO_BROWSER_SERVERS_FOUND	The list of servers for this workgroup is not currently available
0x00001838 SCHED_E_SERVICE_NOT_LOCALSYSTEM	The Task Scheduler service must be configured to run in the System account to function properly. Individual tasks may be configured to run in other accounts.
0x000019C8 ERROR_LOG_SECTOR_INVALID	The log service encountered an invalid log sector.
0x000019C9 ERROR_LOG_SECTOR_PARITY_INVALID	The log service encountered a log sector with invalid block parity.
0x000019CA ERROR_LOG_SECTOR_REMAPPED	The log service encountered a remapped log sector.
0x000019CB ERROR_LOG_BLOCK_INCOMPLETE	The log service encountered a partial or incomplete log block.
0x000019CC ERROR_LOG_INVALID_RANGE	The log service encountered an attempt to access data outside the active log range.
0x000019CD ERROR_LOG_BLOCKS_EXHAUSTED	The log service user marshaling buffers are exhausted.
0x000019CE ERROR_LOG_READ_CONTEXT_INVALID	The log service encountered an attempt to read from a marshaling area with an invalid read context.
0x000019CF ERROR_LOG_RESTART_INVALID	The log service encountered an invalid log restart area.
0x000019D0 ERROR_LOG_BLOCK_VERSION	The log service encountered an invalid log block version.
0x000019D1 ERROR_LOG_BLOCK_INVALID	The log service encountered an invalid log block.
0x000019D2 ERROR_LOG_READ_MODE_INVALID	The log service encountered an attempt to read the log with an invalid read mode.
0x000019D3 ERROR_LOG_NO_RESTART	The log service encountered a log stream with no restart area.
0x000019D4 ERROR_LOG_METADATA_CORRUPT	The log service encountered a corrupted metadata file.

Win32 error codes	Description
0x000019D5 ERROR_LOG_METADATA_INVALID	The log service encountered a metadata file that could not be created by the log file system.
0x000019D6 ERROR_LOG_METADATA_INCONSISTENT	The log service encountered a metadata file with inconsistent data.
0x000019D7 ERROR_LOG_RESERVATION_INVALID	The log service encountered an attempt to erroneous allocate or dispose reservation space.
0x000019D8 ERROR_LOG_CANT_DELETE	The log service cannot delete a log file or file system container.
0x000019D9 ERROR_LOG_CONTAINER_LIMIT_EXCEEDED	The log service has reached the maximum allowable containers allocated to a log file.
0x000019DA ERROR_LOG_START_OF_LOG	The log service has attempted to read or write backward past the start of the log.
0x000019DB ERROR_LOG_POLICY_ALREADY_INSTALLED	The log policy could not be installed because a policy of the same type is already present.
0x000019DC ERROR_LOG_POLICY_NOT_INSTALLED	The log policy in question was not installed at the time of the request.
0x000019DD ERROR_LOG_POLICY_INVALID	The installed set of policies on the log is invalid.
0x000019DE ERROR_LOG_POLICY_CONFLICT	A policy on the log in question prevented the operation from completing.
0x000019DF ERROR_LOG_PINNED_ARCHIVE_TAIL	Log space cannot be reclaimed because the log is pinned by the archive tail.
0x000019E0 ERROR_LOG_RECORD_NONEXISTENT	The log record is not a record in the log file.
0x000019E1 ERROR_LOG_RECORDS_RESERVED_INVALID	The number of reserved log records or the adjustment of the number of reserved log records is invalid.
0x000019E2 ERROR_LOG_SPACE_RESERVED_INVALID	The reserved log space or the adjustment of the log space is invalid.
0x000019E3 ERROR_LOG_TAIL_INVALID	A new or existing archive tail or base of the active log is invalid.
0x000019E4 ERROR_LOG_FULL	The log space is exhausted.
0x000019E5 ERROR_COULD_NOT_RESIZE_LOG	The log could not be set to the requested size.
0x000019E6 ERROR_LOG_MULTIPLEXED	The log is multiplexed; no direct writes to the physical log are allowed.
0x000019E7	The operation failed because the log is a

Win32 error codes	Description
ERROR_LOG_DEDICATED	dedicated log.
0x000019E8 ERROR_LOG_ARCHIVE_NOT_IN_PROGRESS	The operation requires an archive context.
0x000019E9 ERROR_LOG_ARCHIVE_IN_PROGRESS	Log archival is in progress.
0x000019EA ERROR_LOG_EPHEMERAL	The operation requires a non-ephemeral log, but the log is ephemeral.
0x000019EB ERROR_LOG_NOT_ENOUGH_CONTAINERS	The log must have at least two containers before it can be read from or written to.
0x000019EC ERROR_LOG_CLIENT_ALREADY_REGISTERED	A log client has already registered on the stream.
0x000019ED ERROR_LOG_CLIENT_NOT_REGISTERED	A log client has not been registered on the stream.
0x000019EE ERROR_LOG_FULL_HANDLER_IN_PROGRESS	A request has already been made to handle the log full condition.
0x000019EF ERROR_LOG_CONTAINER_READ_FAILED	The log service encountered an error when attempting to read from a log container.
0x000019F0 ERROR_LOG_CONTAINER_WRITE_FAILED	The log service encountered an error when attempting to write to a log container.
0x000019F1 ERROR_LOG_CONTAINER_OPEN_FAILED	The log service encountered an error when attempting to open a log container.
0x000019F2 ERROR_LOG_CONTAINER_STATE_INVALID	The log service encountered an invalid container state when attempting a requested action.
0x000019F3 ERROR_LOG_STATE_INVALID	The log service is not in the correct state to perform a requested action.
0x000019F4 ERROR_LOG_PINNED	The log space cannot be reclaimed because the log is pinned.
0x000019F5 ERROR_LOG_METADATA_FLUSH_FAILED	The log metadata flush failed.
0x000019F6 ERROR_LOG_INCONSISTENT_SECURITY	Security on the log and its containers is inconsistent.
0x000019F7 ERROR_LOG_APPENDED_FLUSH_FAILED	Records were appended to the log or reservation changes were made, but the log could not be flushed.
0x000019F8 ERROR_LOG_PINNED_RESERVATION	The log is pinned due to reservation consuming most of the log space. Free some reserved records to make space available.
0x00001A2C ERROR_INVALID_TRANSACTION	The transaction handle associated with this operation is not valid.

Win32 error codes	Description
0x00001A2D ERROR_TRANSACTION_NOT_ACTIVE	The requested operation was made in the context of a transaction that is no longer active.
0x00001A2E ERROR_TRANSACTION_REQUEST_NOT_VALID	The requested operation is not valid on the transaction object in its current state.
0x00001A2F ERROR_TRANSACTION_NOT_REQUESTED	The caller has called a response API, but the response is not expected because the transaction manager did not issue the corresponding request to the caller.
0x00001A30 ERROR_TRANSACTION_ALREADY_ABORTED	It is too late to perform the requested operation because the transaction has already been aborted.
0x00001A31 ERROR_TRANSACTION_ALREADY_COMMITTED	It is too late to perform the requested operation because the transaction has already been committed.
0x00001A32 ERROR_TM_INITIALIZATION_FAILED	The transaction manager was unable to be successfully initialized. Transacted operations are not supported.
0x00001A33 ERROR_RESOURCEMANAGER_READ_ONLY	The specified resource manager made no changes or updates to the resource under this transaction.
0x00001A34 ERROR_TRANSACTION_NOT_JOINED	The resource manager has attempted to prepare a transaction that it has not successfully joined.
0x00001A35 ERROR_TRANSACTION_SUPERIOR_EXISTS	The transaction object already has a superior enlistment, and the caller attempted an operation that would have created a new superior. Only a single superior enlistment is allowed.
0x00001A36 ERROR_CRM_PROTOCOL_ALREADY_EXISTS	The resource manager tried to register a protocol that already exists.
0x00001A37 ERROR_TRANSACTION_PROPAGATION_FAILED	The attempt to propagate the transaction failed.
0x00001A38 ERROR_CRM_PROTOCOL_NOT_FOUND	The requested propagation protocol was not registered as a CRM.
0x00001A39 ERROR_TRANSACTION_INVALID_MARSHALL_BUFFER	The buffer passed in to PushTransaction or PullTransaction is not in a valid format.
0x00001A3A ERROR_CURRENT_TRANSACTION_NOT_VALID	The current transaction context associated with the thread is not a valid handle to a transaction object.
0x00001A3B ERROR_TRANSACTION_NOT_FOUND	The specified transaction object could not be opened because it was not found.
0x00001A3C	The specified resource manager object could

Win32 error codes	Description
ERROR_RESOURCEMANAGER_NOT_FOUND	not be opened because it was not found.
0x00001A3D ERROR_ENLISTMENT_NOT_FOUND	The specified enlistment object could not be opened because it was not found.
0x00001A3E ERROR_TRANSACTIONMANAGER_NOT_FOUND	The specified transaction manager object could not be opened because it was not found.
0x00001A3F ERROR_TRANSACTIONMANAGER_NOT_ONLINE	The specified resource manager was unable to create an enlistment because its associated transaction manager is not online.
0x00001A40 ERROR_TRANSACTIONMANAGER_RECOVERY_NAME_COLLISION	The specified transaction manager was unable to create the objects contained in its log file in the ObjectB namespace. Therefore, the transaction manager was unable to recover.
0x00001A90 ERROR_TRANSACTIONAL_CONFLICT	The function attempted to use a name that is reserved for use by another transaction.
0x00001A91 ERROR_RM_NOT_ACTIVE	Transaction support within the specified file system resource manager is not started or was shut down due to an error.
0x00001A92 ERROR_RM_METADATA_CORRUPT	The metadata of the resource manager has been corrupted. The resource manager will not function.
0x00001A93 ERROR_DIRECTORY_NOT_RM	The specified directory does not contain a resource manager.
0x00001A95 ERROR_TRANSACTIONS_UNSUPPORTED_REMOTE	The remote server or share does not support transacted file operations.
0x00001A96 ERROR_LOG_RESIZE_INVALID_SIZE	The requested log size is invalid.
0x00001A97 ERROR_OBJECT_NO_LONGER_EXISTS	The object (file, stream, link) corresponding to the handle has been deleted by a transaction savepoint rollback.
0x00001A98 ERROR_STREAM_MINIVERSION_NOT_FOUND	The specified file miniversion was not found for this transacted file open.
0x00001A99 ERROR_STREAM_MINIVERSION_NOT_VALID	The specified file miniversion was found but has been invalidated. The most likely cause is a transaction savepoint rollback.
0x00001A9A ERROR_MINIVERSION_INACCESSIBLE_FROM_SPECIFIED_TRANSACTION	A miniversion may only be opened in the context of the transaction that created it.
0x00001A9B ERROR_CANT_OPEN_MINIVERSION_WITH_MODIFY_INTENT	It is not possible to open a miniversion with modify access.
0x00001A9C ERROR_CANT_CREATE_MORE_STREAM_MINIVERSIONS	It is not possible to create any more miniversions for this stream.

Win32 error codes	Description
0x00001A9E ERROR_REMOTE_FILE_VERSION_MISMATCH	The remote server sent mismatching version numbers or FID for a file opened with transactions.
0x00001A9F ERROR_HANDLE_NO_LONGER_VALID	The handle has been invalidated by a transaction. The most likely cause is the presence of memory mapping on a file, or an open handle when the transaction ended or rolled back to savepoint.
0x00001AA0 ERROR_NO_TXF_METADATA	There is no transaction metadata on the file.
0x00001AA1 ERROR_LOG_CORRUPTION_DETECTED	The log data is corrupt.
0x00001AA2 ERROR_CANT_RECOVER_WITH_HANDLE_OPEN	The file cannot be recovered because a handle is still open on it.
0x00001AA3 ERROR_RM_DISCONNECTED	The transaction outcome is unavailable because the resource manager responsible for it is disconnected.
0x00001AA4 ERROR_ENLISTMENT_NOT_SUPERIOR	The request was rejected because the enlistment in question is not a superior enlistment.
0x00001AA5 ERROR_RECOVERY_NOT_NEEDED	The transactional resource manager is already consistent. Recovery is not needed.
0x00001AA6 ERROR_RM_ALREADY_STARTED	The transactional resource manager has already been started.
0x00001AA7 ERROR_FILE_IDENTITY_NOT_PERSISTENT	The file cannot be opened in a transaction because its identity depends on the outcome of an unresolved transaction.
0x00001AA8 ERROR_CANT_BREAK_TRANSACTIONAL_DEPENDENCY	The operation cannot be performed because another transaction is depending on the fact that this property will not change.
0x00001AA9 ERROR_CANT_CROSS_RM_BOUNDARY	The operation would involve a single file with two transactional resource managers and is therefore not allowed.
0x00001AAA ERROR_TXF_DIR_NOT_EMPTY	The \$Txf directory must be empty for this operation to succeed.
0x00001AAB ERROR_INDOUBT_TRANSACTIONS_EXIST	The operation would leave a transactional resource manager in an inconsistent state and is, therefore, not allowed.
0x00001AAC ERROR_TM_VOLATILE	The operation could not be completed because the transaction manager does not have a log.
0x00001AAD ERROR_ROLLBACK_TIMER_EXPIRED	A rollback could not be scheduled because a previously scheduled rollback has already been executed or is queued for execution.

Win32 error codes	Description
0x00001AAE ERROR_TXF_ATTRIBUTE_CORRUPT	The transactional metadata attribute on the file or directory is corrupt and unreadable.
0x00001AAF ERROR_EFS_NOT_ALLOWED_IN_TRANSACTION	The encryption operation could not be completed because a transaction is active.
0x00001AB0 ERROR_TRANSACTIONAL_OPEN_NOT_ALLOWED	This object is not allowed to be opened in a transaction.
0x00001AB1 ERROR_LOG_GROWTH_FAILED	An attempt to create space in the transactional resource manager's log failed. The failure status has been recorded in the event log.
0x00001AB2 ERROR_TRANSACTED_MAPPING_UNSUPPORTED_REMOTE	Memory mapping (creating a mapped section) to a remote file under a transaction is not supported.
0x00001AB3 ERROR_TXF_METADATA_ALREADY_PRESENT	Transaction metadata is already present on this file and cannot be superseded.
0x00001AB4 ERROR_TRANSACTION_SCOPE_CALLBACKS_NOT_SET	A transaction scope could not be entered because the scope handler has not been initialized.
0x00001AB5 ERROR_TRANSACTION_REQUIRED_PROMOTION	Promotion was required to allow the resource manager to enlist, but the transaction was set to disallow it.
0x00001AB6 ERROR_CANNOT_EXECUTE_FILE_IN_TRANSACTION	This file is open for modification in an unresolved transaction and may be opened for execution only by a transacted reader.
0x00001AB7 ERROR_TRANSACTIONS_NOT_FROZEN	The request to thaw frozen transactions was ignored because transactions were not previously frozen.
0x00001AB8 ERROR_TRANSACTION_FREEZE_IN_PROGRESS	Transactions cannot be frozen because a freeze is already in progress.
0x00001AB9 ERROR_NOT_SNAPSHOT_VOLUME	The target volume is not a snapshot volume. This operation is only valid on a volume mounted as a snapshot.
0x00001ABA ERROR_NO_SAVEPOINT_WITH_OPEN_FILES	The savepoint operation failed because files are open on the transaction. This is not permitted.
0x00001ABB ERROR_DATA_LOST_REPAIR	Windows has discovered corruption in a file, and that file has since been repaired. Data loss may have occurred.
0x00001ABC ERROR_SPARSE_NOT_ALLOWED_IN_TRANSACTION	The sparse operation could not be completed because a transaction is active on the file.
0x00001ABD ERROR_TM_IDENTITY_MISMATCH	The call to create a transaction manager object failed because the Tm Identity stored in the logfile does not match the Tm Identity that was passed in as an argument.

Win32 error codes	Description
0x00001ABE ERROR_FLOATED_SECTION	I/O was attempted on a section object that has been floated as a result of a transaction ending. There is no valid data.
0x00001ABF ERROR_CANNOT_ACCEPT_TRANSACTED_WORK	The transactional resource manager cannot currently accept transacted work due to a transient condition, such as low resources.
0x00001AC0 ERROR_CANNOT_ABORT_TRANSACTIONS	The transactional resource manager had too many transactions outstanding that could not be aborted. The transactional resource manager has been shut down.
0x00001B59 ERROR_CTX_WINSTATION_NAME_INVALID	The specified session name is invalid.
0x00001B5A ERROR_CTX_INVALID_PD	The specified protocol driver is invalid.
0x00001B5B ERROR_CTX_PD_NOT_FOUND	The specified protocol driver was not found in the system path.
0x00001B5C ERROR_CTX_WD_NOT_FOUND	The specified terminal connection driver was not found in the system path.
0x00001B5D ERROR_CTX_CANNOT_MAKE_EVENTLOG_ENTRY	A registry key for event logging could not be created for this session.
0x00001B5E ERROR_CTX_SERVICE_NAME_COLLISION	A service with the same name already exists on the system.
0x00001B5F ERROR_CTX_CLOSE_PENDING	A close operation is pending on the session.
0x00001B60 ERROR_CTX_NO_OUTBUF	There are no free output buffers available.
0x00001B61 ERROR_CTX_MODEM_INF_NOT_FOUND	The MODEM.INF file was not found.
0x00001B62 ERROR_CTX_INVALID_MODEMNAME	The modem name was not found in the MODEM.INF file.
0x00001B63 ERROR_CTX_MODEM_RESPONSE_ERROR	The modem did not accept the command sent to it. Verify that the configured modem name matches the attached modem.
0x00001B64 ERROR_CTX_MODEM_RESPONSE_TIMEOUT	The modem did not respond to the command sent to it. Verify that the modem is properly cabled and turned on.
0x00001B65 ERROR_CTX_MODEM_RESPONSE_NO_CARRIER	Carrier detect has failed or carrier has been dropped due to disconnect.
0x00001B66 ERROR_CTX_MODEM_RESPONSE_NO_DIALTONE	Dial tone not detected within the required time. Verify that the phone cable is properly attached and functional.



Win32 error codes	Description
0x00001B67 ERROR_CTX_MODEM_RESPONSE_BUSY	Busy signal detected at remote site on callback.
0x00001B68 ERROR_CTX_MODEM_RESPONSE_VOICE	Voice detected at remote site on callback.
0x00001B69 ERROR_CTX_TD_ERROR	Transport driver error
0x00001B6E ERROR_CTX_WINSTATION_NOT_FOUND	The specified session cannot be found.
0x00001B6F ERROR_CTX_WINSTATION_ALREADY_EXISTS	The specified session name is already in use.
0x00001B70 ERROR_CTX_WINSTATION_BUSY	The requested operation cannot be completed because the terminal connection is currently busy processing a connect, disconnect, reset, or delete operation.
0x00001B71 ERROR_CTX_BAD_VIDEO_MODE	An attempt has been made to connect to a session whose video mode is not supported by the current client.
0x00001B7B ERROR_CTX_GRAPHICS_INVALID	The application attempted to enable DOS graphics mode. DOS graphics mode is not supported.
0x00001B7D ERROR_CTX_LOGON_DISABLED	Your interactive logon privilege has been disabled. Contact your administrator.
0x00001B7E ERROR_CTX_NOT_CONSOLE	The requested operation can be performed only on the system console. This is most often the result of a driver or system DLL requiring direct console access.
0x00001B80 ERROR_CTX_CLIENT_QUERY_TIMEOUT	The client failed to respond to the server connect message.
0x00001B81 ERROR_CTX_CONSOLE_DISCONNECT	Disconnecting the console session is not supported.
0x00001B82 ERROR_CTX_CONSOLE_CONNECT	Reconnecting a disconnected session to the console is not supported.
0x00001B84 ERROR_CTX_SHADOW_DENIED	The request to control another session remotely was denied.
0x00001B85 ERROR_CTX_WINSTATION_ACCESS_DENIED	The requested session access is denied.
0x00001B89 ERROR_CTX_INVALID_WD	The specified terminal connection driver is invalid.
0x00001B8A ERROR_CTX_SHADOW_INVALID	The requested session cannot be controlled remotely. This may be because the session is disconnected or does not currently have a user logged on.

Win32 error codes	Description
0x00001B8B ERROR_CTX_SHADOW_DISABLED	The requested session is not configured to allow remote control.
0x00001B8C ERROR_CTX_CLIENT_LICENSE_IN_USE	Your request to connect to this terminal server has been rejected. Your terminal server client license number is currently being used by another user. Call your system administrator to obtain a unique license number.
0x00001B8D ERROR_CTX_CLIENT_LICENSE_NOT_SET	Your request to connect to this terminal server has been rejected. Your terminal server client license number has not been entered for this copy of the terminal server client. Contact your system administrator.
0x00001B8E ERROR_CTX_LICENSE_NOT_AVAILABLE	The number of connections to this computer is limited and all connections are in use right now. Try connecting later or contact your system administrator.
0x00001B8F ERROR_CTX_LICENSE_CLIENT_INVALID	The client you are using is not licensed to use this system. Your logon request is denied.
0x00001B90 ERROR_CTX_LICENSE_EXPIRED	The system license has expired. Your logon request is denied.
0x00001B91 ERROR_CTX_SHADOW_NOT_RUNNING	Remote control could not be terminated because the specified session is not currently being remotely controlled.
0x00001B92 ERROR_CTX_SHADOW_ENDED_BY_MODE_CHANGE	The remote control of the console was terminated because the display mode was changed. Changing the display mode in a remote control session is not supported.
0x00001B93 ERROR_ACTIVATION_COUNT_EXCEEDED	Activation has already been reset the maximum number of times for this installation. Your activation timer will not be cleared.
0x00001B94 ERROR_CTX_WINSTATIONS_DISABLED	Remote logons are currently disabled.
0x00001B95 ERROR_CTX_ENCRYPTION_LEVEL_REQUIRED	You do not have the proper encryption level to access this session.
0x00001B96 ERROR_CTX_SESSION_IN_USE	The user %s\\%s is currently logged on to this computer. Only the current user or an administrator can log on to this computer.
0x00001B97 ERROR_CTX_NO_FORCE_LOGOFF	The user %s\\%s is already logged on to the console of this computer. You do not have permission to log in at this time. To resolve this issue, contact %s\\%s and have them log off.
0x00001B98 ERROR_CTX_ACCOUNT_RESTRICTION	Unable to log you on because of an account restriction.
0x00001B99	The RDP component %2 detected an error in

Win32 error codes	Description
ERROR_RDP_PROTOCOL_ERROR	the protocol stream and has disconnected the client.
0x00001B9A ERROR_CTX_CDM_CONNECT	The Client Drive Mapping Service has connected on terminal connection.
0x00001B9B ERROR_CTX_CDM_DISCONNECT	The Client Drive Mapping Service has disconnected on terminal connection.
0x00001B9C ERROR_CTX_SECURITY_LAYER_ERROR	The terminal server security layer detected an error in the protocol stream and has disconnected the client.
0x00001B9D ERROR_TS_INCOMPATIBLE_SESSIONS	The target session is incompatible with the current session.
0x00001F41 FRS_ERR_INVALID_API_SEQUENCE	The file replication service API was called incorrectly.
0x00001F42 FRS_ERR_STARTING_SERVICE	The file replication service cannot be started.
0x00001F43 FRS_ERR_STOPPING_SERVICE	The file replication service cannot be stopped.
0x00001F44 FRS_ERR_INTERNAL_API	The file replication service API terminated the request. The event log may have more information.
0x00001F45 FRS_ERR_INTERNAL	The file replication service terminated the request. The event log may have more information.
0x00001F46 FRS_ERR_SERVICE_COMM	The file replication service cannot be contacted. The event log may have more information.
0x00001F47 FRS_ERR_INSUFFICIENT_PRIV	The file replication service cannot satisfy the request because the user has insufficient privileges. The event log may have more information.
0x00001F48 FRS_ERR_AUTHENTICATION	The file replication service cannot satisfy the request because authenticated RPC is not available. The event log may have more information.
0x00001F49 FRS_ERR_PARENT_INSUFFICIENT_PRIV	The file replication service cannot satisfy the request because the user has insufficient privileges on the domain controller. The event log may have more information.
0x00001F4A FRS_ERR_PARENT_AUTHENTICATION	The file replication service cannot satisfy the request because authenticated RPC is not available on the domain controller. The event log may have more information.
0x00001F4B FRS_ERR_CHILD_TO_PARENT_COMM	The file replication service cannot communicate with the file replication service on the domain

Win32 error codes	Description
	controller. The event log may have more information.
0x00001F4C FRS_ERR_PARENT_TO_CHILD_COMM	The file replication service on the domain controller cannot communicate with the file replication service on this computer. The event log may have more information.
0x00001F4D FRS_ERR_SYSVOL_POPULATE	The file replication service cannot populate the system volume because of an internal error. The event log may have more information.
0x00001F4E FRS_ERR_SYSVOL_POPULATE_TIMEOUT	The file replication service cannot populate the system volume because of an internal timeout. The event log may have more information.
0x00001F4F FRS_ERR_SYSVOL_IS_BUSY	The file replication service cannot process the request. The system volume is busy with a previous request.
0x00001F50 FRS_ERR_SYSVOL_DEMOTE	The file replication service cannot stop replicating the system volume because of an internal error. The event log may have more information.
0x00001F51 FRS_ERR_INVALID_SERVICE_PARAMETER	The file replication service detected an invalid parameter.
0x00002008 ERROR_DS_NOT_INSTALLED	An error occurred while installing the directory service. For more information, see the event log.
0x00002009 ERROR_DS_MEMBERSHIP_EVALUATED_LOCALLY	The directory service evaluated group memberships locally.
0x0000200A ERROR_DS_NO_ATTRIBUTE_OR_VALUE	The specified directory service attribute or value does not exist.
0x0000200B ERROR_DS_INVALID_ATTRIBUTE_YNTAX	The attribute syntax specified to the directory service is invalid.
0x0000200C ERROR_DS_ATTRIBUTE_TYPE_UNDEFINED	The attribute type specified to the directory service is not defined.
0x0000200D ERROR_DS_ATTRIBUTE_OR_VALUE_EXISTS	The specified directory service attribute or value already exists.
0x0000200E ERROR_DS_BUSY	The directory service is busy.
0x0000200F ERROR_DS_UNAVAILABLE	The directory service is unavailable.
0x00002010 ERROR_DS_NO_RIDS_ALLOCATED	The directory service was unable to allocate a relative identifier.
0x00002011 ERROR_DS_NO_MORE_RIDS	The directory service has exhausted the pool of relative identifiers.

Win32 error codes	Description
0x00002012 ERROR_DS_INCORRECT_ROLE_OWNER	The requested operation could not be performed because the directory service is not the master for that type of operation.
0x00002013 ERROR_DS_RIDMGR_INIT_ERROR	The directory service was unable to initialize the subsystem that allocates relative identifiers.
0x00002014 ERROR_DS_OBJ_CLASS_VIOLATION	The requested operation did not satisfy one or more constraints associated with the class of the object.
0x00002015 ERROR_DS_CANT_ON_NON_LEAF	The directory service can perform the requested operation only on a leaf object.
0x00002016 ERROR_DS_CANT_ON_RDN	The directory service cannot perform the requested operation on the relative distinguished name (RDN) attribute of an object.
0x00002017 ERROR_DS_CANT_MOD_OBJ_CLASS	The directory service detected an attempt to modify the object class of an object.
0x00002018 ERROR_DS_CROSS_DOM_MOVE_ERROR	The requested cross-domain move operation could not be performed.
0x00002019 ERROR_DS_GC_NOT_AVAILABLE	Unable to contact the global catalog (GC) server.
0x0000201A ERROR_SHARED_POLICY	The policy object is shared and can only be modified at the root.
0x0000201B ERROR_POLICY_OBJECT_NOT_FOUND	The policy object does not exist.
0x0000201C ERROR_POLICY_ONLY_IN_DS	The requested policy information is only in the directory service.
0x0000201D ERROR_PROMOTION_ACTIVE	A domain controller promotion is currently active.
0x0000201E ERROR_NO_PROMOTION_ACTIVE	A domain controller promotion is not currently active.
0x00002020 ERROR_DS_OPERATIONS_ERROR	An operations error occurred.
0x00002021 ERROR_DS_PROTOCOL_ERROR	A protocol error occurred.
0x00002022 ERROR_DS_TIMELIMIT_EXCEEDED	The time limit for this request was exceeded.
0x00002023 ERROR_DS_SIZELIMIT_EXCEEDED	The size limit for this request was exceeded.
0x00002024 ERROR_DS_ADMIN_LIMIT_EXCEEDED	The administrative limit for this request was exceeded.

Win32 error codes	Description
0x00002025 ERROR_DS_COMPARE_FALSE	The compare response was false.
0x00002026 ERROR_DS_COMPARE_TRUE	The compare response was true.
0x00002027 ERROR_DS_AUTH_METHOD_NOT_SUPPORTED	The requested authentication method is not supported by the server.
0x00002028 ERROR_DS_STRONG_AUTH_REQUIRED	A more secure authentication method is required for this server.
0x00002029 ERROR_DS_INAPPROPRIATE_AUTH	Inappropriate authentication.
0x0000202A ERROR_DS_AUTH_UNKNOWN	The authentication mechanism is unknown.
0x0000202B ERROR_DS_REFERRAL	A referral was returned from the server.
0x0000202C ERROR_DS_UNAVAILABLE_CRIT_EXTENSION	The server does not support the requested critical extension.
0x0000202D ERROR_DS_CONFIDENTIALITY_REQUIRED	This request requires a secure connection.
0x0000202E ERROR_DS_INAPPROPRIATE_MATCHING	Inappropriate matching.
0x0000202F ERROR_DS_CONSTRAINT_VIOLATION	A constraint violation occurred.
0x00002030 ERROR_DS_NO_SUCH_OBJECT	There is no such object on the server.
0x00002031 ERROR_DS_ALIAS_PROBLEM	There is an alias problem.
0x00002032 ERROR_DS_INVALID_DN_SYNTAX	An invalid dn syntax has been specified.
0x00002033 ERROR_DS_IS_LEAF	The object is a leaf object.
0x00002034 ERROR_DS_ALIAS_DEREF_PROBLEM	There is an alias dereferencing problem.
0x00002035 ERROR_DS_UNWILLING_TO_PERFORM	The server is unwilling to process the request.
0x00002036 ERROR_DS_LOOP_DETECT	A loop has been detected.
0x00002037 ERROR_DS_NAMING_VIOLATION	There is a naming violation.
0x00002038	The result set is too large.

Win32 error codes	Description
ERROR_DS_OBJECT_RESULTS_TOO_LARGE	
0x00002039 ERROR_DS_AFFECTS_MULTIPLE_DSAS	The operation affects multiple DSAs.
0x0000203A ERROR_DS_SERVER_DOWN	The server is not operational.
0x0000203B ERROR_DS_LOCAL_ERROR	A local error has occurred.
0x0000203C ERROR_DS_ENCODING_ERROR	An encoding error has occurred.
0x0000203D ERROR_DS_DECODING_ERROR	A decoding error has occurred.
0x0000203E ERROR_DS_FILTER_UNKNOWN	The search filter cannot be recognized.
0x0000203F ERROR_DS_PARAM_ERROR	One or more parameters are illegal.
0x00002040 ERROR_DS_NOT_SUPPORTED	The specified method is not supported.
0x00002041 ERROR_DS_NO_RESULTS_RETURNED	No results were returned.
0x00002042 ERROR_DS_CONTROL_NOT_FOUND	The specified control is not supported by the server.
0x00002043 ERROR_DS_CLIENT_LOOP	A referral loop was detected by the client.
0x00002044 ERROR_DS_REFERRAL_LIMIT_EXCEEDED	The preset referral limit was exceeded.
0x00002045 ERROR_DS_SORT_CONTROL_MISSING	The search requires a SORT control.
0x00002046 ERROR_DS_OFFSET_RANGE_ERROR	The search results exceed the offset range specified.
0x0000206D ERROR_DS_ROOT_MUST_BE_NC	The root object must be the head of a naming context. The root object cannot have an instantiated parent.
0x0000206E ERROR_DS_ADD_REPLICA_INHIBITED	The add replica operation cannot be performed. The naming context must be writable to create the replica.
0x0000206F ERROR_DS_ATT_NOT_DEF_IN_SCHEMA	A reference to an attribute that is not defined in the schema occurred.
0x00002070 ERROR_DS_MAX_OBJ_SIZE_EXCEEDED	The maximum size of an object has been exceeded.

Win32 error codes	Description
0x00002071 ERROR_DS_OBJ_STRING_NAME_EXISTS	An attempt was made to add an object to the directory with a name that is already in use.
0x00002072 ERROR_DS_NO_RDN_DEFINED_IN_SCHEMA	An attempt was made to add an object of a class that does not have an RDN defined in the schema.
0x00002073 ERROR_DS_RDN_DOESNT_MATCH_SCHEMA	An attempt was made to add an object using an RDN that is not the RDN defined in the schema.
0x00002074 ERROR_DS_NO_REQUESTED_ATTRS_FOUND	None of the requested attributes were found on the objects.
0x00002075 ERROR_DS_USER_BUFFER_TOO_SMALL	The user buffer is too small.
0x00002076 ERROR_DS_ATT_IS_NOT_ON_OBJ	The attribute specified in the operation is not present on the object.
0x00002077 ERROR_DS_ILLEGAL_MOD_OPERATION	Illegal modify operation. Some aspect of the modification is not permitted.
0x00002078 ERROR_DS_OBJ_TOO_LARGE	The specified object is too large.
0x00002079 ERROR_DS_BAD_INSTANCE_TYPE	The specified instance type is not valid.
0x0000207A ERROR_DS_MASTERDSA_REQUIRED	The operation must be performed at a master DSA.
0x0000207B ERROR_DS_OBJECT_CLASS_REQUIRED	The object class attribute must be specified.
0x0000207C ERROR_DS_MISSING_REQUIRED_ATT	A required attribute is missing.
0x0000207D ERROR_DS_ATT_NOT_DEF_FOR_CLASS	An attempt was made to modify an object to include an attribute that is not legal for its class.
0x0000207E ERROR_DS_ATT_ALREADY_EXISTS	The specified attribute is already present on the object.
0x00002080 ERROR_DS_CANT_ADD_ATT_VALUES	The specified attribute is not present, or has no values.
0x00002081 ERROR_DS_SINGLE_VALUE_CONSTRAINT	Multiple values were specified for an attribute that can have only one value.
0x00002082 ERROR_DS_RANGE_CONSTRAINT	A value for the attribute was not in the acceptable range of values.
0x00002083 ERROR_DS_ATT_VAL_ALREADY_EXISTS	The specified value already exists.
0x00002084	The attribute cannot be removed because it is



Win32 error codes	Description
ERROR_DS_CANT_REM_MISSING_ATT	not present on the object.
0x00002085 ERROR_DS_CANT_REM_MISSING_ATT_VAL	The attribute value cannot be removed because it is not present on the object.
0x00002086 ERROR_DS_ROOT_CANT_BE_SUBREF	The specified root object cannot be a subreference.
0x00002087 ERROR_DS_NO_CHAINING	Chaining is not permitted.
0x00002088 ERROR_DS_NO_CHAINED_EVAL	Chained evaluation is not permitted.
0x00002089 ERROR_DS_NO_PARENT_OBJECT	The operation could not be performed because the object's parent is either uninstantiated or deleted.
0x0000208A ERROR_DS_PARENT_IS_AN_ALIAS	Having a parent that is an alias is not permitted. Aliases are leaf objects.
0x0000208B ERROR_DS_CANT_MIX_MASTER_AND_REPS	The object and parent must be of the same type, either both masters or both replicas.
0x0000208C ERROR_DS_CHILDREN_EXIST	The operation cannot be performed because child objects exist. This operation can only be performed on a leaf object.
0x0000208D ERROR_DS_OBJ_NOT_FOUND	Directory object not found.
0x0000208E ERROR_DS_ALIASED_OBJ_MISSING	The aliased object is missing.
0x0000208F ERROR_DS_BAD_NAME_SYNTAX	The object name has bad syntax.
0x00002090 ERROR_DS_ALIAS_POINTS_TO_ALIAS	An alias is not permitted to refer to another alias.
0x00002091 ERROR_DS_CANT_DEREF_ALIAS	The alias cannot be dereferenced.
0x00002092 ERROR_DS_OUT_OF_SCOPE	The operation is out of scope.
0x00002093 ERROR_DS_OBJECT_BEING_REMOVED	The operation cannot continue because the object is in the process of being removed.
0x00002094 ERROR_DS_CANT_DELETE_DSA_OBJ	The DSA object cannot be deleted.
0x00002095 ERROR_DS_GENERIC_ERROR	A directory service error has occurred.
0x00002096 ERROR_DS_DSA_MUST_BE_INT_MASTER	The operation can only be performed on an internal master DSA object.

Win32 error codes	Description
0x00002097 ERROR_DS_CLASS_NOT_DSA	The object must be of class DSA.
0x00002098 ERROR_DS_INSUFF_ACCESS_RIGHTS	Insufficient access rights to perform the operation.
0x00002099 ERROR_DS_ILLEGAL_SUPERIOR	The object cannot be added because the parent is not on the list of possible superiors.
0x0000209A ERROR_DS_ATTRIBUTE_OWNED_BY_SAM	Access to the attribute is not permitted because the attribute is owned by the SAM.
0x0000209B ERROR_DS_NAME_TOO_MANY_PARTS	The name has too many parts.
0x0000209C ERROR_DS_NAME_TOO_LONG	The name is too long.
0x0000209D ERROR_DS_NAME_VALUE_TOO_LONG	The name value is too long.
0x0000209E ERROR_DS_NAME_UNPARSEABLE	The directory service encountered an error parsing a name.
0x0000209F ERROR_DS_NAME_TYPE_UNKNOWN	The directory service cannot get the attribute type for a name.
0x000020A0 ERROR_DS_NOT_AN_OBJECT	The name does not identify an object; the name identifies a phantom.
0x000020A1 ERROR_DS_SEC_DESC_TOO_SHORT	The security descriptor is too short.
0x000020A2 ERROR_DS_SEC_DESC_INVALID	The security descriptor is invalid.
0x000020A3 ERROR_DS_NO_DELETED_NAME	Failed to create name for deleted object.
0x000020A4 ERROR_DS_SUBREF_MUST_HAVE_PARENT	The parent of a new subreference must exist.
0x000020A5 ERROR_DS_NCNAME_MUST_BE_NC	The object must be a naming context.
0x000020A6 ERROR_DS_CANT_ADD_SYSTEM_ONLY	It is not permitted to add an attribute that is owned by the system.
0x000020A7 ERROR_DS_CLASS_MUST_BE_CONCRETE	The class of the object must be structural; you cannot instantiate an abstract class.
0x000020A8 ERROR_DS_INVALID_DMD	The schema object could not be found.
0x000020A9 ERROR_DS_OBJ_GUID_EXISTS	A local object with this GUID (dead or alive) already exists.
0x000020AA	The operation cannot be performed on a back

Win32 error codes	Description
ERROR_DS_NOT_ON_BACKLINK	link.
0x000020AB ERROR_DS_NO_CROSSREF_FOR_NC	The cross-reference for the specified naming context could not be found.
0x000020AC ERROR_DS_SHUTTING_DOWN	The operation could not be performed because the directory service is shutting down.
0x000020AD ERROR_DS_UNKNOWN_OPERATION	The directory service request is invalid.
0x000020AE ERROR_DS_INVALID_ROLE_OWNER	The role owner attribute could not be read.
0x000020AF ERROR_DS_COULDNT_CONTACT_FSMO	The requested Flexible Single Master Operations (FSMO) operation failed. The current FSMO holder could not be contacted.
0x000020B0 ERROR_DS_CROSS_NC_DN_RENAME	Modification of a distinguished name across a naming context is not permitted.
0x000020B1 ERROR_DS_CANT_MOD_SYSTEM_ONLY	The attribute cannot be modified because it is owned by the system.
0x000020B2 ERROR_DS_REPLICATOR_ONLY	Only the replicator can perform this function.
0x000020B3 ERROR_DS_OBJ_CLASS_NOT_DEFINED	The specified class is not defined.
0x000020B4 ERROR_DS_OBJ_CLASS_NOT_SUBCLASS	The specified class is not a subclass.
0x000020B5 ERROR_DS_NAME_REFERENCE_INVALID	The name reference is invalid.
0x000020B6 ERROR_DS_CROSS_REF_EXISTS	A cross-reference already exists.
0x000020B7 ERROR_DS_CANT_DEL_MASTER_CROSSREF	It is not permitted to delete a master cross-reference.
0x000020B8 ERROR_DS_SUBTREE_NOTIFY_NOT_NC_HEAD	Subtree notifications are only supported on naming context (NC) heads.
0x000020B9 ERROR_DS_NOTIFY_FILTER_TOO_COMPLEX	Notification filter is too complex.
0x000020BA ERROR_DS_DUP_RDN	Schema update failed: Duplicate RDN.
0x000020BB ERROR_DS_DUP_OID	Schema update failed: Duplicate OID.
0x000020BC ERROR_DS_DUP_MAPI_ID	Schema update failed: Duplicate Message Application Programming Interface (MAPI) identifier.

Win32 error codes	Description
0x000020BD ERROR_DS_DUP_SCHEMA_ID_GUID	Schema update failed: Duplicate schema ID GUID.
0x000020BE ERROR_DS_DUP_LDAP_DISPLAY_NAME	Schema update failed: Duplicate LDAP display name.
0x000020BF ERROR_DS_SEMANTIC_ATT_TEST	Schema update failed: Range-Lower less than Range-Upper.
0x000020C0 ERROR_DS_SYNTAX_MISMATCH	Schema update failed: Syntax mismatch.
0x000020C1 ERROR_DS_EXISTS_IN_MUST_HAVE	Schema deletion failed: Attribute is used in the Must-Contain list.
0x000020C2 ERROR_DS_EXISTS_IN_MAY_HAVE	Schema deletion failed: Attribute is used in the May-Contain list.
0x000020C3 ERROR_DS_NONEXISTENT_MAY_HAVE	Schema update failed: Attribute in May-Contain list does not exist.
0x000020C4 ERROR_DS_NONEXISTENT_MUST_HAVE	Schema update failed: Attribute in the Must-Contain list does not exist.
0x000020C5 ERROR_DS_AUX_CLS_TEST_FAIL	Schema update failed: Class in the Aux Class list does not exist or is not an auxiliary class.
0x000020C6 ERROR_DS_NONEXISTENT_POSS_SUP	Schema update failed: Class in the Poss-Superiors list does not exist.
0x000020C7 ERROR_DS_SUB_CLS_TEST_FAIL	Schema update failed: Class in the subclass of the list does not exist or does not satisfy hierarchy rules.
0x000020C8 ERROR_DS_BAD_RDN_ATT_ID_SYNTAX	Schema update failed: Rdn-Att-Id has wrong syntax.
0x000020C9 ERROR_DS_EXISTS_IN_AUX_CLS	Schema deletion failed: Class is used as an auxiliary class.
0x000020CA ERROR_DS_EXISTS_IN_SUB_CLS	Schema deletion failed: Class is used as a subclass.
0x000020CB ERROR_DS_EXISTS_IN_POSS_SUP	Schema deletion failed: Class is used as a Poss-Superior.
0x000020CC ERROR_DS_RECALCSHEMA_FAILED	Schema update failed in recalculating validation cache.
0x000020CD ERROR_DS_TREE_DELETE_NOT_FINISHED	The tree deletion is not finished. The request must be made again to continue deleting the tree.
0x000020CE ERROR_DS_CANT_DELETE	The requested delete operation could not be performed.
0x000020CF ERROR_DS_ATT_SCHEMA_REQ_ID	Cannot read the governs class identifier for the schema record.

Win32 error codes	Description
0x000020D0 ERROR_DS_BAD_ATT_SCHEMA_SYNTAX	The attribute schema has bad syntax.
0x000020D1 ERROR_DS_CANT_CACHE_ATT	The attribute could not be cached.
0x000020D2 ERROR_DS_CANT_CACHE_CLASS	The class could not be cached.
0x000020D3 ERROR_DS_CANT_REMOVE_ATT_CACHE	The attribute could not be removed from the cache.
0x000020D4 ERROR_DS_CANT_REMOVE_CLASS_CACHE	The class could not be removed from the cache.
0x000020D5 ERROR_DS_CANT_RETRIEVE_DN	The distinguished name attribute could not be read.
0x000020D6 ERROR_DS_MISSING_SUPREF	No superior reference has been configured for the directory service. The directory service is, therefore, unable to issue referrals to objects outside this forest.
0x000020D7 ERROR_DS_CANT_RETRIEVE_INSTANCE	The instance type attribute could not be retrieved.
0x000020D8 ERROR_DS_CODE_INCONSISTENCY	An internal error has occurred.
0x000020D9 ERROR_DS_DATABASE_ERROR	A database error has occurred.
0x000020DA ERROR_DS_GOVERNSID_MISSING	The <b>governsID</b> attribute is missing.
0x000020DB ERROR_DS_MISSING_EXPECTED_ATT	An expected attribute is missing.
0x000020DC ERROR_DS_NCNAME_MISSING_CR_REF	The specified naming context is missing a cross-reference.
0x000020DD ERROR_DS_SECURITY_CHECKING_ERROR	A security checking error has occurred.
0x000020DE ERROR_DS_SCHEMA_NOT_LOADED	The schema is not loaded.
0x000020DF ERROR_DS_SCHEMA_ALLOC_FAILED	Schema allocation failed. Check if the machine is running low on memory.
0x000020E0 ERROR_DS_ATT_SCHEMA_REQ_SYNTAX	Failed to obtain the required syntax for the attribute schema.
0x000020E1 ERROR_DS_GCVERIFY_ERROR	The GC verification failed. The GC is not available or does not support the operation. Some part of the directory is currently not available.

Win32 error codes	Description
0x000020E2 ERROR_DS_DRA_SCHEMA_MISMATCH	The replication operation failed because of a schema mismatch between the servers involved.
0x000020E3 ERROR_DS_CANT_FIND_DSA_OBJ	The DSA object could not be found.
0x000020E4 ERROR_DS_CANT_FIND_EXPECTED_NC	The naming context could not be found.
0x000020E5 ERROR_DS_CANT_FIND_NC_IN_CACHE	The naming context could not be found in the cache.
0x000020E6 ERROR_DS_CANT_RETRIEVE_CHILD	The child object could not be retrieved.
0x000020E7 ERROR_DS_SECURITY_ILLEGAL_MODIFY	The modification was not permitted for security reasons.
0x000020E8 ERROR_DS_CANT_REPLACE_HIDDEN_REC	The operation cannot replace the hidden record.
0x000020E9 ERROR_DS_BAD_HIERARCHY_FILE	The hierarchy file is invalid.
0x000020EA ERROR_DS_BUILD_HIERARCHY_TABLE_FAILED	The attempt to build the hierarchy table failed.
0x000020EB ERROR_DS_CONFIG_PARAM_MISSING	The directory configuration parameter is missing from the registry.
0x000020EC ERROR_DS_COUNTING_AB_INDICES_FAILED	The attempt to count the address book indices failed.
0x000020ED ERROR_DS_HIERARCHY_TABLE_MALLOC_FAILED	The allocation of the hierarchy table failed.
0x000020EE ERROR_DS_INTERNAL_FAILURE	The directory service encountered an internal failure.
0x000020EF ERROR_DS_UNKNOWN_ERROR	The directory service encountered an unknown failure.
0x000020F0 ERROR_DS_ROOT_REQUIRES_CLASS_TOP	A root object requires a class of "top".
0x000020F1 ERROR_DS_REFUSING_FSMO_ROLES	This directory server is shutting down, and cannot take ownership of new floating single-master operation roles.
0x000020F2 ERROR_DS_MISSING_FSMO_SETTINGS	The directory service is missing mandatory configuration information and is unable to determine the ownership of floating single-master operation roles.
0x000020F3 ERROR_DS_UNABLE_TO_SURRENDER_ROLES	The directory service was unable to transfer ownership of one or more floating single-master operation roles to other servers.

Win32 error codes	Description
0x000020F4 ERROR_DS_DRA_GENERIC	The replication operation failed.
0x000020F5 ERROR_DS_DRA_INVALID_PARAMETER	An invalid parameter was specified for this replication operation.
0x000020F6 ERROR_DS_DRA_BUSY	The directory service is too busy to complete the replication operation at this time.
0x000020F7 ERROR_DS_DRA_BAD_DN	The DN specified for this replication operation is invalid.
0x000020F8 ERROR_DS_DRA_BAD_NC	The naming context specified for this replication operation is invalid.
0x000020F9 ERROR_DS_DRA_DN_EXISTS	The DN specified for this replication operation already exists.
0x000020FA ERROR_DS_DRA_INTERNAL_ERROR	The replication system encountered an internal error.
0x000020FB ERROR_DS_DRA_INCONSISTENT_DIT	The replication operation encountered a database inconsistency.
0x000020FC ERROR_DS_DRA_CONNECTION_FAILED	The server specified for this replication operation could not be contacted.
0x000020FD ERROR_DS_DRA_BAD_INSTANCE_TYPE	The replication operation encountered an object with an invalid instance type.
0x000020FE ERROR_DS_DRA_OUT_OF_MEM	The replication operation failed to allocate memory.
0x000020FF ERROR_DS_DRA_MAIL_PROBLEM	The replication operation encountered an error with the mail system.
0x00002100 ERROR_DS_DRA_REF_ALREADY_EXISTS	The replication reference information for the target server already exists.
0x00002101 ERROR_DS_DRA_REF_NOT_FOUND	The replication reference information for the target server does not exist.
0x00002102 ERROR_DS_DRA_OBJ_IS_REP_SOURCE	The naming context cannot be removed because it is replicated to another server.
0x00002103 ERROR_DS_DRA_DB_ERROR	The replication operation encountered a database error.
0x00002104 ERROR_DS_DRA_NO_REPLICA	The naming context is in the process of being removed or is not replicated from the specified server.
0x00002105 ERROR_DS_DRA_ACCESS_DENIED	Replication access was denied.
0x00002106 ERROR_DS_DRA_NOT_SUPPORTED	The requested operation is not supported by this version of the directory service.

Win32 error codes	Description
0x00002107 ERROR_DS_DRA_RPC_CANCELLED	The replication RPC was canceled.
0x00002108 ERROR_DS_DRA_SOURCE_DISABLED	The source server is currently rejecting replication requests.
0x00002109 ERROR_DS_DRA_SINK_DISABLED	The destination server is currently rejecting replication requests.
0x0000210A ERROR_DS_DRA_NAME_COLLISION	The replication operation failed due to a collision of object names.
0x0000210B ERROR_DS_DRA_SOURCE_REINSTALLED	The replication source has been reinstalled.
0x0000210C ERROR_DS_DRA_MISSING_PARENT	The replication operation failed because a required parent object is missing.
0x0000210D ERROR_DS_DRA_PREEMPTED	The replication operation was preempted.
0x0000210E ERROR_DS_DRA_ABANDON_SYNC	The replication synchronization attempt was abandoned because of a lack of updates.
0x0000210F ERROR_DS_DRA_SHUTDOWN	The replication operation was terminated because the system is shutting down.
0x00002110 ERROR_DS_DRA_INCOMPATIBLE_PARTIAL_SET	A synchronization attempt failed because the destination DC is currently waiting to synchronize new partial attributes from the source. This condition is normal if a recent schema change modified the partial attribute set. The destination partial attribute set is not a subset of the source partial attribute set.
0x00002111 ERROR_DS_DRA_SOURCE_IS_PARTIAL_REPLICA	The replication synchronization attempt failed because a master replica attempted to sync from a partial replica.
0x00002112 ERROR_DS_DRA_EXTN_CONNECTION_FAILED	The server specified for this replication operation was contacted, but that server was unable to contact an additional server needed to complete the operation.
0x00002113 ERROR_DS_INSTALL_SCHEMA_MISMATCH	The version of the directory service schema of the source forest is not compatible with the version of the directory service on this computer.
0x00002114 ERROR_DS_DUP_LINK_ID	Schema update failed: An attribute with the same link identifier already exists.
0x00002115 ERROR_DS_NAME_ERROR_RESOLVING	Name translation: Generic processing error.
0x00002116 ERROR_DS_NAME_ERROR_NOT_FOUND	Name translation: Could not find the name or insufficient right to see name.



Win32 error codes	Description
0x00002117 ERROR_DS_NAME_ERROR_NOT_UNIQUE	Name translation: Input name mapped to more than one output name.
0x00002118 ERROR_DS_NAME_ERROR_NO_MAPPING	Name translation: The input name was found but not the associated output format.
0x00002119 ERROR_DS_NAME_ERROR_DOMAIN_ONLY	Name translation: Unable to resolve completely, only the domain was found.
0x0000211A ERROR_DS_NAME_ERROR_NO_SYNTACTICAL_MAPPING	Name translation: Unable to perform purely syntactical mapping at the client without going out to the wire.
0x0000211B ERROR_DS_CONSTRUCTED_ATT_MOD	Modification of a constructed attribute is not allowed.
0x0000211C ERROR_DS_WRONG_OM_OBJ_CLASS	The OM-Object-Class specified is incorrect for an attribute with the specified syntax.
0x0000211D ERROR_DS_DRA_REPL_PENDING	The replication request has been posted; waiting for a reply.
0x0000211E ERROR_DS_DS_REQUIRED	The requested operation requires a directory service, and none was available.
0x0000211F ERROR_DS_INVALID_LDAP_DISPLAY_NAME	The LDAP display name of the class or attribute contains non-ASCII characters.
0x00002120 ERROR_DS_NON_BASE_SEARCH	The requested search operation is only supported for base searches.
0x00002121 ERROR_DS_CANT_RETRIEVE_ATTS	The search failed to retrieve attributes from the database.
0x00002122 ERROR_DS_BACKLINK_WITHOUT_LINK	The schema update operation tried to add a backward link attribute that has no corresponding forward link.
0x00002123 ERROR_DS_EPOCH_MISMATCH	The source and destination of a cross-domain move do not agree on the object's epoch number. Either the source or the destination does not have the latest version of the object.
0x00002124 ERROR_DS_SRC_NAME_MISMATCH	The source and destination of a cross-domain move do not agree on the object's current name. Either the source or the destination does not have the latest version of the object.
0x00002125 ERROR_DS_SRC_AND_DST_NC_IDENTICAL	The source and destination for the cross-domain move operation are identical. The caller should use a local move operation instead of a cross-domain move operation.
0x00002126 ERROR_DS_DST_NC_MISMATCH	The source and destination for a cross-domain move do not agree on the naming contexts in the forest. Either the source or the destination does not have the latest version of the Partitions container.

Win32 error codes	Description
0x00002127 ERROR_DS_NOT_AUTHORITY_FOR_DST_NC	The destination of a cross-domain move is not authoritative for the destination naming context.
0x00002128 ERROR_DS_SRC_GUID_MISMATCH	The source and destination of a cross-domain move do not agree on the identity of the source object. Either the source or the destination does not have the latest version of the source object.
0x00002129 ERROR_DS_CANT_MOVE_DELETED_OBJECT	The object being moved across domains is already known to be deleted by the destination server. The source server does not have the latest version of the source object.
0x0000212A ERROR_DS_PDC_OPERATION_IN_PROGRESS	Another operation that requires exclusive access to the PDC FSMO is already in progress.
0x0000212B ERROR_DS_CROSS_DOMAIN_CLEANUP_REQD	A cross-domain move operation failed because two versions of the moved object exist—one each in the source and destination domains. The destination object needs to be removed to restore the system to a consistent state.
0x0000212C ERROR_DS_ILLEGAL_XDOM_MOVE_OPERATION	This object may not be moved across domain boundaries either because cross-domain moves for this class are not allowed, or the object has some special characteristics, for example, a trust account or a restricted relative identifier (RID), that prevent its move.
0x0000212D ERROR_DS_CANT_WITH_ACCT_GROUP_MEMBERSHPS	Cannot move objects with memberships across domain boundaries because, once moved, this violates the membership conditions of the account group. Remove the object from any account group memberships and retry.
0x0000212E ERROR_DS_NC_MUST_HAVE_NC_PARENT	A naming context head must be the immediate child of another naming context head, not of an interior node.
0x0000212F ERROR_DS_CR_IMPOSSIBLE_TO_VALIDATE	The directory cannot validate the proposed naming context name because it does not hold a replica of the naming context above the proposed naming context. Ensure that the domain naming master role is held by a server that is configured as a GC server, and that the server is up-to-date with its replication partners. (Applies only to Windows 2000 domain naming masters.)
0x00002130 ERROR_DS_DST_DOMAIN_NOT_NATIVE	Destination domain must be in native mode.
0x00002131 ERROR_DS_MISSING_INFRASTRUCTURE_CONTAINER	The operation cannot be performed because the server does not have an infrastructure container in the domain of interest.

Win32 error codes	Description
0x00002132 ERROR_DS_CANT_MOVE_ACCOUNT_GROUP	Cross-domain moves of nonempty account groups is not allowed.
0x00002133 ERROR_DS_CANT_MOVE_RESOURCE_GROUP	Cross-domain moves of nonempty resource groups is not allowed.
0x00002134 ERROR_DS_INVALID_SEARCH_FLAG	The search flags for the attribute are invalid. The ambiguous name resolution (ANR) bit is valid only on attributes of Unicode or Teletex strings.
0x00002135 ERROR_DS_NO_TREE_DELETE_ABOVE_NC	Tree deletions starting at an object that has an NC head as a descendant are not allowed.
0x00002136 ERROR_DS_COULDNT_LOCK_TREE_FOR_DELETE	The directory service failed to lock a tree in preparation for a tree deletion because the tree was in use.
0x00002137 ERROR_DS_COULDNT_IDENTIFY_OBJECTS_FOR_TREE_DELETE	The directory service failed to identify the list of objects to delete while attempting a tree deletion.
0x00002138 ERROR_DS_SAM_INIT_FAILURE	SAM initialization failed because of the following error: %1. Error Status: 0x%2. Click OK to shut down the system and reboot into Directory Services Restore Mode. Check the event log for detailed information.
0x00002139 ERROR_DS_SENSITIVE_GROUP_VIOLATION	Only an administrator can modify the membership list of an administrative group.
0x0000213A ERROR_DS_CANT_MOD_PRIMARYGROUPID	Cannot change the primary group ID of a domain controller account.
0x0000213B ERROR_DS_ILLEGAL_BASE_SCHEMA_MOD	An attempt was made to modify the base schema.
0x0000213C ERROR_DS_NONSAFE_SCHEMA_CHANGE	Adding a new mandatory attribute to an existing class, deleting a mandatory attribute from an existing class, or adding an optional attribute to the special class Top that is not a backlink attribute (directly or through inheritance, for example, by adding or deleting an auxiliary class) is not allowed.
0x0000213D ERROR_DS_SCHEMA_UPDATE_DISALLOWED	Schema update is not allowed on this DC because the DC is not the schema FSMO role owner.
0x0000213E ERROR_DS_CANT_CREATE_UNDER_SCHEMA	An object of this class cannot be created under the schema container. You can only create Attribute-Schema and Class-Schema objects under the schema container.
0x0000213F ERROR_DS_INSTALL_NO_SRC_SCH_VERSION	The replica or child install failed to get the <b>objectVersion</b> attribute on the schema container on the source DC. Either the attribute is missing on the schema container or the

Win32 error codes	Description
	credentials supplied do not have permission to read it.
0x00002140 ERROR_DS_INSTALL_NO_SCH_VERSION_IN_INIFILE	The replica or child install failed to read the <b>objectVersion</b> attribute in the SCHEMA section of the file schema.ini in the System32 directory.
0x00002141 ERROR_DS_INVALID_GROUP_TYPE	The specified group type is invalid.
0x00002142 ERROR_DS_NO_NEST_GLOBALGROUP_IN_MIXEDDOMAIN	You cannot nest global groups in a mixed domain if the group is security-enabled.
0x00002143 ERROR_DS_NO_NEST_LOCALGROUP_IN_MIXEDDOMAIN	You cannot nest local groups in a mixed domain if the group is security-enabled.
0x00002144 ERROR_DS_GLOBAL_CANT_HAVE_LOCAL_MEMBER	A global group cannot have a local group as a member.
0x00002145 ERROR_DS_GLOBAL_CANT_HAVE_UNIVERSAL_MEMBER	A global group cannot have a universal group as a member.
0x00002146 ERROR_DS_UNIVERSAL_CANT_HAVE_LOCAL_MEMBER	A universal group cannot have a local group as a member.
0x00002147 ERROR_DS_GLOBAL_CANT_HAVE_CROSSDOMAIN_MEMBER	A global group cannot have a cross-domain member.
0x00002148 ERROR_DS_LOCAL_CANT_HAVE_CROSSDOMAIN_LOCAL_MEMBER	A local group cannot have another cross domain local group as a member.
0x00002149 ERROR_DS_HAVE_PRIMARY_MEMBERS	A group with primary members cannot change to a security-disabled group.
0x0000214A ERROR_DS_STRING_SD_CONVERSION_FAILED	The schema cache load failed to convert the string default security descriptor (SD) on a class-schema object.
0x0000214B ERROR_DS_NAMING_MASTER_GC	Only DSAs configured to be GC servers should be allowed to hold the domain naming master FSMO role. (Applies only to Windows 2000 servers.)
0x0000214C ERROR_DS_DNS_LOOKUP_FAILURE	The DSA operation is unable to proceed because of a DNS lookup failure.
0x0000214D ERROR_DS_COULDNT_UPDATE_SPNS	While processing a change to the DNS host name for an object, the SPN values could not be kept in sync.
0x0000214E ERROR_DS_CANT_RETRIEVE_SD	The Security Descriptor attribute could not be read.

Win32 error codes	Description
0x0000214F ERROR_DS_KEY_NOT_UNIQUE	The object requested was not found, but an object with that key was found.
0x00002150 ERROR_DS_WRONG_LINKED_ATT_SYNTAX	The syntax of the linked attribute being added is incorrect. Forward links can only have syntax 2.5.5.1, 2.5.5.7, and 2.5.5.14, and backlinks can only have syntax 2.5.5.1.
0x00002151 ERROR_DS_SAM_NEED_BOOTKEY_PASSWORD	SAM needs to get the boot password.
0x00002152 ERROR_DS_SAM_NEED_BOOTKEY_FLOPPY	SAM needs to get the boot key from the floppy disk.
0x00002153 ERROR_DS_CANT_START	Directory Service cannot start.
0x00002154 ERROR_DS_INIT_FAILURE	Directory Services could not start.
0x00002155 ERROR_DS_NO_PKT_PRIVACY_ON_CONNECTION	The connection between client and server requires packet privacy or better.
0x00002156 ERROR_DS_SOURCE_DOMAIN_IN_FOREST	The source domain may not be in the same forest as the destination.
0x00002157 ERROR_DS_DESTINATION_DOMAIN_NOT_IN_FOREST	The destination domain must be in the forest.
0x00002158 ERROR_DS_DESTINATION_AUDITING_NOT_ENABLED	The operation requires that destination domain auditing be enabled.
0x00002159 ERROR_DS_CANT_FIND_DC_FOR_SRC_DOMAIN	The operation could not locate a DC for the source domain.
0x0000215A ERROR_DS_SRC_OBJ_NOT_GROUP_OR_USER	The source object must be a group or user.
0x0000215B ERROR_DS_SRC_SID_EXISTS_IN_FOREST	The source object's SID already exists in the destination forest.
0x0000215C ERROR_DS_SRC_AND_DST_OBJECT_CLASS_MISMATCH	The source and destination object must be of the same type.
0x0000215D ERROR_SAM_INIT_FAILURE	SAM initialization failed because of the following error: %1. Error Status: 0x%2. Click OK to shut down the system and reboot into Safe Mode. Check the event log for detailed information.
0x0000215E ERROR_DS_DRA_SCHEMA_INFO_SHIP	Schema information could not be included in the replication request.
0x0000215F ERROR_DS_DRA_SCHEMA_CONFLICT	The replication operation could not be completed due to a schema incompatibility.
0x00002160	The replication operation could not be

Win32 error codes	Description
ERROR_DS_DRA_EARLIER_SCHEMA_CONFLICT	completed due to a previous schema incompatibility.
0x00002161 ERROR_DS_DRA_OBJ_NC_MISMATCH	The replication update could not be applied because either the source or the destination has not yet received information regarding a recent cross-domain move operation.
0x00002162 ERROR_DS_NC_STILL_HAS_DSAS	The requested domain could not be deleted because there exist domain controllers that still host this domain.
0x00002163 ERROR_DS_GC_REQUIRED	The requested operation can be performed only on a GC server.
0x00002164 ERROR_DS_LOCAL_MEMBER_OF_LOCAL_ONLY	A local group can only be a member of other local groups in the same domain.
0x00002165 ERROR_DS_NO_FPO_IN_UNIVERSAL_GROUPS	Foreign security principals cannot be members of universal groups.
0x00002166 ERROR_DS_CANT_ADD_TO_GC	The attribute is not allowed to be replicated to the GC because of security reasons.
0x00002167 ERROR_DS_NO_CHECKPOINT_WITH_PDC	The checkpoint with the PDC could not be taken because too many modifications are currently being processed.
0x00002168 ERROR_DS_SOURCE_AUDITING_NOT_ENABLED	The operation requires that source domain auditing be enabled.
0x00002169 ERROR_DS_CANT_CREATE_IN_NONDOMAIN_NC	Security principal objects can only be created inside domain naming contexts.
0x0000216A ERROR_DS_INVALID_NAME_FOR_SPN	An SPN could not be constructed because the provided host name is not in the necessary format.
0x0000216B ERROR_DS_FILTER_USES_CONSTRUCTED_ATTRS	A filter was passed that uses constructed attributes.
0x0000216C ERROR_DS_UNICODEPWD_NOT_IN_QUOTES	The <b>unicodePwd</b> attribute value must be enclosed in quotation marks.
0x0000216D ERROR_DS_MACHINE_ACCOUNT_QUOTA_EXCEEDED	Your computer could not be joined to the domain. You have exceeded the maximum number of computer accounts you are allowed to create in this domain. Contact your system administrator to have this limit reset or increased.
0x0000216E ERROR_DS_MUST_BE_RUN_ON_DST_DC	For security reasons, the operation must be run on the destination DC.
0x0000216F ERROR_DS_SRC_DC_MUST_BE_SP4_OR_GREATER	For security reasons, the source DC must be Windows NT 4.0 SP4 and later.
0x00002170	Critical directory service system objects cannot

Win32 error codes	Description
ERROR_DS_CANT_TREE_DELETE_CRITICAL_OBJ	be deleted during tree deletion operations. The tree deletion may have been partially performed.
0x00002171 ERROR_DS_INIT_FAILURE_CONSOLE	Directory Services could not start because of the following error: %1. Error Status: 0x%2. Click OK to shut down the system. You can use the Recovery Console to further diagnose the system.
0x00002172 ERROR_DS_SAM_INIT_FAILURE_CONSOLE	SAM initialization failed because of the following error: %1. Error Status: 0x%2. Click OK to shut down the system. You can use the Recovery Console to further diagnose the system.
0x00002173 ERROR_DS_FOREST_VERSION_TOO_HIGH	The version of the operating system installed is incompatible with the current forest functional level. You must upgrade to a new version of the operating system before this server can become a domain controller in this forest.
0x00002174 ERROR_DS_DOMAIN_VERSION_TOO_HIGH	The version of the operating system installed is incompatible with the current domain functional level. You must upgrade to a new version of the operating system before this server can become a domain controller in this domain.
0x00002175 ERROR_DS_FOREST_VERSION_TOO_LOW	The version of the operating system installed on this server no longer supports the current forest functional level. You must raise the forest functional level before this server can become a domain controller in this forest.
0x00002176 ERROR_DS_DOMAIN_VERSION_TOO_LOW	The version of the operating system installed on this server no longer supports the current domain functional level. You must raise the domain functional level before this server can become a domain controller in this domain.
0x00002177 ERROR_DS_INCOMPATIBLE_VERSION	The version of the operating system installed on this server is incompatible with the functional level of the domain or forest.
0x00002178 ERROR_DS_LOW_DSA_VERSION	The functional level of the domain (or forest) cannot be raised to the requested value because one or more domain controllers in the domain (or forest) are at a lower, incompatible functional level.
0x00002179 ERROR_DS_NO_BEHAVIOR_VERSION_IN_MIXEDDOMAIN	The forest functional level cannot be raised to the requested value because one or more domains are still in mixed-domain mode. All domains in the forest must be in native mode for you to raise the forest functional level.
0x0000217A ERROR_DS_NOT_SUPPORTED_SORT_ORDER	The sort order requested is not supported.

Win32 error codes	Description
0x0000217B ERROR_DS_NAME_NOT_UNIQUE	The requested name already exists as a unique identifier.
0x0000217C ERROR_DS_MACHINE_ACCOUNT_CREATED_PRENT4	The machine account was created before Windows NT 4.0. The account needs to be re-created.
0x0000217D ERROR_DS_OUT_OF_VERSION_STORE	The database is out of version store.
0x0000217E ERROR_DS_INCOMPATIBLE_CONTROLS_USED	Unable to continue operation because multiple conflicting controls were used.
0x0000217F ERROR_DS_NO_REF_DOMAIN	Unable to find a valid security descriptor reference domain for this partition.
0x00002180 ERROR_DS_RESERVED_LINK_ID	Schema update failed: The link identifier is reserved.
0x00002181 ERROR_DS_LINK_ID_NOT_AVAILABLE	Schema update failed: There are no link identifiers available.
0x00002182 ERROR_DS_AG_CANT_HAVE_UNIVERSAL_MEMBER	An account group cannot have a universal group as a member.
0x00002183 ERROR_DS_MODIFYDN_DISALLOWED_BY_INSTANCE_TYPE	Rename or move operations on naming context heads or read-only objects are not allowed.
0x00002184 ERROR_DS_NO_OBJECT_MOVE_IN_SCHEMA_NC	Move operations on objects in the schema naming context are not allowed.
0x00002185 ERROR_DS_MODIFYDN_DISALLOWED_BY_FLAG	A system flag has been set on the object that does not allow the object to be moved or renamed.
0x00002186 ERROR_DS_MODIFYDN_WRONG_GRANDPARENT	This object is not allowed to change its grandparent container. Moves are not forbidden on this object, but are restricted to sibling containers.
0x00002187 ERROR_DS_NAME_ERROR_TRUST_REFERRAL	Unable to resolve completely; a referral to another forest was generated.
0x00002188 ERROR_NOT_SUPPORTED_ON_STANDARD_SERVER	The requested action is not supported on a standard server.
0x00002189 ERROR_DS_CANT_ACCESS_REMOTE_PART_OF_AD	Could not access a partition of the directory service located on a remote server. Make sure at least one server is running for the partition in question.
0x0000218A ERROR_DS_CR_IMPOSSIBLE_TO_VALIDATE_V2	The directory cannot validate the proposed naming context (or partition) name because it does not hold a replica, nor can it contact a replica of the naming context above the proposed naming context. Ensure that the parent naming context is properly registered in



Win32 error codes	Description
	the DNS, and at least one replica of this naming context is reachable by the domain naming master.
0x0000218B ERROR_DS_THREAD_LIMIT_EXCEEDED	The thread limit for this request was exceeded.
0x0000218C ERROR_DS_NOT_CLOSEST	The GC server is not in the closest site.
0x0000218D ERROR_DS_CANT_DERIVE_SPN_WITHOUT_SERVER_REF	The directory service cannot derive an SPN with which to mutually authenticate the target server because the corresponding server object in the local DS database has no <b>serverReference</b> attribute.
0x0000218E ERROR_DS_SINGLE_USER_MODE_FAILED	The directory service failed to enter single-user mode.
0x0000218F ERROR_DS_NTDSRIPT_SYNTAX_ERROR	The directory service cannot parse the script because of a syntax error.
0x00002190 ERROR_DS_NTDSRIPT_PROCESS_ERROR	The directory service cannot process the script because of an error.
0x00002191 ERROR_DS_DIFFERENT_REPL_EPOCHS	The directory service cannot perform the requested operation because the servers involved are of different replication epochs (which is usually related to a domain rename that is in progress).
0x00002192 ERROR_DS_DRS_EXTENSIONS_CHANGED	The directory service binding must be renegotiated due to a change in the server extensions information.
0x00002193 ERROR_DS_REPLICA_SET_CHANGE_NOT_ALLOWED_ON_DISABLED_CR	The operation is not allowed on a disabled cross-reference.
0x00002194 ERROR_DS_NO_MSDS_INTID	Schema update failed: No values for msDS-IntId are available.
0x00002195 ERROR_DS_DUP_MSDS_INTID	Schema update failed: Duplicate msDS-IntId. Retry the operation.
0x00002196 ERROR_DS_EXISTS_IN_RDNATTID	Schema deletion failed: Attribute is used in rDNAttID.
0x00002197 ERROR_DS_AUTHORIZATION_FAILED	The directory service failed to authorize the request.
0x00002198 ERROR_DS_INVALID_SCRIPT	The directory service cannot process the script because it is invalid.
0x00002199 ERROR_DS_REMOTE_CROSSREF_OP_FAILED	The remote create cross-reference operation failed on the domain naming master FSMO. The operation's error is in the extended data.

Win32 error codes	Description
0x0000219A ERROR_DS_CROSS_REF_BUSY	A cross-reference is in use locally with the same name.
0x0000219B ERROR_DS_CANT_DERIVE_SPN_FOR_DELETED_DOMAIN	The directory service cannot derive an SPN with which to mutually authenticate the target server because the server's domain has been deleted from the forest.
0x0000219C ERROR_DS_CANT_DEMOTE_WITH_WRITEABLE_NC	Writable NCs prevent this DC from demoting.
0x0000219D ERROR_DS_DUPLICATE_ID_FOUND	The requested object has a nonunique identifier and cannot be retrieved.
0x0000219E ERROR_DS_INSUFFICIENT_ATTR_TO_CREATE_OBJECT	Insufficient attributes were given to create an object. This object may not exist because it may have been deleted and the garbage already collected.
0x0000219F ERROR_DS_GROUP_CONVERSION_ERROR	The group cannot be converted due to attribute restrictions on the requested group type.
0x000021A0 ERROR_DS_CANT_MOVE_APP_BASIC_GROUP	Cross-domain moves of nonempty basic application groups is not allowed.
0x000021A1 ERROR_DS_CANT_MOVE_APP_QUERY_GROUP	Cross-domain moves of nonempty query-based application groups is not allowed.
0x000021A2 ERROR_DS_ROLE_NOT_VERIFIED	The FSMO role ownership could not be verified because its directory partition did not replicate successfully with at least one replication partner.
0x000021A3 ERROR_DS_WKO_CONTAINER_CANNOT_BE_SPECIAL	The target container for a redirection of a well-known object container cannot already be a special container.
0x000021A4 ERROR_DS_DOMAIN_RENAME_IN_PROGRESS	The directory service cannot perform the requested operation because a domain rename operation is in progress.
0x000021A5 ERROR_DS_EXISTING_AD_CHILD_NC	The directory service detected a child partition below the requested partition name. The partition hierarchy must be created in a top down method.
0x000021A6 ERROR_DS_REPL_LIFETIME_EXCEEDED	The directory service cannot replicate with this server because the time since the last replication with this server has exceeded the tombstone lifetime.
0x000021A7 ERROR_DS_DISALLOWED_IN_SYSTEM_CONTAINER	The requested operation is not allowed on an object under the system container.
0x000021A8 ERROR_DS_LDAP_SEND_QUEUE_FULL	The LDAP server's network send queue has filled up because the client is not processing the results of its requests fast enough. No more requests will be processed until the client

Win32 error codes	Description
	catches up. If the client does not catch up then it will be disconnected.
0x000021A9 ERROR_DS_DRA_OUT_SCHEDULE_WINDOW	The scheduled replication did not take place because the system was too busy to execute the request within the schedule window. The replication queue is overloaded. Consider reducing the number of partners or decreasing the scheduled replication frequency.
0x000021AA ERROR_DS_POLICY_NOT_KNOWN	At this time, it cannot be determined if the branch replication policy is available on the hub domain controller. Retry at a later time to account for replication latencies.
0x000021AB ERROR_NO_SITE_SETTINGS_OBJECT	The site settings object for the specified site does not exist.
0x000021AC ERROR_NO_SECRETS	The local account store does not contain secret material for the specified account.
0x000021AD ERROR_NO_WRITABLE_DC_FOUND	Could not find a writable domain controller in the domain.
0x000021AE ERROR_DS_NO_SERVER_OBJECT	The server object for the domain controller does not exist.
0x000021AF ERROR_DS_NO_NTDSA_OBJECT	The NTDS Settings object for the domain controller does not exist.
0x000021B0 ERROR_DS_NON_ASQ_SEARCH	The requested search operation is not supported for attribute scoped query (ASQ) searches.
0x000021B1 ERROR_DS_AUDIT_FAILURE	A required audit event could not be generated for the operation.
0x000021B2 ERROR_DS_INVALID_SEARCH_FLAG_ SUBTREE	The search flags for the attribute are invalid. The subtree index bit is valid only on single-valued attributes.
0x000021B3 ERROR_DS_INVALID_SEARCH_FLAG_ TUPLE	The search flags for the attribute are invalid. The tuple index bit is valid only on attributes of Unicode strings.
0x00002329 DNS_ERROR_RCODE_FORMAT_ERROR	DNS server unable to interpret format.
0x0000232A DNS_ERROR_RCODE_SERVER_FAILURE	DNS server failure.
0x0000232B DNS_ERROR_RCODE_NAME_ERROR	DNS name does not exist.
0x0000232C DNS_ERROR_RCODE_NOT_IMPLEMENTED	DNS request not supported by name server.
0x0000232D	DNS operation refused.

Win32 error codes	Description
DNS_ERROR_RCODE_REFUSED	
0x0000232E DNS_ERROR_RCODE_YXDOMAIN	DNS name that should not exist, does exist.
0x0000232F DNS_ERROR_RCODE_YXRRSET	DNS resource record (RR) set that should not exist, does exist.
0x00002330 DNS_ERROR_RCODE_NXRRSET	DNS RR set that should to exist, does not exist.
0x00002331 DNS_ERROR_RCODE_NOTAUTH	DNS server not authoritative for zone.
0x00002332 DNS_ERROR_RCODE_NOTZONE	DNS name in update or prereq is not in zone.
0x00002338 DNS_ERROR_RCODE_BADSIG	DNS signature failed to verify.
0x00002339 DNS_ERROR_RCODE_BADKEY	DNS bad key.
0x0000233A DNS_ERROR_RCODE_BADTIME	DNS signature validity expired.
0x0000251D DNS_INFO_NO_RECORDS	No records found for given DNS query.
0x0000251E DNS_ERROR_BAD_PACKET	Bad DNS packet.
0x0000251F DNS_ERROR_NO_PACKET	No DNS packet.
0x00002520 DNS_ERROR_RCODE	DNS error, check rcode.
0x00002521 DNS_ERROR_UNSECURE_PACKET	Unsecured DNS packet.
0x0000254F DNS_ERROR_INVALID_TYPE	Invalid DNS type.
0x00002550 DNS_ERROR_INVALID_IP_ADDRESS	Invalid IP address.
0x00002551 DNS_ERROR_INVALID_PROPERTY	Invalid property.
0x00002552 DNS_ERROR_TRY_AGAIN_LATER	Try DNS operation again later.
0x00002553 DNS_ERROR_NOT_UNIQUE	Record for given name and type is not unique.
0x00002554 DNS_ERROR_NON_RFC_NAME	DNS name does not comply with RFC specifications.

Win32 error codes	Description
0x00002555 DNS_STATUS_FQDN	DNS name is a fully qualified DNS name.
0x00002556 DNS_STATUS_DOTTED_NAME	DNS name is dotted (multilabel).
0x00002557 DNS_STATUS_SINGLE_PART_NAME	DNS name is a single-part name.
0x00002558 DNS_ERROR_INVALID_NAME_CHAR	DNS name contains an invalid character.
0x00002559 DNS_ERROR_NUMERIC_NAME	DNS name is entirely numeric.
0x0000255A DNS_ERROR_NOT_ALLOWED_ON_ROOT_SERVER	The operation requested is not permitted on a DNS root server.
0x0000255B DNS_ERROR_NOT_ALLOWED_UNDER_DELEGATION	The record could not be created because this part of the DNS namespace has been delegated to another server.
0x0000255C DNS_ERROR_CANNOT_FIND_ROOT_HINTS	The DNS server could not find a set of root hints.
0x0000255D DNS_ERROR_INCONSISTENT_ROOT_HINTS	The DNS server found root hints but they were not consistent across all adapters.
0x0000255E DNS_ERROR_DWORD_VALUE_TOO_SMALL	The specified value is too small for this parameter.
0x0000255F DNS_ERROR_DWORD_VALUE_TOO_LARGE	The specified value is too large for this parameter.
0x00002560 DNS_ERROR_BACKGROUND_LOADING	This operation is not allowed while the DNS server is loading zones in the background. Try again later.
0x00002561 DNS_ERROR_NOT_ALLOWED_ON_RODC	The operation requested is not permitted on against a DNS server running on a read-only DC.
0x00002581 DNS_ERROR_ZONE_DOES_NOT_EXIST	DNS zone does not exist.
0x00002582 DNS_ERROR_NO_ZONE_INFO	DNS zone information not available.
0x00002583 DNS_ERROR_INVALID_ZONE_OPERATION	Invalid operation for DNS zone.
0x00002584 DNS_ERROR_ZONE_CONFIGURATION_ERROR	Invalid DNS zone configuration.
0x00002585 DNS_ERROR_ZONE_HAS_NO_SOA_RECORD	DNS zone has no start of authority (SOA) record.
0x00002586	DNS zone has no Name Server (NS) record.

Win32 error codes	Description
DNS_ERROR_ZONE_HAS_NO_NS_RECORDS	
0x00002587 DNS_ERROR_ZONE_LOCKED	DNS zone is locked.
0x00002588 DNS_ERROR_ZONE_CREATION_FAILED	DNS zone creation failed.
0x00002589 DNS_ERROR_ZONE_ALREADY_EXISTS	DNS zone already exists.
0x0000258A DNS_ERROR_AUTOZONE_ALREADY_EXISTS	DNS automatic zone already exists.
0x0000258B DNS_ERROR_INVALID_ZONE_TYPE	Invalid DNS zone type.
0x0000258C DNS_ERROR_SECONDARY_REQUIRES_MASTER_IP	Secondary DNS zone requires master IP address.
0x0000258D DNS_ERROR_ZONE_NOT_SECONDARY	DNS zone not secondary.
0x0000258E DNS_ERROR_NEED_SECONDARY_ADDRESSES	Need secondary IP address.
0x0000258F DNS_ERROR_WINS_INIT_FAILED	WINS initialization failed.
0x00002590 DNS_ERROR_NEED_WINS_SERVERS	Need WINS servers.
0x00002591 DNS_ERROR_NBSTAT_INIT_FAILED	NBTSTAT initialization call failed.
0x00002592 DNS_ERROR_SOA_DELETE_INVALID	Invalid delete of SOA.
0x00002593 DNS_ERROR_FORWARDER_ALREADY_EXISTS	A conditional forwarding zone already exists for that name.
0x00002594 DNS_ERROR_ZONE_REQUIRES_MASTER_IP	This zone must be configured with one or more master DNS server IP addresses.
0x00002595 DNS_ERROR_ZONE_IS_SHUTDOWN	The operation cannot be performed because this zone is shut down.
0x000025B3 DNS_ERROR_PRIMARY_REQUIRES_DATAFILE	The primary DNS zone requires a data file.
0x000025B4 DNS_ERROR_INVALID_DATAFILE_NAME	Invalid data file name for the DNS zone.
0x000025B5 DNS_ERROR_DATAFILE_OPEN_FAILURE	Failed to open the data file for the DNS zone.
0x000025B6 DNS_ERROR_FILE_WRITEBACK_FAILED	Failed to write the data file for the DNS zone.

Win32 error codes	Description
0x000025B7 DNS_ERROR_DATAFILE_PARSING	Failure while reading datafile for DNS zone.
0x000025E5 DNS_ERROR_RECORD_DOES_NOT_EXIST	DNS record does not exist.
0x000025E6 DNS_ERROR_RECORD_FORMAT	DNS record format error.
0x000025E7 DNS_ERROR_NODE_CREATION_FAILED	Node creation failure in DNS.
0x000025E8 DNS_ERROR_UNKNOWN_RECORD_TYPE	Unknown DNS record type.
0x000025E9 DNS_ERROR_RECORD_TIMED_OUT	DNS record timed out.
0x000025EA DNS_ERROR_NAME_NOT_IN_ZONE	Name not in DNS zone.
0x000025EB DNS_ERROR_CNAME_LOOP	CNAME loop detected.
0x000025EC DNS_ERROR_NODE_IS_CNAME	Node is a CNAME DNS record.
0x000025ED DNS_ERROR_CNAME_COLLISION	A CNAME record already exists for the given name.
0x000025EE DNS_ERROR_RECORD_ONLY_AT_ZONE_ROOT	Record is only at DNS zone root.
0x000025EF DNS_ERROR_RECORD_ALREADY_EXISTS	DNS record already exists.
0x000025F0 DNS_ERROR_SECONDARY_DATA	Secondary DNS zone data error.
0x000025F1 DNS_ERROR_NO_CREATE_CACHE_DATA	Could not create DNS cache data.
0x000025F2 DNS_ERROR_NAME_DOES_NOT_EXIST	DNS name does not exist.
0x000025F3 DNS_WARNING_PTR_CREATE_FAILED	Could not create pointer (PTR) record.
0x000025F4 DNS_WARNING_DOMAIN_UNDELETED	DNS domain was undeleted.
0x000025F5 DNS_ERROR_DS_UNAVAILABLE	The directory service is unavailable.
0x000025F6 DNS_ERROR_DS_ZONE_ALREADY_EXISTS	DNS zone already exists in the directory service.
0x000025F7	DNS server not creating or reading the boot file

Win32 error codes	Description
DNS_ERROR_NO_BOOTFILE_IF_DS_ZONE	for the directory service integrated DNS zone.
0x00002617 DNS_INFO_AXFR_COMPLETE	DNS AXFR (zone transfer) complete.
0x00002618 DNS_ERROR_AXFR	DNS zone transfer failed.
0x00002619 DNS_INFO_ADDED_LOCAL_WINS	Added local WINS server.
0x00002649 DNS_STATUS_CONTINUE_NEEDED	Secure update call needs to continue update request.
0x0000267B DNS_ERROR_NO_TCPIP	TCP/IP network protocol not installed.
0x0000267C DNS_ERROR_NO_DNS_SERVERS	No DNS servers configured for local system.
0x000026AD DNS_ERROR_DP_DOES_NOT_EXIST	The specified directory partition does not exist.
0x000026AE DNS_ERROR_DP_ALREADY_EXISTS	The specified directory partition already exists.
0x000026AF DNS_ERROR_DP_NOT_ENLISTED	This DNS server is not enlisted in the specified directory partition.
0x000026B0 DNS_ERROR_DP_ALREADY_ENLISTED	This DNS server is already enlisted in the specified directory partition.
0x000026B1 DNS_ERROR_DP_NOT_AVAILABLE	The directory partition is not available at this time. Wait a few minutes and try again.
0x000026B2 DNS_ERROR_DP_FSMO_ERROR	The application directory partition operation failed. The domain controller holding the domain naming master role is down or unable to service the request or is not running Windows Server 2003.
0x00002714 WSAEINTR	A blocking operation was interrupted by a call to WSACancelBlockingCall.
0x00002719 WSAEBADF	The file handle supplied is not valid.
0x0000271D WSAEACCES	An attempt was made to access a socket in a way forbidden by its access permissions.
0x0000271E WSAEFAULT	The system detected an invalid pointer address in attempting to use a pointer argument in a call.
0x00002726 WSAEINVAL	An invalid argument was supplied.
0x00002728	Too many open sockets.



Win32 error codes	Description
WSAEMFILE	
0x00002733 WSAEWOULDBLOCK	A nonblocking socket operation could not be completed immediately.
0x00002734 WSAEINPROGRESS	A blocking operation is currently executing.
0x00002735 WSAEALREADY	An operation was attempted on a nonblocking socket that already had an operation in progress.
0x00002736 WSAENOTSOCK	An operation was attempted on something that is not a socket.
0x00002737 WSAEDESTADDRREQ	A required address was omitted from an operation on a socket.
0x00002738 WSAEMSGSIZE	A message sent on a datagram socket was larger than the internal message buffer or some other network limit, or the buffer used to receive a datagram into was smaller than the datagram itself.
0x00002739 WSAEPROTOTYPE	A protocol was specified in the socket function call that does not support the semantics of the socket type requested.
0x0000273A WSAENOPROTOOPT	An unknown, invalid, or unsupported option or level was specified in a getsockopt or setsockopt call.
0x0000273B WSAEPROTONOSUPPORT	The requested protocol has not been configured into the system, or no implementation for it exists.
0x0000273C WSAESOCKTNOSUPPORT	The support for the specified socket type does not exist in this address family.
0x0000273D WSAEOPNOTSUPP	The attempted operation is not supported for the type of object referenced.
0x0000273E WSAEPFNOSUPPORT	The protocol family has not been configured into the system or no implementation for it exists.
0x0000273F WSAEAFNOSUPPORT	An address incompatible with the requested protocol was used.
0x00002740 WSAEADDRINUSE	Only one usage of each socket address (protocol/network address/port) is normally permitted.
0x00002741 WSAEADDRNOTAVAIL	The requested address is not valid in its context.
0x00002742 WSAENETDOWN	A socket operation encountered a dead network.

Win32 error codes	Description
0x00002743 WSAENETUNREACH	A socket operation was attempted to an unreachable network.
0x00002744 WSAENETRESET	The connection has been broken due to keep-alive activity detecting a failure while the operation was in progress.
0x00002745 WSAECONNABORTED	An established connection was aborted by the software in your host machine.
0x00002746 WSAECONNRESET	An existing connection was forcibly closed by the remote host.
0x00002747 WSAENOBUFS	An operation on a socket could not be performed because the system lacked sufficient buffer space or because a queue was full.
0x00002748 WSAEISCONN	A connect request was made on an already connected socket.
0x00002749 WSAENOTCONN	A request to send or receive data was disallowed because the socket is not connected and (when sending on a datagram socket using a sendto call) no address was supplied.
0x0000274A WSAESHUTDOWN	A request to send or receive data was disallowed because the socket had already been shut down in that direction with a previous shutdown call.
0x0000274B WSAETOOMANYREFS	Too many references to a kernel object.
0x0000274C WSAETIMEDOUT	A connection attempt failed because the connected party did not properly respond after a period of time, or the established connection failed because the connected host failed to respond.
0x0000274D WSAECONNREFUSED	No connection could be made because the target machine actively refused it.
0x0000274E WSAELOOP	Cannot translate name.
0x0000274F WSAENAMETOOLONG	Name or name component was too long.
0x00002750 WSAEHOSTDOWN	A socket operation failed because the destination host was down.
0x00002751 WSAEHOSTUNREACH	A socket operation was attempted to an unreachable host.
0x00002752 WSAENOTEMPTY	Cannot remove a directory that is not empty.
0x00002753	A Windows Sockets implementation may have

Win32 error codes	Description
WSAEPROCLIM	a limit on the number of applications that may use it simultaneously.
0x00002754 WSAEUSERS	Ran out of quota.
0x00002755 WSAEDQUOT	Ran out of disk quota.
0x00002756 WSAESTALE	File handle reference is no longer available.
0x00002757 WSAEREMOTE	Item is not available locally.
0x0000276B WSASYSNOTREADY	WSAStartup cannot function at this time because the underlying system it uses to provide network services is currently unavailable.
0x0000276C WSAVERNOTSUPPORTED	The Windows Sockets version requested is not supported.
0x0000276D WSANOTINITIALISED	Either the application has not called WSAStartup, or WSAStartup failed.
0x00002775 WSAEDISCON	Returned by WSAREcv or WSAREcvFrom to indicate that the remote party has initiated a graceful shutdown sequence.
0x00002776 WSAENOMORE	No more results can be returned by WSALookupServiceNext.
0x00002777 WSAECANCELLED	A call to WSALookupServiceEnd was made while this call was still processing. The call has been canceled.
0x00002778 WSAEINVALIDPROCTABLE	The procedure call table is invalid.
0x00002779 WSAEINVALIDPROVIDER	The requested service provider is invalid.
0x0000277A WSAEPROVIDERFAILEDINIT	The requested service provider could not be loaded or initialized.
0x0000277B WSASYSCALLFAILURE	A system call that should never fail has failed.
0x0000277C WSASERVICE_NOT_FOUND	No such service is known. The service cannot be found in the specified namespace.
0x0000277D WSATYPE_NOT_FOUND	The specified class was not found.
0x0000277E WSA_E_NO_MORE	No more results can be returned by WSALookupServiceNext.

Win32 error codes	Description
0x0000277F WSA_E_CANCELLED	A call to WSALookupServiceEnd was made while this call was still processing. The call has been canceled.
0x00002780 WSAEREFUSED	A database query failed because it was actively refused.
0x00002AF9 WSAHOST_NOT_FOUND	No such host is known.
0x00002AFA WSATRY_AGAIN	This is usually a temporary error during host name resolution and means that the local server did not receive a response from an authoritative server.
0x00002AFB WSANO_RECOVERY	A nonrecoverable error occurred during a database lookup.
0x00002AFC WSANO_DATA	The requested name is valid, but no data of the requested type was found.
0x00002AFD WSA_QOS_RECEIVERS	At least one reserve has arrived.
0x00002AFE WSA_QOS_SENDERS	At least one path has arrived.
0x00002AFF WSA_QOS_NO_SENDERS	There are no senders.
0x00002B00 WSA_QOS_NO_RECEIVERS	There are no receivers.
0x00002B01 WSA_QOS_REQUEST_CONFIRMED	Reserve has been confirmed.
0x00002B02 WSA_QOS_ADMISSION_FAILURE	Error due to lack of resources.
0x00002B03 WSA_QOS_POLICY_FAILURE	Rejected for administrative reasons—bad credentials.
0x00002B04 WSA_QOS_BAD_STYLE	Unknown or conflicting style.
0x00002B05 WSA_QOS_BAD_OBJECT	There is a problem with some part of the filterspec or provider-specific buffer in general.
0x00002B06 WSA_QOS_TRAFFIC_CTRL_ERROR	There is a problem with some part of the flowspec.
0x00002B07 WSA_QOS_GENERIC_ERROR	General quality of serve (QOS) error.
0x00002B08 WSA_QOS_ESERVICETYPE	An invalid or unrecognized service type was found in the flowspec.
0x00002B09	An invalid or inconsistent flowspec was found in

Win32 error codes	Description
WSA_QOS_EFLOWSPEC	the QOS structure.
0x00002B0A WSA_QOS_EPROVSPECBUF	Invalid QOS provider-specific buffer.
0x00002B0B WSA_QOS_EFILTERSTYLE	An invalid QOS filter style was used.
0x00002B0C WSA_QOS_EFILTERTYPE	An invalid QOS filter type was used.
0x00002B0D WSA_QOS_EFILTERCOUNT	An incorrect number of QOS FILTERSPECS were specified in the FLOWDESCRIPTOR.
0x00002B0E WSA_QOS_EOBJLENGTH	An object with an invalid <b>ObjectLength</b> field was specified in the QOS provider-specific buffer.
0x00002B0F WSA_QOS_EFLOWCOUNT	An incorrect number of flow descriptors was specified in the QOS structure.
0x00002B10 WSA_QOS_EUNKOWNPSOBJ	An unrecognized object was found in the QOS provider-specific buffer.
0x00002B11 WSA_QOS_EPOLICYOBJ	An invalid policy object was found in the QOS provider-specific buffer.
0x00002B12 WSA_QOS_EFLOWDESC	An invalid QOS flow descriptor was found in the flow descriptor list.
0x00002B13 WSA_QOS_EPSFLOWSPEC	An invalid or inconsistent flowspec was found in the QOS provider-specific buffer.
0x00002B14 WSA_QOS_EPSFILTERSPEC	An invalid FILTERSPEC was found in the QOS provider-specific buffer.
0x00002B15 WSA_QOS_ESDMODEOBJ	An invalid shape discard mode object was found in the QOS provider-specific buffer.
0x00002B16 WSA_QOS_ESHAPERATEOBJ	An invalid shaping rate object was found in the QOS provider-specific buffer.
0x00002B17 WSA_QOS_RESERVED_PETYPE	A reserved policy element was found in the QOS provider-specific buffer.
0x000032C8 ERROR_IPSEC_QM_POLICY_EXISTS	The specified quick mode policy already exists.
0x000032C9 ERROR_IPSEC_QM_POLICY_NOT_FOUND	The specified quick mode policy was not found.
0x000032CA ERROR_IPSEC_QM_POLICY_IN_USE	The specified quick mode policy is being used.
0x000032CB ERROR_IPSEC_MM_POLICY_EXISTS	The specified main mode policy already exists.
0x000032CC	The specified main mode policy was not found.

Win32 error codes	Description
ERROR_IPSEC_MM_POLICY_NOT_FOUND	
0x000032CD ERROR_IPSEC_MM_POLICY_IN_USE	The specified main mode policy is being used.
0x000032CE ERROR_IPSEC_MM_FILTER_EXISTS	The specified main mode filter already exists.
0x000032CF ERROR_IPSEC_MM_FILTER_NOT_FOUND	The specified main mode filter was not found.
0x000032D0 ERROR_IPSEC_TRANSPORT_FILTER_EXISTS	The specified transport mode filter already exists.
0x000032D1 ERROR_IPSEC_TRANSPORT_FILTER_NOT_FOUND	The specified transport mode filter does not exist.
0x000032D2 ERROR_IPSEC_MM_AUTH_EXISTS	The specified main mode authentication list exists.
0x000032D3 ERROR_IPSEC_MM_AUTH_NOT_FOUND	The specified main mode authentication list was not found.
0x000032D4 ERROR_IPSEC_MM_AUTH_IN_USE	The specified main mode authentication list is being used.
0x000032D5 ERROR_IPSEC_DEFAULT_MM_POLICY_NOT_FOUND	The specified default main mode policy was not found.
0x000032D6 ERROR_IPSEC_DEFAULT_MM_AUTH_NOT_FOUND	The specified default main mode authentication list was not found.
0x000032D7 ERROR_IPSEC_DEFAULT_QM_POLICY_NOT_FOUND	The specified default quick mode policy was not found.
0x000032D8 ERROR_IPSEC_TUNNEL_FILTER_EXISTS	The specified tunnel mode filter exists.
0x000032D9 ERROR_IPSEC_TUNNEL_FILTER_NOT_FOUND	The specified tunnel mode filter was not found.
0x000032DA ERROR_IPSEC_MM_FILTER_PENDING_DELETION	The main mode filter is pending deletion.
0x000032DB ERROR_IPSEC_TRANSPORT_FILTER_PENDING_DELETION	The transport filter is pending deletion.
0x000032DC ERROR_IPSEC_TUNNEL_FILTER_PENDING_DELETION	The tunnel filter is pending deletion.
0x000032DD ERROR_IPSEC_MM_POLICY_PENDING_DELETION	The main mode policy is pending deletion.
0x000032DE ERROR_IPSEC_MM_AUTH_PENDING_DELETION	The main mode authentication bundle is pending deletion.
0x000032DF	The quick mode policy is pending deletion.

Win32 error codes	Description
ERROR_IPSEC_QM_POLICY_PENDING_DELETION	
0x000032E0 WARNING_IPSEC_MM_POLICY_PRUNED	The main mode policy was successfully added, but some of the requested offers are not supported.
0x000032E1 WARNING_IPSEC_QM_POLICY_PRUNED	The quick mode policy was successfully added, but some of the requested offers are not supported.
0x000035E8 ERROR_IPSEC_IKE_NEG_STATUS_BEGIN	ERROR_IPSEC_IKE_NEG_STATUS_BEGIN
0x000035E9 ERROR_IPSEC_IKE_AUTH_FAIL	The IKE authentication credentials are unacceptable.
0x000035EA ERROR_IPSEC_IKE_ATTRIB_FAIL	The IKE security attributes are unacceptable.
0x000035EB ERROR_IPSEC_IKE_NEGOTIATION_PENDING	The IKE negotiation is in progress.
0x000035EC ERROR_IPSEC_IKE_GENERAL_PROCESSING_ERROR	General processing error.
0x000035ED ERROR_IPSEC_IKE_TIMED_OUT	Negotiation timed out.
0x000035EE ERROR_IPSEC_IKE_NO_CERT	The IKE failed to find a valid machine certificate. Contact your network security administrator about installing a valid certificate in the appropriate certificate store.
0x000035EF ERROR_IPSEC_IKE_SA_DELETED	The IKE security association (SA) was deleted by a peer before it was completely established.
0x000035F0 ERROR_IPSEC_IKE_SA_REAPED	The IKE SA was deleted before it was completely established.
0x000035F1 ERROR_IPSEC_IKE_MM_ACQUIRE_DROP	The negotiation request sat in the queue too long.
0x000035F2 ERROR_IPSEC_IKE_QM_ACQUIRE_DROP	The negotiation request sat in the queue too long.
0x000035F3 ERROR_IPSEC_IKE_QUEUE_DROP_MM	The negotiation request sat in the queue too long.
0x000035F4 ERROR_IPSEC_IKE_QUEUE_DROP_NO_MM	The negotiation request sat in the queue too long.
0x000035F5 ERROR_IPSEC_IKE_DROP_NO_RESPONSE	There was no response from a peer.
0x000035F6 ERROR_IPSEC_IKE_MM_DELAY_DROP	The negotiation took too long.
0x000035F7	The negotiation took too long.

Win32 error codes	Description
ERROR_IPSEC_IKE_QM_DELAY_DROP	
0x000035F8 ERROR_IPSEC_IKE_ERROR	An unknown error occurred.
0x000035F9 ERROR_IPSEC_IKE_CRL_FAILED	The certificate revocation check failed.
0x000035FA ERROR_IPSEC_IKE_INVALID_KEY_USAGE	Invalid certificate key usage.
0x000035FB ERROR_IPSEC_IKE_INVALID_CERT_TYPE	Invalid certificate type.
0x000035FC ERROR_IPSEC_IKE_NO_PRIVATE_KEY	The IKE negotiation failed because the machine certificate used does not have a private key. IPsec certificates require a private key. Contact your network security administrator about a certificate that has a private key.
0x000035FE ERROR_IPSEC_IKE_DH_FAIL	There was a failure in the Diffie-Hellman computation.
0x00003600 ERROR_IPSEC_IKE_INVALID_HEADER	Invalid header.
0x00003601 ERROR_IPSEC_IKE_NO_POLICY	No policy configured.
0x00003602 ERROR_IPSEC_IKE_INVALID_SIGNATURE	Failed to verify signature.
0x00003603 ERROR_IPSEC_IKE_KERBEROS_ERROR	Failed to authenticate using Kerberos.
0x00003604 ERROR_IPSEC_IKE_NO_PUBLIC_KEY	The peer's certificate did not have a public key.
0x00003605 ERROR_IPSEC_IKE_PROCESS_ERR	Error processing the error payload.
0x00003606 ERROR_IPSEC_IKE_PROCESS_ERR_SA	Error processing the SA payload.
0x00003607 ERROR_IPSEC_IKE_PROCESS_ERR_PROP	Error processing the proposal payload.
0x00003608 ERROR_IPSEC_IKE_PROCESS_ERR_TRANS	Error processing the transform payload.
0x00003609 ERROR_IPSEC_IKE_PROCESS_ERR_KEY	Error processing the key exchange payload.
0x0000360A ERROR_IPSEC_IKE_PROCESS_ERR_ID	Error processing the ID payload.
0x0000360B ERROR_IPSEC_IKE_PROCESS_ERR_CERT	Error processing the certification payload.



Win32 error codes	Description
0x0000360C ERROR_IPSEC_IKE_PROCESS_ERR_CERT_REQ	Error processing the certificate request payload.
0x0000360D ERROR_IPSEC_IKE_PROCESS_ERR_HASH	Error processing the hash payload.
0x0000360E ERROR_IPSEC_IKE_PROCESS_ERR_SIG	Error processing the signature payload.
0x0000360F ERROR_IPSEC_IKE_PROCESS_ERR_NONCE	Error processing the nonce payload.
0x00003610 ERROR_IPSEC_IKE_PROCESS_ERR_NOTIFY	Error processing the notify payload.
0x00003611 ERROR_IPSEC_IKE_PROCESS_ERR_DELETE	Error processing the delete payload.
0x00003612 ERROR_IPSEC_IKE_PROCESS_ERR_VENDOR	Error processing the VendorId payload.
0x00003613 ERROR_IPSEC_IKE_INVALID_PAYLOAD	Invalid payload received.
0x00003614 ERROR_IPSEC_IKE_LOAD_SOFT_SA	Soft SA loaded.
0x00003615 ERROR_IPSEC_IKE_SOFT_SA_TORN_DOWN	Soft SA torn down.
0x00003616 ERROR_IPSEC_IKE_INVALID_COOKIE	Invalid cookie received.
0x00003617 ERROR_IPSEC_IKE_NO_PEER_CERT	Peer failed to send valid machine certificate.
0x00003618 ERROR_IPSEC_IKE_PEER_CRL_FAILED	Certification revocation check of peer's certificate failed.
0x00003619 ERROR_IPSEC_IKE_POLICY_CHANGE	New policy invalidated SAs formed with the old policy.
0x0000361A ERROR_IPSEC_IKE_NO_MM_POLICY	There is no available main mode IKE policy.
0x0000361B ERROR_IPSEC_IKE_NOTCBPRIV	Failed to enable trusted computer base (TCB) privilege.
0x0000361C ERROR_IPSEC_IKE_SECLOADFAIL	Failed to load SECURITY.DLL.
0x0000361D ERROR_IPSEC_IKE_FAILSSPINIT	Failed to obtain the security function table dispatch address from the SSPI.
0x0000361E ERROR_IPSEC_IKE_FAILQUERYSSP	Failed to query the Kerberos package to obtain the max token size.
0x0000361F	Failed to obtain the Kerberos server credentials

Win32 error codes	Description
ERROR_IPSEC_IKE_SRVACQFAIL	for the Internet Security Association and Key Management Protocol (ISAKMP)/ERROR_IPSEC_IKE service. Kerberos authentication will not function. The most likely reason for this is lack of domain membership. This is normal if your computer is a member of a workgroup.
0x00003620 ERROR_IPSEC_IKE_SRVQUERYCRED	Failed to determine the SSPI principal name for ISAKMP/ERROR_IPSEC_IKE service (QueryCredentialsAttributes).
0x00003621 ERROR_IPSEC_IKE_GETSPIFAIL	Failed to obtain a new service provider interface (SPI) for the inbound SA from the IPsec driver. The most common cause for this is that the driver does not have the correct filter. Check your policy to verify the filters.
0x00003622 ERROR_IPSEC_IKE_INVALID_FILTER	Given filter is invalid
0x00003623 ERROR_IPSEC_IKE_OUT_OF_MEMORY	Memory allocation failed.
0x00003624 ERROR_IPSEC_IKE_ADD_UPDATE_KEY_FAILED	Failed to add an SA to the IPsec driver. The most common cause for this is if the IKE negotiation took too long to complete. If the problem persists, reduce the load on the faulting machine.
0x00003625 ERROR_IPSEC_IKE_INVALID_POLICY	Invalid policy.
0x00003626 ERROR_IPSEC_IKE_UNKNOWN_DOI	Invalid digital object identifier (DOI).
0x00003627 ERROR_IPSEC_IKE_INVALID_SITUATION	Invalid situation.
0x00003628 ERROR_IPSEC_IKE_DH_FAILURE	Diffie-Hellman failure.
0x00003629 ERROR_IPSEC_IKE_INVALID_GROUP	Invalid Diffie-Hellman group.
0x0000362A ERROR_IPSEC_IKE_ENCRYPT	Error encrypting payload.
0x0000362B ERROR_IPSEC_IKE_DECRYPT	Error decrypting payload.
0x0000362C ERROR_IPSEC_IKE_POLICY_MATCH	Policy match error.
0x0000362D ERROR_IPSEC_IKE_UNSUPPORTED_ID	Unsupported ID.
0x0000362E	Hash verification failed.

Win32 error codes	Description
ERROR_IPSEC_IKE_INVALID_HASH	
0x0000362F ERROR_IPSEC_IKE_INVALID_HASH_ALG	Invalid hash algorithm.
0x00003630 ERROR_IPSEC_IKE_INVALID_HASH_SIZE	Invalid hash size.
0x00003631 ERROR_IPSEC_IKE_INVALID_ENCRYPT_ALG	Invalid encryption algorithm.
0x00003632 ERROR_IPSEC_IKE_INVALID_AUTH_ALG	Invalid authentication algorithm.
0x00003633 ERROR_IPSEC_IKE_INVALID_SIG	Invalid certificate signature.
0x00003634 ERROR_IPSEC_IKE_LOAD_FAILED	Load failed.
0x00003635 ERROR_IPSEC_IKE_RPC_DELETE	Deleted by using an RPC call.
0x00003636 ERROR_IPSEC_IKE_BENIGN_REINIT	A temporary state was created to perform reinitialization. This is not a real failure.
0x00003637 ERROR_IPSEC_IKE_INVALID_RESPONDER_LIFETIME_NOTIFY	The lifetime value received in the Responder Lifetime Notify is below the Windows 2000 configured minimum value. Fix the policy on the peer machine.
0x00003639 ERROR_IPSEC_IKE_INVALID_CERT_KEYLEN	Key length in the certificate is too small for configured security requirements.
0x0000363A ERROR_IPSEC_IKE_MM_LIMIT	Maximum number of established MM SAs to peer exceeded.
0x0000363B ERROR_IPSEC_IKE_NEGOTIATION_DISABLED	The IKE received a policy that disables negotiation.
0x0000363C ERROR_IPSEC_IKE_QM_LIMIT	Reached maximum quick mode limit for the main mode. New main mode will be started.
0x0000363D ERROR_IPSEC_IKE_MM_EXPIRED	Main mode SA lifetime expired or the peer sent a main mode delete.
0x0000363E ERROR_IPSEC_IKE_PEER_MM_ASSUMED_INVALID	Main mode SA assumed to be invalid because peer stopped responding.
0x0000363F ERROR_IPSEC_IKE_CERT_CHAIN_POLICY_MISMATCH	Certificate does not chain to a trusted root in IPsec policy.
0x00003640 ERROR_IPSEC_IKE_UNEXPECTED_MESSAGE_ID	Received unexpected message ID.
0x00003641 ERROR_IPSEC_IKE_INVALID_UMATTS	Received invalid AuthIP user mode attributes.

Win32 error codes	Description
0x00003642 ERROR_IPSEC_IKE_DOS_COOKIE_SENT	Sent DOS cookie notify to initiator.
0x00003643 ERROR_IPSEC_IKE_SHUTTING_DOWN	The IKE service is shutting down.
0x00003644 ERROR_IPSEC_IKE_CGA_AUTH_FAILED	Could not verify the binding between the color graphics adaptor (CGA) address and the certificate.
0x00003645 ERROR_IPSEC_IKE_PROCESS_ERR_NATOA	Error processing the NatOA payload.
0x00003646 ERROR_IPSEC_IKE_INVALID_MM_FOR_QM	The parameters of the main mode are invalid for this quick mode.
0x00003647 ERROR_IPSEC_IKE_QM_EXPIRED	The quick mode SA was expired by the IPsec driver.
0x00003648 ERROR_IPSEC_IKE_TOO_MANY_FILTERS	Too many dynamically added IKEEXT filters were detected.
0x00003649 ERROR_IPSEC_IKE_NEG_STATUS_END	ERROR_IPSEC_IKE_NEG_STATUS_END
0x000036B0 ERROR_SXS_SECTION_NOT_FOUND	The requested section was not present in the activation context.
0x000036B1 ERROR_SXS_CANT_GEN_ACTCTX	The application has failed to start because its side-by-side configuration is incorrect. See the application event log for more detail.
0x000036B2 ERROR_SXS_INVALID_ACTCTXDATA_FORMAT	The application binding data format is invalid.
0x000036B3 ERROR_SXS_ASSEMBLY_NOT_FOUND	The referenced assembly is not installed on your system.
0x000036B4 ERROR_SXS_MANIFEST_FORMAT_ERROR	The manifest file does not begin with the required tag and format information.
0x000036B5 ERROR_SXS_MANIFEST_PARSE_ERROR	The manifest file contains one or more syntax errors.
0x000036B6 ERROR_SXS_ACTIVATION_CONTEXT_DISABLED	The application attempted to activate a disabled activation context.
0x000036B7 ERROR_SXS_KEY_NOT_FOUND	The requested lookup key was not found in any active activation context.
0x000036B8 ERROR_SXS_VERSION_CONFLICT	A component version required by the application conflicts with another active component version.
0x000036B9 ERROR_SXS_WRONG_SECTION_TYPE	The type requested activation context section does not match the query API used.
0x000036BA	Lack of system resources has required isolated

Win32 error codes	Description
ERROR_SXS_THREAD_QUERIES_DISABLED	activation to be disabled for the current thread of execution.
0x000036BB ERROR_SXS_PROCESS_DEFAULT_ALREADY_SET	An attempt to set the process default activation context failed because the process default activation context was already set.
0x000036BC ERROR_SXS_UNKNOWN_ENCODING_GROUP	The encoding group identifier specified is not recognized.
0x000036BD ERROR_SXS_UNKNOWN_ENCODING	The encoding requested is not recognized.
0x000036BE ERROR_SXS_INVALID_XML_NAMESPACE_URI	The manifest contains a reference to an invalid URI.
0x000036BF ERROR_SXS_ROOT_MANIFEST_DEPENDENCY_NOT_INSTALLED	The application manifest contains a reference to a dependent assembly that is not installed.
0x000036C0 ERROR_SXS_LEAF_MANIFEST_DEPENDENCY_NOT_INSTALLED	The manifest for an assembly used by the application has a reference to a dependent assembly that is not installed.
0x000036C1 ERROR_SXS_INVALID_ASSEMBLY_IDENTITY_ATTRIBUTE	The manifest contains an attribute for the assembly identity that is not valid.
0x000036C2 ERROR_SXS_MANIFEST_MISSING_REQUIRED_DEFAULT_NAMESPACE	The manifest is missing the required default namespace specification on the assembly element.
0x000036C3 ERROR_SXS_MANIFEST_INVALID_REQUIRED_DEFAULT_NAMESPACE	The manifest has a default namespace specified on the assembly element but its value is not urn:schemas-microsoft-com:asm.v1".
0x000036C4 ERROR_SXS_PRIVATE_MANIFEST_CROSS_PATH_WITH_REPARSE_POINT	The private manifest probed has crossed the reparse-point-associated path.
0x000036C5 ERROR_SXS_DUPLICATE_DLL_NAME	Two or more components referenced directly or indirectly by the application manifest have files by the same name.
0x000036C6 ERROR_SXS_DUPLICATE_WINDOWCLASS_NAME	Two or more components referenced directly or indirectly by the application manifest have window classes with the same name.
0x000036C7 ERROR_SXS_DUPLICATE_CLSID	Two or more components referenced directly or indirectly by the application manifest have the same COM server CLSIDs.
0x000036C8 ERROR_SXS_DUPLICATE_IID	Two or more components referenced directly or indirectly by the application manifest have proxies for the same COM interface IIDs.
0x000036C9 ERROR_SXS_DUPLICATE_TLBID	Two or more components referenced directly or indirectly by the application manifest have the

Win32 error codes	Description
	same COM type library TLBIDs.
0x000036CA ERROR_SXS_DUPLICATE_PROGID	Two or more components referenced directly or indirectly by the application manifest have the same COM ProgIDs.
0x000036CB ERROR_SXS_DUPLICATE_ASSEMBLY_NAME	Two or more components referenced directly or indirectly by the application manifest are different versions of the same component, which is not permitted.
0x000036CC ERROR_SXS_FILE_HASH_MISMATCH	A component's file does not match the verification information present in the component manifest.
0x000036CD ERROR_SXS_POLICY_PARSE_ERROR	The policy manifest contains one or more syntax errors.
0x000036CE ERROR_SXS_XML_E_MISSINGQUOTE	Manifest Parse Error: A string literal was expected, but no opening quotation mark was found.
0x000036CF ERROR_SXS_XML_E_COMMENTSYNTAX	Manifest Parse Error: Incorrect syntax was used in a comment.
0x000036D0 ERROR_SXS_XML_E_BADSTARTNAMECHAR	Manifest Parse Error: A name started with an invalid character.
0x000036D1 ERROR_SXS_XML_E_BADNAMECHAR	Manifest Parse Error: A name contained an invalid character.
0x000036D2 ERROR_SXS_XML_E_BADCHARINSTRING	Manifest Parse Error: A string literal contained an invalid character.
0x000036D3 ERROR_SXS_XML_E_XMLDECLSYNTAX	Manifest Parse Error: Invalid syntax for an XML declaration.
0x000036D4 ERROR_SXS_XML_E_BADCHARDATA	Manifest Parse Error: An Invalid character was found in text content.
0x000036D5 ERROR_SXS_XML_E_MISSINGWHITESPACE	Manifest Parse Error: Required white space was missing.
0x000036D6 ERROR_SXS_XML_E_EXPECTINGTAGEND	Manifest Parse Error: The angle bracket (>) character was expected.
0x000036D7 ERROR_SXS_XML_E_MISSINGSEMICOLON	Manifest Parse Error: A semicolon (;) was expected.
0x000036D8 ERROR_SXS_XML_E_UNBALANCEDPAREN	Manifest Parse Error: Unbalanced parentheses.
0x000036D9 ERROR_SXS_XML_E_INTERNALERROR	Manifest Parse Error: Internal error.
0x000036DA ERROR_SXS_XML_E_UNEXPECTED_WHITESPACE	Manifest Parse Error: Whitespace is not allowed at this location.

Win32 error codes	Description
0x000036DB ERROR_SXS_XML_E_INCOMPLETE_ENCODING	Manifest Parse Error: End of file reached in invalid state for current encoding.
0x000036DC ERROR_SXS_XML_E_MISSING_PAREN	Manifest Parse Error: Missing parenthesis.
0x000036DD ERROR_SXS_XML_E_EXPECTINGCLOSEQUOTE	Manifest Parse Error: A single (') or double (") quotation mark is missing.
0x000036DE ERROR_SXS_XML_E_MULTIPLE_COLONS	Manifest Parse Error: Multiple colons are not allowed in a name.
0x000036DF ERROR_SXS_XML_E_INVALID_DECIMAL	Manifest Parse Error: Invalid character for decimal digit.
0x000036E0 ERROR_SXS_XML_E_INVALID_HEXIDECIMAL	Manifest Parse Error: Invalid character for hexadecimal digit.
0x000036E1 ERROR_SXS_XML_E_INVALID_UNICODE	Manifest Parse Error: Invalid Unicode character value for this platform.
0x000036E2 ERROR_SXS_XML_E_WHITESPACEORQUESTIONMARK	Manifest Parse Error: Expecting whitespace or question mark (?).
0x000036E3 ERROR_SXS_XML_E_UNEXPECTEDENDTAG	Manifest Parse Error: End tag was not expected at this location.
0x000036E4 ERROR_SXS_XML_E_UNCLOSEDTAG	Manifest Parse Error: The following tags were not closed: %1.
0x000036E5 ERROR_SXS_XML_E_DUPLICATEATTRIBUTE	Manifest Parse Error: Duplicate attribute.
0x000036E6 ERROR_SXS_XML_E_MULTIPLEROOTS	Manifest Parse Error: Only one top-level element is allowed in an XML document.
0x000036E7 ERROR_SXS_XML_E_INVALIDATROOTLEVEL	Manifest Parse Error: Invalid at the top level of the document.
0x000036E8 ERROR_SXS_XML_E_BADXMLDECL	Manifest Parse Error: Invalid XML declaration.
0x000036E9 ERROR_SXS_XML_E_MISSINGROOT	Manifest Parse Error: XML document must have a top-level element.
0x000036EA ERROR_SXS_XML_E_UNEXPECTEDEOF	Manifest Parse Error: Unexpected end of file.
0x000036EB ERROR_SXS_XML_E_BADPEREFINSUBSET	Manifest Parse Error: Parameter entities cannot be used inside markup declarations in an internal subset.
0x000036EC ERROR_SXS_XML_E_UNCLOSEDSTARTTAG	Manifest Parse Error: Element was not closed.
0x000036ED ERROR_SXS_XML_E_UNCLOSEDENDTAG	Manifest Parse Error: End element was missing the angle bracket (>) character.

Win32 error codes	Description
0x000036EE ERROR_SXS_XML_E_UNCLOSEDSTRING	Manifest Parse Error: A string literal was not closed.
0x000036EF ERROR_SXS_XML_E_UNCLOSEDCOMMENT	Manifest Parse Error: A comment was not closed.
0x000036F0 ERROR_SXS_XML_E_UNCLOSEDDECL	Manifest Parse Error: A declaration was not closed.
0x000036F1 ERROR_SXS_XML_E_UNCLOSEDCDATA	Manifest Parse Error: A CDATA section was not closed.
0x000036F2 ERROR_SXS_XML_E_RESERVEDNAMESPACE	Manifest Parse Error: The namespace prefix is not allowed to start with the reserved string "xml".
0x000036F3 ERROR_SXS_XML_E_INVALIDENCODING	Manifest Parse Error: System does not support the specified encoding.
0x000036F4 ERROR_SXS_XML_E_INVALIDSWITCH	Manifest Parse Error: Switch from current encoding to specified encoding not supported.
0x000036F5 ERROR_SXS_XML_E_BADXMLCASE	Manifest Parse Error: The name "xml" is reserved and must be lowercase.
0x000036F6 ERROR_SXS_XML_E_INVALID_STANDALONE	Manifest Parse Error: The stand-alone attribute must have the value "yes" or "no".
0x000036F7 ERROR_SXS_XML_E_UNEXPECTED_STANDALONE	Manifest Parse Error: The stand-alone attribute cannot be used in external entities.
0x000036F8 ERROR_SXS_XML_E_INVALID_VERSION	Manifest Parse Error: Invalid version number.
0x000036F9 ERROR_SXS_XML_E_MISSINGEQUALS	Manifest Parse Error: Missing equal sign (=) between the attribute and the attribute value.
0x000036FA ERROR_SXS_PROTECTION_RECOVERY_FAILED	Assembly Protection Error: Unable to recover the specified assembly.
0x000036FB ERROR_SXS_PROTECTION_PUBLIC_KEY_OO_SHORT	Assembly Protection Error: The public key for an assembly was too short to be allowed.
0x000036FC ERROR_SXS_PROTECTION_CATALOG_NOT_VALID	Assembly Protection Error: The catalog for an assembly is not valid, or does not match the assembly's manifest.
0x000036FD ERROR_SXS_UNTRANSLATABLE_HRESULT	An HRESULT could not be translated to a corresponding Win32 error code.
0x000036FE ERROR_SXS_PROTECTION_CATALOG_FILE_MISSING	Assembly Protection Error: The catalog for an assembly is missing.
0x000036FF ERROR_SXS_MISSING_ASSEMBLY_IDENTITY_ATTRIBUTE	The supplied assembly identity is missing one or more attributes that must be present in this context.
0x00003700	The supplied assembly identity has one or



Win32 error codes	Description
ERROR_SXS_INVALID_ASSEMBLY_IDENTITY_ATTRIBUTE_NAME	more attribute names that contain characters not permitted in XML names.
0x00003701 ERROR_SXS_ASSEMBLY_MISSING	The referenced assembly could not be found.
0x00003702 ERROR_SXS_CORRUPT_ACTIVATION_STACK	The activation context activation stack for the running thread of execution is corrupt.
0x00003703 ERROR_SXS_CORRUPTION	The application isolation metadata for this process or thread has become corrupt.
0x00003704 ERROR_SXS_EARLY_DEACTIVATION	The activation context being deactivated is not the most recently activated one.
0x00003705 ERROR_SXS_INVALID_DEACTIVATION	The activation context being deactivated is not active for the current thread of execution.
0x00003706 ERROR_SXS_MULTIPLE_DEACTIVATION	The activation context being deactivated has already been deactivated.
0x00003707 ERROR_SXS_PROCESS_TERMINATION_REQUESTED	A component used by the isolation facility has requested to terminate the process.
0x00003708 ERROR_SXS_RELEASE_ACTIVATION_ONTEXT	A kernel mode component is releasing a reference on an activation context.
0x00003709 ERROR_SXS_SYSTEM_DEFAULT_ACTIVATION_CONTEXT_EMPTY	The activation context of the system default assembly could not be generated.
0x0000370A ERROR_SXS_INVALID_IDENTITY_ATTRIBUTE_VALUE	The value of an attribute in an identity is not within the legal range.
0x0000370B ERROR_SXS_INVALID_IDENTITY_ATTRIBUTE_NAME	The name of an attribute in an identity is not within the legal range.
0x0000370C ERROR_SXS_IDENTITY_DUPLICATE_ATTRIBUTE	An identity contains two definitions for the same attribute.
0x0000370D ERROR_SXS_IDENTITY_PARSE_ERROR	The identity string is malformed. This may be due to a trailing comma, more than two unnamed attributes, a missing attribute name, or a missing attribute value.
0x0000370E ERROR_MALFORMED_SUBSTITUTION_STRING	A string containing localized substitutable content was malformed. Either a dollar sign (\$) was followed by something other than a left parenthesis or another dollar sign, or a substitution's right parenthesis was not found.
0x0000370F ERROR_SXS_INCORRECT_PUBLIC_KEY_OKEN	The public key token does not correspond to the public key specified.
0x00003710 ERROR_UNMAPPED_SUBSTITUTION_STRING	A substitution string had no mapping.
0x00003711	The component must be locked before making

Win32 error codes	Description
ERROR_SXS_ASSEMBLY_NOT_LOCKED	the request.
0x00003712 ERROR_SXS_COMPONENT_STORE_CORRUPT	The component store has been corrupted.
0x00003713 ERROR_ADVANCED_INSTALLER_FAILED	An advanced installer failed during setup or servicing.
0x00003714 ERROR_XML_ENCODING_MISMATCH	The character encoding in the XML declaration did not match the encoding used in the document.
0x00003715 ERROR_SXS_MANIFEST_IDENTITY_SAME_BUT_CONTENTS_DIFFERENT	The identities of the manifests are identical, but the contents are different.
0x00003716 ERROR_SXS_IDENTITIES_DIFFERENT	The component identities are different.
0x00003717 ERROR_SXS_ASSEMBLY_IS_NOT_A_DEPLOYMENT	The assembly is not a deployment.
0x00003718 ERROR_SXS_FILE_NOT_PART_OF_ASSEMBLY	The file is not a part of the assembly.
0x00003719 ERROR_SXS_MANIFEST_TOO_BIG	The size of the manifest exceeds the maximum allowed.
0x0000371A ERROR_SXS_SETTING_NOT_REGISTERED	The setting is not registered.
0x0000371B ERROR_SXS_TRANSACTION_CLOSURE_INCOMPLETE	One or more required members of the transaction are not present.
0x00003A98 ERROR_EVT_INVALID_CHANNEL_PATH	The specified channel path is invalid.
0x00003A99 ERROR_EVT_INVALID_QUERY	The specified query is invalid.
0x00003A9A ERROR_EVT_PUBLISHER_METADATA_NOT_FOUND	The publisher metadata cannot be found in the resource.
0x00003A9B ERROR_EVT_EVENT_TEMPLATE_NOT_FOUND	The template for an event definition cannot be found in the resource (error = %1).
0x00003A9C ERROR_EVT_INVALID_PUBLISHER_NAME	The specified publisher name is invalid.
0x00003A9D ERROR_EVT_INVALID_EVENT_DATA	The event data raised by the publisher is not compatible with the event template definition in the publisher's manifest.
0x00003A9F ERROR_EVT_CHANNEL_NOT_FOUND	The specified channel could not be found. Check channel configuration.
0x00003AA0 ERROR_EVT_MALFORMED_XML_TEXT	The specified XML text was not well-formed. See extended error for more details.

Win32 error codes	Description
0x00003AA1 ERROR_EVT_SUBSCRIPTION_TO_DIRECT_CHANNEL	The caller is trying to subscribe to a direct channel which is not allowed. The events for a direct channel go directly to a log file and cannot be subscribed to.
0x00003AA2 ERROR_EVT_CONFIGURATION_ERROR	Configuration error.
0x00003AA3 ERROR_EVT_QUERY_RESULT_STALE	The query result is stale or invalid. This may be due to the log being cleared or rolling over after the query result was created. Users should handle this code by releasing the query result object and reissuing the query.
0x00003AA4 ERROR_EVT_QUERY_RESULT_INVALID_POSITION	Query result is currently at an invalid position.
0x00003AA5 ERROR_EVT_NON_VALIDATING_MSXML	Registered Microsoft XML (MSXML) does not support validation.
0x00003AA6 ERROR_EVT_FILTER_ALREADYSCOPED	An expression can only be followed by a change-of-scope operation if it itself evaluates to a node set and is not already part of some other change-of-scope operation.
0x00003AA7 ERROR_EVT_FILTER_NOTELTSET	Cannot perform a step operation from a term that does not represent an element set.
0x00003AA8 ERROR_EVT_FILTER_INVARG	Left side arguments to binary operators must be either attributes, nodes, or variables and right side arguments must be constants.
0x00003AA9 ERROR_EVT_FILTER_INVTEST	A step operation must involve either a node test or, in the case of a predicate, an algebraic expression against which to test each node in the node set identified by the preceding node set can be evaluated.
0x00003AAA ERROR_EVT_FILTER_INVTYPE	This data type is currently unsupported.
0x00003AAB ERROR_EVT_FILTER_PARSEERR	A syntax error occurred at position %1d!
0x00003AAC ERROR_EVT_FILTER_UNSUPPORTEDOP	This operator is unsupported by this implementation of the filter.
0x00003AAD ERROR_EVT_FILTER_UNEXPECTEDTOKEN	The token encountered was unexpected.
0x00003AAE ERROR_EVT_INVALID_OPERATION_OVER_ENABLED_DIRECT_CHANNEL	The requested operation cannot be performed over an enabled direct channel. The channel must first be disabled before performing the requested operation.
0x00003AAF ERROR_EVT_INVALID_CHANNEL_PROPERTY_VALUE	Channel property %1!s! contains an invalid value. The value has an invalid type, is outside the valid range, cannot be updated, or is not

Win32 error codes	Description
	supported by this type of channel.
0x00003AB0 ERROR_EVT_INVALID_PUBLISHER_PROPERTY_VALUE	Publisher property %1!s! contains an invalid value. The value has an invalid type, is outside the valid range, cannot be updated, or is not supported by this type of publisher.
0x00003AB1 ERROR_EVT_CHANNEL_CANNOT_ACTIVATE	The channel fails to activate.
0x00003AB2 ERROR_EVT_FILTER_TOO_COMPLEX	The xpath expression exceeded supported complexity. Simplify it or split it into two or more simple expressions.
0x00003AB3 ERROR_EVT_MESSAGE_NOT_FOUND	The message resource is present but the message is not found in the string or message table.
0x00003AB4 ERROR_EVT_MESSAGE_ID_NOT_FOUND	The message ID for the desired message could not be found.
0x00003AB5 ERROR_EVT_UNRESOLVED_VALUE_INSERT	The substitution string for the insert index (%1) could not be found.
0x00003AB6 ERROR_EVT_UNRESOLVED_PARAMETER_INSERT	The description string for the parameter reference (%1) could not be found.
0x00003AB7 ERROR_EVT_MAX_INSERTS_REACHED	The maximum number of replacements has been reached.
0x00003AB8 ERROR_EVT_EVENT_DEFINITION_NOT_FOUND	The event definition could not be found for the event ID (%1).
0x00003AB9 ERROR_EVT_MESSAGE_LOCALE_NOT_FOUND	The locale-specific resource for the desired message is not present.
0x00003ABA ERROR_EVT_VERSION_TOO_OLD	The resource is too old to be compatible.
0x00003ABB ERROR_EVT_VERSION_TOO_NEW	The resource is too new to be compatible.
0x00003ABC ERROR_EVT_CANNOT_OPEN_CHANNEL_OF_QUERY	The channel at index %1 of the query cannot be opened.
0x00003ABD ERROR_EVT_PUBLISHER_DISABLED	The publisher has been disabled and its resource is not available. This usually occurs when the publisher is in the process of being uninstalled or upgraded.
0x00003AE8 ERROR_EC_SUBSCRIPTION_CANNOT_ACTIVATE	The subscription fails to activate.
0x00003AE9 ERROR_EC_LOG_DISABLED	The log of the subscription is in a disabled state and events cannot be forwarded to it. The log must first be enabled before the subscription can be activated.

Win32 error codes	Description
0x00003AFC ERROR_MUI_FILE_NOT_FOUND	The resource loader failed to find the Multilingual User Interface (MUI) file.
0x00003AFD ERROR_MUI_INVALID_FILE	The resource loader failed to load the MUI file because the file failed to pass validation.
0x00003AFE ERROR_MUI_INVALID_RC_CONFIG	The release candidate (RC) manifest is corrupted with garbage data, is an unsupported version, or is missing a required item.
0x00003AFF ERROR_MUI_INVALID_LOCALE_NAME	The RC manifest has an invalid culture name.
0x00003B00 ERROR_MUI_INVALID_ULTIMATEFALLBACK_NAME	The RC Manifest has an invalid ultimate fallback name.
0x00003B01 ERROR_MUI_FILE_NOT_LOADED	The resource loader cache does not have a loaded MUI entry.
0x00003B02 ERROR_RESOURCE_ENUM_USER_STOP	The user stopped resource enumeration.
0x00003B03 ERROR_MUI_INTLSETTINGS_UILANG_NOT_INSTALLED	User interface language installation failed.
0x00003B04 ERROR_MUI_INTLSETTINGS_INVALID_LOCALE_NAME	Locale installation failed.
0x00003B60 ERROR_MCA_INVALID_CAPABILITIES_STRING	The monitor returned a DDC/CI capabilities string that did not comply with the ACCESS.bus 3.0, DDC/CI 1.1, or MCCS 2 Revision 1 specification.
0x00003B61 ERROR_MCA_INVALID_VCP_VERSION	The monitor's VCP version (0xDF) VCP code returned an invalid version value.
0x00003B62 ERROR_MCA_MONITOR_VIOLATES_MCCS_SPECIFICATION	The monitor does not comply with the MCCS specification it claims to support.
0x00003B63 ERROR_MCA_MCCS_VERSION_MISMATCH	The MCCS version in a monitor's mcs_ver capability does not match the MCCS version the monitor reports when the VCP version (0xDF) VCP code is used.
0x00003B64 ERROR_MCA_UNSUPPORTED_MCCS_VERSION	The monitor configuration API works only with monitors that support the MCCS 1.0, MCCS 2.0, or MCCS 2.0 Revision 1 specifications.
0x00003B65 ERROR_MCA_INTERNAL_ERROR	An internal monitor configuration API error occurred.
0x00003B66 ERROR_MCA_INVALID_TECHNOLOGY_TYPE_RETURNED	The monitor returned an invalid monitor technology type. CRT, plasma, and LCD (TFT) are examples of monitor technology types. This error implies that the monitor violated the MCCS 2.0 or MCCS 2.0 Revision 1 specification.

Win32 error codes	Description
0x00003B67 ERROR_MCA_UNSUPPORTED_COLOR_TEMPERATURE	The SetMonitorColorTemperature() caller passed a color temperature to it that the current monitor did not support. CRT, plasma, and LCD (TFT) are examples of monitor technology types. This error implies that the monitor violated the MCCS 2.0 or MCCS 2.0 Revision 1 specification.
0x00003B92 ERROR_AMBIGUOUS_SYSTEM_DEVICE	The requested system device cannot be identified due to multiple indistinguishable devices potentially matching the identification criteria.
0x00003BC3 ERROR_SYSTEM_DEVICE_NOT_FOUND	The requested system device cannot be found.

## 2.3 NTSTATUS Values

Values are 32 bit and are laid out as follows. The following diagram is independent of endianness; that is, the diagram is shown in host byte order and merely shows the layout of the numbering space.

Any protocol that uses NTSTATUS values on the wire is responsible for stating the order that the bytes are placed on the wire.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
Sev	C	R	Facility													Code															

**Sev:** Severity. Severity codes are as follows.

Value	Meaning
STATUS_SEVERITY_SUCCESS 00	Success
STATUS_SEVERITY_INFORMATIONAL 01	Informational
STATUS_SEVERITY_WARNING 10	Warning
STATUS_SEVERITY_ERROR 11	Error

**C:** Customer. This specifies if the value is customer- or Microsoft-defined. This bit is set for customer-defined values and clear for Microsoft-defined values. [<3>](#)

**R:** Reserved. MUST be set to 0 so that it is possible to map an NTSTATUS value to an equivalent [HRESULT value](#), as specified in section [2.1](#), by setting this bit.

**Facility:** A value that, together with the C bit, indicates the numbering space to use for the **Code** field. <4>

**Code:** The remainder of the error code. Vendors SHOULD reuse the values in the following table with their indicated meaning or define their own values with the C bit set. Choosing any other value with the C bit clear runs the risk of a collision in the future.

By combining the previous fields into a single 32-bit numbering space, the following NTSTATUS values are defined. Most values also have a defined default message that can be used to map the value to a human-readable text message. When this is done, the NTSTATUS value is also known as a message identifier.

In the following descriptions, a percentage sign that is followed by one or more alphanumeric characters (for example, "%1" or "%hs") indicates a variable that is replaced by text at the time the value is returned.

Value	Meaning
STATUS_SUCCESS 0x00000000	The operation completed successfully.
STATUS_WAIT_0 0x00000000	STATUS_WAIT_0
STATUS_WAIT_1 0x00000001	STATUS_WAIT_1
STATUS_WAIT_2 0x00000002	STATUS_WAIT_2
STATUS_WAIT_3 0x00000003	STATUS_WAIT_3
STATUS_WAIT_63 0x0000003F	STATUS_WAIT_63
STATUS_ABANDONED 0x00000080	STATUS_ABANDONED
STATUS_ABANDONED_WAIT_0 0x00000080	STATUS_ABANDONED_WAIT_0
STATUS_ABANDONED_WAIT_63 0x000000BF	STATUS_ABANDONED_WAIT_63
STATUS_USER_APC 0x000000C0	STATUS_USER_APC
STATUS_KERNEL_APC 0x00000100	STATUS_KERNEL_APC
STATUS_ALERTED 0x00000101	STATUS_ALERTED
STATUS_TIMEOUT	STATUS_TIMEOUT

Value	Meaning
0x00000102	
STATUS_PENDING 0x00000103	The operation that was requested is pending completion.
STATUS_REPARSE 0x00000104	A reparse should be performed by the Object Manager because the name of the file resulted in a symbolic link.
STATUS_MORE_ENTRIES 0x00000105	Returned by enumeration APIs to indicate more information is available to successive calls.
STATUS_NOT_ALL_ASSIGNED 0x00000106	Indicates not all privileges or groups that are referenced are assigned to the caller. This allows, for example, all privileges to be disabled without having to know exactly which privileges are assigned.
STATUS_SOME_NOT_MAPPED 0x00000107	Some of the information to be translated has not been translated.
STATUS_OPLOCK_BREAK_IN_PROGRESS 0x00000108	An open/create operation completed while an opportunistic lock (oplock) break is underway.
STATUS_VOLUME_MOUNTED 0x00000109	A new volume has been mounted by a file system.
STATUS_RXACT_COMMITTED 0x0000010A	This success level status indicates that the transaction state already exists for the registry subtree but that a transaction commit was previously aborted. The commit has now been completed.
STATUS_NOTIFY_CLEANUP 0x0000010B	Indicates that a notify change request has been completed due to closing the handle that made the notify change request.
STATUS_NOTIFY_ENUM_DIR 0x0000010C	Indicates that a notify change request is being completed and that the information is not being returned in the caller's buffer. The caller now needs to enumerate the files to find the changes.
STATUS_NO_QUOTAS_FOR_ACCOUNT 0x0000010D	{No Quotas} No system quota limits are specifically set for this account.
STATUS_PRIMARY_TRANSPORT_CONNECT_FAILED 0x0000010E	{Connect Failure on Primary Transport} An attempt was made to connect to the remote server %hs on the primary transport, but the connection failed. The computer WAS able to connect on a secondary transport.



Value	Meaning
STATUS_PAGE_FAULT_TRANSITION 0x00000110	The page fault was a transition fault.
STATUS_PAGE_FAULT_DEMAND_ZERO 0x00000111	The page fault was a demand zero fault.
STATUS_PAGE_FAULT_COPY_ON_WRITE 0x00000112	The page fault was a demand zero fault.
STATUS_PAGE_FAULT_GUARD_PAGE 0x00000113	The page fault was a demand zero fault.
STATUS_PAGE_FAULT_PAGING_FILE 0x00000114	The page fault was satisfied by reading from a secondary storage device.
STATUS_CACHE_PAGE_LOCKED 0x00000115	The cached page was locked during operation.
STATUS_CRASH_DUMP 0x00000116	The crash dump exists in a paging file.
STATUS_BUFFER_ALL_ZEROS 0x00000117	The specified buffer contains all zeros.
STATUS_REPARSE_OBJECT 0x00000118	A reparse should be performed by the Object Manager because the name of the file resulted in a symbolic link.
STATUS_RESOURCE_REQUIREMENTS_CHANGED 0x00000119	The device has succeeded a query-stop and its resource requirements have changed.
STATUS_TRANSLATION_COMPLETE 0x00000120	The translator has translated these resources into the global space and no additional translations should be performed.
STATUS_DS_MEMBERSHIP_EVALUATED_LOCALLY 0x00000121	The directory service evaluated group memberships locally, because it was unable to contact a global catalog server.
STATUS_NOTHING_TO_TERMINATE 0x00000122	A process being terminated has no threads to terminate.
STATUS_PROCESS_NOT_IN_JOB 0x00000123	The specified process is not part of a job.
STATUS_PROCESS_IN_JOB 0x00000124	The specified process is part of a job.
STATUS_VOLSNAP_HIBERNATE_READY 0x00000125	{Volume Shadow Copy Service} The system is now ready for hibernation.

Value	Meaning
STATUS_FSFILTER_OP_COMPLETED_SUCCESSFULLY 0x00000126	A file system or file system filter driver has successfully completed an FsFilter operation.
STATUS_INTERRUPT_VECTOR_ALREADY_CONNECTED 0x00000127	The specified interrupt vector was already connected.
STATUS_INTERRUPT_STILL_CONNECTED 0x00000128	The specified interrupt vector is still connected.
STATUS_PROCESS_CLONED 0x00000129	The current process is a cloned process.
STATUS_FILE_LOCKED_WITH_ONLY_READERS 0x0000012A	The file was locked and all users of the file can only read.
STATUS_FILE_LOCKED_WITH_WRITERS 0x0000012B	The file was locked and at least one user of the file can write.
STATUS_RESOURCEMANAGER_READ_ONLY 0x00000202	The specified ResourceManager made no changes or updates to the resource under this transaction.
STATUS_WAIT_FOR_OPLOCK 0x00000367	An operation is blocked and waiting for an oplock.
DBG_EXCEPTION_HANDLED 0x00010001	Debugger handled the exception.
DBG_CONTINUE 0x00010002	The debugger continued.
STATUS_FLT_IO_COMPLETE 0x001C0001	The IO was completed by a filter.
STATUS_OBJECT_NAME_EXISTS 0x40000000	{Object Exists} An attempt was made to create an object but the object name already exists.
STATUS_THREAD_WAS_SUSPENDED 0x40000001	{Thread Suspended} A thread termination occurred while the thread was suspended. The thread resumed, and termination proceeded.
STATUS_WORKING_SET_LIMIT_RANGE 0x40000002	{Working Set Range Error} An attempt was made to set the working set minimum or maximum to values that are outside the allowable range.
STATUS_IMAGE_NOT_AT_BASE 0x40000003	{Image Relocated} An image file could not be mapped at the address that is specified in the image file. Local fixes must be performed on this image.
STATUS_RXACT_STATE_CREATED	This informational level status indicates

Value	Meaning
0x40000004	that a specified registry subtree transaction state did not yet exist and had to be created.
STATUS_SEGMENT_NOTIFICATION 0x40000005	{Segment Load} A virtual DOS machine (VDM) is loading, unloading, or moving an MS-DOS or Win16 program segment image. An exception is raised so that a debugger can load, unload, or track symbols and breakpoints within these 16-bit segments.
STATUS_LOCAL_USER_SESSION_KEY 0x40000006	{Local Session Key} A user session key was requested for a local remote procedure call (RPC) connection. The session key that is returned is a constant value and not unique to this connection.
STATUS_BAD_CURRENT_DIRECTORY 0x40000007	{Invalid Current Directory} The process cannot switch to the startup current directory %hs. Select OK to set the current directory to %hs, or select CANCEL to exit.
STATUS_SERIAL_MORE_WRITES 0x40000008	{Serial IOCTL Complete} A serial I/O operation was completed by another write to a serial port. (The IOCTL_SERIAL_XOFF_COUNTER reached zero.)
STATUS_REGISTRY_RECOVERED 0x40000009	{Registry Recovery} One of the files that contains the system registry data had to be recovered by using a log or alternate copy. The recovery was successful.
STATUS_FT_READ_RECOVERY_FROM_BACKUP 0x4000000A	{Redundant Read} To satisfy a read request, the Windows NT fault-tolerant file system successfully read the requested data from a redundant copy. This was done because the file system encountered a failure on a member of the fault-tolerant volume but was unable to reassign the failing area of the device.
STATUS_FT_WRITE_RECOVERY 0x4000000B	{Redundant Write} To satisfy a write request, the Windows NT fault-tolerant file system successfully wrote a redundant copy of the information. This was done because the file system encountered a failure on a member of the fault-tolerant volume but was unable to reassign the failing area of the device.
STATUS_SERIAL_COUNTER_TIMEOUT	{Serial IOCTL Timeout} A serial I/O

Value	Meaning
0x4000000C	operation completed because the time-out period expired. (The IOCTL_SERIAL_XOFF_COUNTER had not reached zero.)
STATUS_NULL_LM_PASSWORD 0x4000000D	{Password Too Complex} The Windows password is too complex to be converted to a LAN Manager password. The LAN Manager password that returned is a NULL string.
STATUS_IMAGE_MACHINE_TYPE_MISMATCH 0x4000000E	{Machine Type Mismatch} The image file %hs is valid but is for a machine type other than the current machine. Select OK to continue, or CANCEL to fail the DLL load.
STATUS_RECEIVE_PARTIAL 0x4000000F	{Partial Data Received} The network transport returned partial data to its client. The remaining data will be sent later.
STATUS_RECEIVE_EXPEDITED 0x40000010	{Expedited Data Received} The network transport returned data to its client that was marked as expedited by the remote system.
STATUS_RECEIVE_PARTIAL_EXPEDITED 0x40000011	{Partial Expedited Data Received} The network transport returned partial data to its client and this data was marked as expedited by the remote system. The remaining data will be sent later.
STATUS_EVENT_DONE 0x40000012	{TDI Event Done} The TDI indication has completed successfully.
STATUS_EVENT_PENDING 0x40000013	{TDI Event Pending} The TDI indication has entered the pending state.
STATUS_CHECKING_FILE_SYSTEM 0x40000014	Checking file system on %wZ.
STATUS_FATAL_APP_EXIT 0x40000015	{Fatal Application Exit} %hs
STATUS_PREDEFINED_HANDLE 0x40000016	The specified registry key is referenced by a predefined handle.
STATUS_WAS_UNLOCKED 0x40000017	{Page Unlocked} The page protection of a locked page was changed to 'No Access' and the page was unlocked from memory and from the process.
STATUS_SERVICE_NOTIFICATION 0x40000018	%hs

Value	Meaning
STATUS_WAS_LOCKED 0x40000019	{Page Locked} One of the pages to lock was already locked.
STATUS_LOG_HARD_ERROR 0x4000001A	Application popup: %1 : %2
STATUS_ALREADY_WIN32 0x4000001B	STATUS_ALREADY_WIN32
STATUS_WX86_UNSIMULATE 0x4000001C	An exception status code that is used by the Win32 x86 emulation subsystem.
STATUS_WX86_CONTINUE 0x4000001D	An exception status code that is used by the Win32 x86 emulation subsystem.
STATUS_WX86_SINGLE_STEP 0x4000001E	An exception status code that is used by the Win32 x86 emulation subsystem.
STATUS_WX86_BREAKPOINT 0x4000001F	An exception status code that is used by the Win32 x86 emulation subsystem.
STATUS_WX86_EXCEPTION_CONTINUE 0x40000020	An exception status code that is used by the Win32 x86 emulation subsystem.
STATUS_WX86_EXCEPTION_LASTCHANCE 0x40000021	An exception status code that is used by the Win32 x86 emulation subsystem.
STATUS_WX86_EXCEPTION_CHAIN 0x40000022	An exception status code that is used by the Win32 x86 emulation subsystem.
STATUS_IMAGE_MACHINE_TYPE_MISMATCH_EXE 0x40000023	{Machine Type Mismatch} The image file %hs is valid but is for a machine type other than the current machine.
STATUS_NO_YIELD_PERFORMED 0x40000024	A yield execution was performed and no thread was available to run.
STATUS_TIMER_RESUME_IGNORED 0x40000025	The resume flag to a timer API was ignored.
STATUS_ARBITRATION_UNHANDLED 0x40000026	The arbiter has deferred arbitration of these resources to its parent.
STATUS_CARDBUS_NOT_SUPPORTED 0x40000027	The device has detected a CardBus card in its slot.
STATUS_WX86_CREATEWX86TIB 0x40000028	An exception status code that is used by the Win32 x86 emulation subsystem.
STATUS_MP_PROCESSOR_MISMATCH 0x40000029	The CPUs in this multiprocessor system are not all the same revision level. To use all processors, the operating system restricts itself to the features of the

Value	Meaning
	least capable processor in the system. If problems occur with this system, contact the CPU manufacturer to see if this mix of processors is supported.
STATUS_HIBERNATED 0x4000002A	The system was put into hibernation.
STATUS_RESUME_HIBERNATION 0x4000002B	The system was resumed from hibernation.
STATUS_FIRMWARE_UPDATED 0x4000002C	Windows has detected that the system firmware (BIOS) was updated [previous firmware date = %2, current firmware date %3].
STATUS_DRIVERS_LEAKING_LOCKED_PAGES 0x4000002D	A device driver is leaking locked I/O pages and is causing system degradation. The system has automatically enabled the tracking code to try and catch the culprit.
STATUS_MESSAGE_RETRIEVED 0x4000002E	The ALPC message being canceled has already been retrieved from the queue on the other side.
STATUS_SYSTEM_POWERSTATE_TRANSITION 0x4000002F	The system power state is transitioning from %2 to %3.
STATUS_ALPC_CHECK_COMPLETION_LIST 0x40000030	The receive operation was successful. Check the ALPC completion list for the received message.
STATUS_SYSTEM_POWERSTATE_COMPLEX_TRANSITION 0x40000031	The system power state is transitioning from %2 to %3 but could enter %4.
STATUS_ACCESS_AUDIT_BY_POLICY 0x40000032	Access to %1 is monitored by policy rule %2.
STATUS_ABANDON_HIBERFILE 0x40000033	A valid hibernation file has been invalidated and should be abandoned.
STATUS_BIZRULES_NOT_ENABLED 0x40000034	Business rule scripts are disabled for the calling application.
STATUS_WAKE_SYSTEM 0x40000294	The system has awoken.
STATUS_DS_SHUTTING_DOWN 0x40000370	The directory service is shutting down.
DBG_REPLY_LATER 0x40010001	Debugger will reply later.
DBG_UNABLE_TO_PROVIDE_HANDLE	Debugger cannot provide a handle.

Value	Meaning
0x40010002	
DBG_TERMINATE_THREAD 0x40010003	Debugger terminated the thread.
DBG_TERMINATE_PROCESS 0x40010004	Debugger terminated the process.
DBG_CONTROL_C 0x40010005	Debugger obtained control of C.
DBG_PRINTEXCEPTION_C 0x40010006	Debugger printed an exception on control C.
DBG_RIPEXCEPTION 0x40010007	Debugger received a RIP exception.
DBG_CONTROL_BREAK 0x40010008	Debugger received a control break.
DBG_COMMAND_EXCEPTION 0x40010009	Debugger command communication exception.
RPC_NT_UUID_LOCAL_ONLY 0x40020056	A UUID that is valid only on this computer has been allocated.
RPC_NT_SEND_INCOMPLETE 0x400200AF	Some data remains to be sent in the request buffer.
STATUS_CTX_CDM_CONNECT 0x400A0004	The Client Drive Mapping Service has connected on Terminal Connection.
STATUS_CTX_CDM_DISCONNECT 0x400A0005	The Client Drive Mapping Service has disconnected on Terminal Connection.
STATUS_SXS_RELEASE_ACTIVATION_CONTEXT 0x4015000D	A kernel mode component is releasing a reference on an activation context.
STATUS_RECOVERY_NOT_NEEDED 0x40190034	The transactional resource manager is already consistent. Recovery is not needed.
STATUS_RM_ALREADY_STARTED 0x40190035	The transactional resource manager has already been started.
STATUS_LOG_NO_RESTART 0x401A000C	The log service encountered a log stream with no restart area.
STATUS_VIDEO_DRIVER_DEBUG_REPORT_REQUEST 0x401B00EC	{Display Driver Recovered From Failure} The %hs display driver has detected a failure and recovered from it. Some graphical operations may have failed. The next time you restart the machine, a dialog box appears, giving

Value	Meaning
	you an opportunity to upload data about this failure to Microsoft.
STATUS_GRAPHICS_PARTIAL_DATA_POPULATED 0x401E000A	The specified buffer is not big enough to contain the entire requested dataset. Partial data is populated up to the size of the buffer.  The caller needs to provide a buffer of the size as specified in the partially populated buffer's content (interface specific).
STATUS_GRAPHICS_DRIVER_MISMATCH 0x401E0117	The kernel driver detected a version mismatch between it and the user mode driver.
STATUS_GRAPHICS_MODE_NOT_PINNED 0x401E0307	No mode is pinned on the specified VidPN source/target.
STATUS_GRAPHICS_NO_PREFERRED_MODE 0x401E031E	The specified mode set does not specify a preference for one of its modes.
STATUS_GRAPHICS_DATASET_IS_EMPTY 0x401E034B	The specified dataset (for example, mode set, frequency range set, descriptor set, or topology) is empty.
STATUS_GRAPHICS_NO_MORE_ELEMENTS_IN_DATASET 0x401E034C	The specified dataset (for example, mode set, frequency range set, descriptor set, or topology) does not contain any more elements.
STATUS_GRAPHICS_PATH_CONTENT_GEOMETRY_TRANSFORMATI ON_NOT_PINNED 0x401E0351	The specified content transformation is not pinned on the specified VidPN present path.
STATUS_GRAPHICS_UNKNOWN_CHILD_STATUS 0x401E042F	The child device presence was not reliably detected.
STATUS_GRAPHICS_LEADLINK_START_DEFERRED 0x401E0437	Starting the lead adapter in a linked configuration has been temporarily deferred.
STATUS_GRAPHICS_POLLING_TOO_FREQUENTLY 0x401E0439	The display adapter is being polled for children too frequently at the same polling level.
STATUS_GRAPHICS_START_DEFERRED 0x401E043A	Starting the adapter has been temporarily deferred.
STATUS_NDIS_INDICATION_REQUIRED 0x40230001	The request will be completed later by an NDIS status indication.
STATUS_GUARD_PAGE_VIOLATION 0x80000001	{EXCEPTION} Guard Page Exception A page of memory that marks the end of a data structure, such as a stack or an array, has been accessed.



Value	Meaning
STATUS_DATATYPE_MISALIGNMENT 0x80000002	{EXCEPTION} Alignment Fault A data type misalignment was detected in a load or store instruction.
STATUS_BREAKPOINT 0x80000003	{EXCEPTION} Breakpoint A breakpoint has been reached.
STATUS_SINGLE_STEP 0x80000004	{EXCEPTION} Single Step A single step or trace operation has just been completed.
STATUS_BUFFER_OVERFLOW 0x80000005	{Buffer Overflow} The data was too large to fit into the specified buffer.
STATUS_NO_MORE_FILES 0x80000006	{No More Files} No more files were found which match the file specification.
STATUS_WAKE_SYSTEM_DEBUGGER 0x80000007	{Kernel Debugger Awakened} The system debugger was awakened by an interrupt.
STATUS_HANDLES_CLOSED 0x8000000A	{Handles Closed} Handles to objects have been automatically closed because of the requested operation.
STATUS_NO_INHERITANCE 0x8000000B	{Non-Inheritable ACL} An access control list (ACL) contains no components that can be inherited.
STATUS_GUID_SUBSTITUTION_MADE 0x8000000C	{GUID Substitution} During the translation of a globally unique identifier (GUID) to a Windows security ID (SID), no administratively defined GUID prefix was found. A substitute prefix was used, which will not compromise system security. However, this may provide a more restrictive access than intended.
STATUS_PARTIAL_COPY 0x8000000D	Because of protection conflicts, not all the requested bytes could be copied.
STATUS_DEVICE_PAPER_EMPTY 0x8000000E	{Out of Paper} The printer is out of paper.
STATUS_DEVICE_POWERED_OFF 0x8000000F	{Device Power Is Off} The printer power has been turned off.
STATUS_DEVICE_OFF_LINE 0x80000010	{Device Offline} The printer has been taken offline.
STATUS_DEVICE_BUSY 0x80000011	{Device Busy} The device is currently busy.
STATUS_NO_MORE_EAS 0x80000012	{No More EAs} No more extended attributes (EAs) were found for the file.

Value	Meaning
STATUS_INVALID_EA_NAME 0x80000013	{Illegal EA} The specified extended attribute (EA) name contains at least one illegal character.
STATUS_EA_LIST_INCONSISTENT 0x80000014	{Inconsistent EA List} The extended attribute (EA) list is inconsistent.
STATUS_INVALID_EA_FLAG 0x80000015	{Invalid EA Flag} An invalid extended attribute (EA) flag was set.
STATUS_VERIFY_REQUIRED 0x80000016	{Verifying Disk} The media has changed and a verify operation is in progress; therefore, no reads or writes may be performed to the device, except those that are used in the verify operation.
STATUS_EXTRANEOUS_INFORMATION 0x80000017	{Too Much Information} The specified access control list (ACL) contained more information than was expected.
STATUS_RXACT_COMMIT_NECESSARY 0x80000018	This warning level status indicates that the transaction state already exists for the registry subtree, but that a transaction commit was previously aborted. The commit has NOT been completed but has not been rolled back either; therefore, it may still be committed, if needed.
STATUS_NO_MORE_ENTRIES 0x8000001A	{No More Entries} No more entries are available from an enumeration operation.
STATUS_FILEMARK_DETECTED 0x8000001B	{Filemark Found} A filemark was detected.
STATUS_MEDIA_CHANGED 0x8000001C	{Media Changed} The media may have changed.
STATUS_BUS_RESET 0x8000001D	{I/O Bus Reset} An I/O bus reset was detected.
STATUS_END_OF_MEDIA 0x8000001E	{End of Media} The end of the media was encountered.
STATUS_BEGINNING_OF_MEDIA 0x8000001F	The beginning of a tape or partition has been detected.
STATUS_MEDIA_CHECK 0x80000020	{Media Changed} The media may have changed.
STATUS_SETMARK_DETECTED 0x80000021	A tape access reached a set mark.

Value	Meaning
STATUS_NO_DATA_DETECTED 0x80000022	During a tape access, the end of the data written is reached.
STATUS_REDIRECTOR_HAS_OPEN_HANDLES 0x80000023	The redirector is in use and cannot be unloaded.
STATUS_SERVER_HAS_OPEN_HANDLES 0x80000024	The server is in use and cannot be unloaded.
STATUS_ALREADY_DISCONNECTED 0x80000025	The specified connection has already been disconnected.
STATUS_LONGJUMP 0x80000026	A long jump has been executed.
STATUS_CLEANER_CARTRIDGE_INSTALLED 0x80000027	A cleaner cartridge is present in the tape library.
STATUS_PLUGPLAY_QUERY_VETOED 0x80000028	The Plug and Play query operation was not successful.
STATUS_UNWIND_CONSOLIDATE 0x80000029	A frame consolidation has been executed.
STATUS_REGISTRY_HIVE_RECOVERED 0x8000002A	{Registry Hive Recovered} The registry hive (file): %hs was corrupted and it has been recovered. Some data might have been lost.
STATUS_DLL_MIGHT_BE_INSECURE 0x8000002B	The application is attempting to run executable code from the module %hs. This may be insecure. An alternative, %hs, is available. Should the application use the secure module %hs?
STATUS_DLL_MIGHT_BE_INCOMPATIBLE 0x8000002C	The application is loading executable code from the module %hs. This is secure but may be incompatible with previous releases of the operating system. An alternative, %hs, is available. Should the application use the secure module %hs?
STATUS_STOPPED_ON_SYMLINK 0x8000002D	The create operation stopped after reaching a symbolic link.
STATUS_DEVICE_REQUIRES_CLEANING 0x80000288	The device has indicated that cleaning is necessary.
STATUS_DEVICE_DOOR_OPEN 0x80000289	The device has indicated that its door is open. Further operations require it closed and secured.
STATUS_DATA_LOST_REPAIR	Windows discovered a corruption in the file %hs. This file has now been

Value	Meaning
0x80000803	repaired. Check if any data in the file was lost because of the corruption.
DBG_EXCEPTION_NOT_HANDLED 0x80010001	Debugger did not handle the exception.
STATUS_CLUSTER_NODE_ALREADY_UP 0x80130001	The cluster node is already up.
STATUS_CLUSTER_NODE_ALREADY_DOWN 0x80130002	The cluster node is already down.
STATUS_CLUSTER_NETWORK_ALREADY_ONLINE 0x80130003	The cluster network is already online.
STATUS_CLUSTER_NETWORK_ALREADY_OFFLINE 0x80130004	The cluster network is already offline.
STATUS_CLUSTER_NODE_ALREADY_MEMBER 0x80130005	The cluster node is already a member of the cluster.
STATUS_COULD_NOT_RESIZE_LOG 0x80190009	The log could not be set to the requested size.
STATUS_NO_TXF_METADATA 0x80190029	There is no transaction metadata on the file.
STATUS_CANT_RECOVER_WITH_HANDLE_OPEN 0x80190031	The file cannot be recovered because there is a handle still open on it.
STATUS_TXF_METADATA_ALREADY_PRESENT 0x80190041	Transaction metadata is already present on this file and cannot be superseded.
STATUS_TRANSACTION_SCOPE_CALLBACKS_NOT_SET 0x80190042	A transaction scope could not be entered because the scope handler has not been initialized.
STATUS_VIDEO_HUNG_DISPLAY_DRIVER_THREAD_RECOVERED 0x801B00EB	{Display Driver Stopped Responding and recovered} The %hs display driver has stopped working normally. The recovery had been performed.
STATUS_FLT_BUFFER_TOO_SMALL 0x801C0001	{Buffer too small} The buffer is too small to contain the entry. No information has been written to the buffer.
STATUS_FVE_PARTIAL_METADATA 0x80210001	Volume metadata read or write is incomplete.
STATUS_UNSUCCESSFUL 0xC0000001	{Operation Failed} The requested operation was unsuccessful.
STATUS_NOT_IMPLEMENTED	{Not Implemented} The requested

Value	Meaning
0xC0000002	operation is not implemented.
STATUS_INVALID_INFO_CLASS 0xC0000003	{Invalid Parameter} The specified information class is not a valid information class for the specified object.
STATUS_INFO_LENGTH_MISMATCH 0xC0000004	The specified information record length does not match the length that is required for the specified information class.
STATUS_ACCESS_VIOLATION 0xC0000005	The instruction at 0x%08lx referenced memory at 0x%08lx. The memory could not be %s.
STATUS_IN_PAGE_ERROR 0xC0000006	The instruction at 0x%08lx referenced memory at 0x%08lx. The required data was not placed into memory because of an I/O error status of 0x%08lx.
STATUS_PAGEFILE_QUOTA 0xC0000007	The page file quota for the process has been exhausted.
STATUS_INVALID_HANDLE 0xC0000008	An invalid HANDLE was specified.
STATUS_BAD_INITIAL_STACK 0xC0000009	An invalid initial stack was specified in a call to NtCreateThread.
STATUS_BAD_INITIAL_PC 0xC000000A	An invalid initial start address was specified in a call to NtCreateThread.
STATUS_INVALID_CID 0xC000000B	An invalid client ID was specified.
STATUS_TIMER_NOT_CANCELED 0xC000000C	An attempt was made to cancel or set a timer that has an associated APC and the specified thread is not the thread that originally set the timer with an associated APC routine.
STATUS_INVALID_PARAMETER 0xC000000D	An invalid parameter was passed to a service or function.
STATUS_NO_SUCH_DEVICE 0xC000000E	A device that does not exist was specified.
STATUS_NO_SUCH_FILE 0xC000000F	{File Not Found} The file %hs does not exist.
STATUS_INVALID_DEVICE_REQUEST 0xC0000010	The specified request is not a valid operation for the target device.
STATUS_END_OF_FILE	The end-of-file marker has been reached. There is no valid data in the

Value	Meaning
0xC0000011	file beyond this marker.
STATUS_WRONG_VOLUME 0xC0000012	{Wrong Volume} The wrong volume is in the drive. Insert volume %hs into drive %hs.
STATUS_NO_MEDIA_IN_DEVICE 0xC0000013	{No Disk} There is no disk in the drive. Insert a disk into drive %hs.
STATUS_UNRECOGNIZED_MEDIA 0xC0000014	{Unknown Disk Format} The disk in drive %hs is not formatted properly. Check the disk, and reformat it, if needed.
STATUS_NONEXISTENT_SECTOR 0xC0000015	{Sector Not Found} The specified sector does not exist.
STATUS_MORE_PROCESSING_REQUIRED 0xC0000016	{Still Busy} The specified I/O request packet (IRP) cannot be disposed of because the I/O operation is not complete.
STATUS_NO_MEMORY 0xC0000017	{Not Enough Quota} Not enough virtual memory or paging file quota is available to complete the specified operation.
STATUS_CONFLICTING_ADDRESSES 0xC0000018	{Conflicting Address Range} The specified address range conflicts with the address space.
STATUS_NOT_MAPPED_VIEW 0xC0000019	The address range to unmap is not a mapped view.
STATUS_UNABLE_TO_FREE_VM 0xC000001A	The virtual memory cannot be freed.
STATUS_UNABLE_TO_DELETE_SECTION 0xC000001B	The specified section cannot be deleted.
STATUS_INVALID_SYSTEM_SERVICE 0xC000001C	An invalid system service was specified in a system service call.
STATUS_ILLEGAL_INSTRUCTION 0xC000001D	{EXCEPTION} Illegal Instruction An attempt was made to execute an illegal instruction.
STATUS_INVALID_LOCK_SEQUENCE 0xC000001E	{Invalid Lock Sequence} An attempt was made to execute an invalid lock sequence.
STATUS_INVALID_VIEW_SIZE 0xC000001F	{Invalid Mapping} An attempt was made to create a view for a section that is bigger than the section.
STATUS_INVALID_FILE_FOR_SECTION 0xC0000020	{Bad File} The attributes of the specified mapping file for a section of

Value	Meaning
	memory cannot be read.
STATUS_ALREADY_COMMITTED 0xC0000021	{Already Committed} The specified address range is already committed.
STATUS_ACCESS_DENIED 0xC0000022	{Access Denied} A process has requested access to an object but has not been granted those access rights.
STATUS_BUFFER_TOO_SMALL 0xC0000023	{Buffer Too Small} The buffer is too small to contain the entry. No information has been written to the buffer.
STATUS_OBJECT_TYPE_MISMATCH 0xC0000024	{Wrong Type} There is a mismatch between the type of object that is required by the requested operation and the type of object that is specified in the request.
STATUS_NONCONTINUABLE_EXCEPTION 0xC0000025	{EXCEPTION} Cannot Continue Windows cannot continue from this exception.
STATUS_INVALID_DISPOSITION 0xC0000026	An invalid exception disposition was returned by an exception handler.
STATUS_UNWIND 0xC0000027	Unwind exception code.
STATUS_BAD_STACK 0xC0000028	An invalid or unaligned stack was encountered during an unwind operation.
STATUS_INVALID_UNWIND_TARGET 0xC0000029	An invalid unwind target was encountered during an unwind operation.
STATUS_NOT_LOCKED 0xC000002A	An attempt was made to unlock a page of memory that was not locked.
STATUS_PARITY_ERROR 0xC000002B	A device parity error on an I/O operation.
STATUS_UNABLE_TO_DECOMMIT_VM 0xC000002C	An attempt was made to decommit uncommitted virtual memory.
STATUS_NOT_COMMITTED 0xC000002D	An attempt was made to change the attributes on memory that has not been committed.
STATUS_INVALID_PORT_ATTRIBUTES 0xC000002E	Invalid object attributes specified to NtCreatePort or invalid port attributes specified to NtConnectPort.
STATUS_PORT_MESSAGE_TOO_LONG	The length of the message that was

Value	Meaning
0xC000002F	passed to NtRequestPort or NtRequestWaitReplyPort is longer than the maximum message that is allowed by the port.
STATUS_INVALID_PARAMETER_MIX 0xC0000030	An invalid combination of parameters was specified.
STATUS_INVALID_QUOTA_LOWER 0xC0000031	An attempt was made to lower a quota limit below the current usage.
STATUS_DISK_CORRUPT_ERROR 0xC0000032	{Corrupt Disk} The file system structure on the disk is corrupt and unusable. Run the Chkdsk utility on the volume %hs.
STATUS_OBJECT_NAME_INVALID 0xC0000033	The object name is invalid.
STATUS_OBJECT_NAME_NOT_FOUND 0xC0000034	The object name is not found.
STATUS_OBJECT_NAME_COLLISION 0xC0000035	The object name already exists.
STATUS_PORT_DISCONNECTED 0xC0000037	An attempt was made to send a message to a disconnected communication port.
STATUS_DEVICE_ALREADY_ATTACHED 0xC0000038	An attempt was made to attach to a device that was already attached to another device.
STATUS_OBJECT_PATH_INVALID 0xC0000039	The object path component was not a directory object.
STATUS_OBJECT_PATH_NOT_FOUND 0xC000003A	{Path Not Found} The path %hs does not exist.
STATUS_OBJECT_PATH_SYNTAX_BAD 0xC000003B	The object path component was not a directory object.
STATUS_DATA_OVERRUN 0xC000003C	{Data Overrun} A data overrun error occurred.
STATUS_DATA_LATE_ERROR 0xC000003D	{Data Late} A data late error occurred.
STATUS_DATA_ERROR 0xC000003E	{Data Error} An error occurred in reading or writing data.
STATUS_CRC_ERROR 0xC000003F	{Bad CRC} A cyclic redundancy check (CRC) checksum error occurred.



Value	Meaning
STATUS_SECTION_TOO_BIG 0xC0000040	{Section Too Large} The specified section is too big to map the file.
STATUS_PORT_CONNECTION_REFUSED 0xC0000041	The NtConnectPort request is refused.
STATUS_INVALID_PORT_HANDLE 0xC0000042	The type of port handle is invalid for the operation that is requested.
STATUS_SHARING_VIOLATION 0xC0000043	A file cannot be opened because the share access flags are incompatible.
STATUS_QUOTA_EXCEEDED 0xC0000044	Insufficient quota exists to complete the operation.
STATUS_INVALID_PAGE_PROTECTION 0xC0000045	The specified page protection was not valid.
STATUS_MUTANT_NOT_OWNED 0xC0000046	An attempt to release a mutant object was made by a thread that was not the owner of the mutant object.
STATUS_SEMAPHORE_LIMIT_EXCEEDED 0xC0000047	An attempt was made to release a semaphore such that its maximum count would have been exceeded.
STATUS_PORT_ALREADY_SET 0xC0000048	An attempt was made to set the DebugPort or ExceptionPort of a process, but a port already exists in the process, or an attempt was made to set the CompletionPort of a file but a port was already set in the file, or an attempt was made to set the associated completion port of an ALPC port but it is already set.
STATUS_SECTION_NOT_IMAGE 0xC0000049	An attempt was made to query image information on a section that does not map an image.
STATUS_SUSPEND_COUNT_EXCEEDED 0xC000004A	An attempt was made to suspend a thread whose suspend count was at its maximum.
STATUS_THREAD_IS_TERMINATING 0xC000004B	An attempt was made to suspend a thread that has begun termination.
STATUS_BAD_WORKING_SET_LIMIT 0xC000004C	An attempt was made to set the working set limit to an invalid value (for example, the minimum greater than maximum).
STATUS_INCOMPATIBLE_FILE_MAP 0xC000004D	A section was created to map a file that is not compatible with an already existing section that maps the same file.

Value	Meaning
STATUS_SECTION_PROTECTION 0xC000004E	A view to a section specifies a protection that is incompatible with the protection of the initial view.
STATUS_EAS_NOT_SUPPORTED 0xC000004F	An operation involving EAs failed because the file system does not support EAs.
STATUS_EA_TOO_LARGE 0xC0000050	An EA operation failed because the EA set is too large.
STATUS_NONEXISTENT_EA_ENTRY 0xC0000051	An EA operation failed because the name or EA index is invalid.
STATUS_NO_EAS_ON_FILE 0xC0000052	The file for which EAs were requested has no EAs.
STATUS_EA_CORRUPT_ERROR 0xC0000053	The EA is corrupt and cannot be read.
STATUS_FILE_LOCK_CONFLICT 0xC0000054	A requested read/write cannot be granted due to a conflicting file lock.
STATUS_LOCK_NOT_GRANTED 0xC0000055	A requested file lock cannot be granted due to other existing locks.
STATUS_DELETE_PENDING 0xC0000056	A non-close operation has been requested of a file object that has a delete pending.
STATUS_CTL_FILE_NOT_SUPPORTED 0xC0000057	An attempt was made to set the control attribute on a file. This attribute is not supported in the destination file system.
STATUS_UNKNOWN_REVISION 0xC0000058	Indicates a revision number that was encountered or specified is not one that is known by the service. It may be a more recent revision than the service is aware of.
STATUS_REVISION_MISMATCH 0xC0000059	Indicates that two revision levels are incompatible.
STATUS_INVALID_OWNER 0xC000005A	Indicates a particular security ID may not be assigned as the owner of an object.
STATUS_INVALID_PRIMARY_GROUP 0xC000005B	Indicates a particular security ID may not be assigned as the primary group of an object.
STATUS_NO_IMPERSONATION_TOKEN 0xC000005C	An attempt has been made to operate on an impersonation token by a thread that is not currently impersonating a client.

Value	Meaning
STATUS_CANT_DISABLE_MANDATORY 0xC000005D	A mandatory group may not be disabled.
STATUS_NO_LOGON_SERVERS 0xC000005E	No logon servers are currently available to service the logon request.
STATUS_NO_SUCH_LOGON_SESSION 0xC000005F	A specified logon session does not exist. It may already have been terminated.
STATUS_NO_SUCH_PRIVILEGE 0xC0000060	A specified privilege does not exist.
STATUS_PRIVILEGE_NOT_HELD 0xC0000061	A required privilege is not held by the client.
STATUS_INVALID_ACCOUNT_NAME 0xC0000062	The name provided is not a properly formed account name.
STATUS_USER_EXISTS 0xC0000063	The specified account already exists.
STATUS_NO_SUCH_USER 0xC0000064	The specified account does not exist.
STATUS_GROUP_EXISTS 0xC0000065	The specified group already exists.
STATUS_NO_SUCH_GROUP 0xC0000066	The specified group does not exist.
STATUS_MEMBER_IN_GROUP 0xC0000067	The specified user account is already in the specified group account. Also used to indicate a group cannot be deleted because it contains a member.
STATUS_MEMBER_NOT_IN_GROUP 0xC0000068	The specified user account is not a member of the specified group account.
STATUS_LAST_ADMIN 0xC0000069	Indicates the requested operation would disable or delete the last remaining administration account. This is not allowed to prevent creating a situation in which the system cannot be administrated.
STATUS_WRONG_PASSWORD 0xC000006A	When trying to update a password, this return status indicates that the value provided as the current password is not correct.
STATUS_ILL_FORMED_PASSWORD 0xC000006B	When trying to update a password, this return status indicates that the value provided for the new password contains values that are not allowed in

Value	Meaning
	passwords.
STATUS_PASSWORD_RESTRICTION 0xC000006C	When trying to update a password, this status indicates that some password update rule has been violated. For example, the password may not meet length criteria.
STATUS_LOGON_FAILURE 0xC000006D	The attempted logon is invalid. This is either due to a bad username or authentication information.
STATUS_ACCOUNT_RESTRICTION 0xC000006E	Indicates a referenced user name and authentication information are valid, but some user account restriction has prevented successful authentication (such as time-of-day restrictions).
STATUS_INVALID_LOGON_HOURS 0xC000006F	The user account has time restrictions and may not be logged onto at this time.
STATUS_INVALID_WORKSTATION 0xC0000070	The user account is restricted so that it may not be used to log on from the source workstation.
STATUS_PASSWORD_EXPIRED 0xC0000071	The user account password has expired.
STATUS_ACCOUNT_DISABLED 0xC0000072	The referenced account is currently disabled and may not be logged on to.
STATUS_NONE_MAPPED 0xC0000073	None of the information to be translated has been translated.
STATUS_TOO_MANY_LUIDS_REQUESTED 0xC0000074	The number of LUIDs requested may not be allocated with a single allocation.
STATUS_LUIDS_EXHAUSTED 0xC0000075	Indicates there are no more LUIDs to allocate.
STATUS_INVALID_SUB_AUTHORITY 0xC0000076	Indicates the sub-authority value is invalid for the particular use.
STATUS_INVALID_ACL 0xC0000077	Indicates the ACL structure is not valid.
STATUS_INVALID_SID 0xC0000078	Indicates the SID structure is not valid.
STATUS_INVALID_SECURITY_DESCR 0xC0000079	Indicates the SECURITY_DESCRIPTOR structure is not valid.
STATUS_PROCEDURE_NOT_FOUND 0xC000007A	Indicates the specified procedure address cannot be found in the DLL.

Value	Meaning
STATUS_INVALID_IMAGE_FORMAT 0xC000007B	{Bad Image} %hs is either not designed to run on Windows or it contains an error. Try installing the program again using the original installation media or contact your system administrator or the software vendor for support.
STATUS_NO_TOKEN 0xC000007C	An attempt was made to reference a token that does not exist. This is typically done by referencing the token that is associated with a thread when the thread is not impersonating a client.
STATUS_BAD_INHERITANCE_ACL 0xC000007D	Indicates that an attempt to build either an inherited ACL or ACE was not successful. This can be caused by a number of things. One of the more probable causes is the replacement of a CreatorId with a SID that did not fit into the ACE or ACL.
STATUS_RANGE_NOT_LOCKED 0xC000007E	The range specified in NtUnlockFile was not locked.
STATUS_DISK_FULL 0xC000007F	An operation failed because the disk was full.
STATUS_SERVER_DISABLED 0xC0000080	The GUID allocation server is disabled at the moment.
STATUS_SERVER_NOT_DISABLED 0xC0000081	The GUID allocation server is enabled at the moment.
STATUS_TOO_MANY_GUIDS_REQUESTED 0xC0000082	Too many GUIDs were requested from the allocation server at once.
STATUS_GUIDS_EXHAUSTED 0xC0000083	The GUIDs could not be allocated because the Authority Agent was exhausted.
STATUS_INVALID_ID_AUTHORITY 0xC0000084	The value provided was an invalid value for an identifier authority.
STATUS_AGENTS_EXHAUSTED 0xC0000085	No more authority agent values are available for the particular identifier authority value.
STATUS_INVALID_VOLUME_LABEL 0xC0000086	An invalid volume label has been specified.
STATUS_SECTION_NOT_EXTENDED 0xC0000087	A mapped section could not be extended.
STATUS_NOT_MAPPED_DATA	Specified section to flush does not map

Value	Meaning
0xC0000088	a data file.
STATUS_RESOURCE_DATA_NOT_FOUND 0xC0000089	Indicates the specified image file did not contain a resource section.
STATUS_RESOURCE_TYPE_NOT_FOUND 0xC000008A	Indicates the specified resource type cannot be found in the image file.
STATUS_RESOURCE_NAME_NOT_FOUND 0xC000008B	Indicates the specified resource name cannot be found in the image file.
STATUS_ARRAY_BOUNDS_EXCEEDED 0xC000008C	{EXCEPTION} Array bounds exceeded.
STATUS_FLOAT_DENORMAL_OPERAND 0xC000008D	{EXCEPTION} Floating-point denormal operand.
STATUS_FLOAT_DIVIDE_BY_ZERO 0xC000008E	{EXCEPTION} Floating-point division by zero.
STATUS_FLOAT_INEXACT_RESULT 0xC000008F	{EXCEPTION} Floating-point inexact result.
STATUS_FLOAT_INVALID_OPERATION 0xC0000090	{EXCEPTION} Floating-point invalid operation.
STATUS_FLOAT_OVERFLOW 0xC0000091	{EXCEPTION} Floating-point overflow.
STATUS_FLOAT_STACK_CHECK 0xC0000092	{EXCEPTION} Floating-point stack check.
STATUS_FLOAT_UNDERFLOW 0xC0000093	{EXCEPTION} Floating-point underflow.
STATUS_INTEGER_DIVIDE_BY_ZERO 0xC0000094	{EXCEPTION} Integer division by zero.
STATUS_INTEGER_OVERFLOW 0xC0000095	{EXCEPTION} Integer overflow.
STATUS_PRIVILEGED_INSTRUCTION 0xC0000096	{EXCEPTION} Privileged instruction.
STATUS_TOO_MANY_PAGING_FILES 0xC0000097	An attempt was made to install more paging files than the system supports.
STATUS_FILE_INVALID 0xC0000098	The volume for a file has been externally altered such that the opened file is no longer valid.
STATUS_ALLOTTED_SPACE_EXCEEDED 0xC0000099	When a block of memory is allotted for future updates, such as the memory allocated to hold discretionary access

Value	Meaning
	control and primary group information, successive updates may exceed the amount of memory originally allotted. Because a quota may already have been charged to several processes that have handles to the object, it is not reasonable to alter the size of the allocated memory. Instead, a request that requires more memory than has been allotted must fail and the STATUS_ALLOTTED_SPACE_EXCEEDED error returned.
STATUS_INSUFFICIENT_RESOURCES 0xC000009A	Insufficient system resources exist to complete the API.
STATUS_DFS_EXIT_PATH_FOUND 0xC000009B	An attempt has been made to open a DFS exit path control file.
STATUS_DEVICE_DATA_ERROR 0xC000009C	STATUS_DEVICE_DATA_ERROR
STATUS_DEVICE_NOT_CONNECTED 0xC000009D	STATUS_DEVICE_NOT_CONNECTED
STATUS_DEVICE_POWER_FAILURE 0xC000009E	STATUS_DEVICE_POWER_FAILURE
STATUS_FREE_VM_NOT_AT_BASE 0xC000009F	Virtual memory cannot be freed because the base address is not the base of the region and a region size of zero was specified.
STATUS_MEMORY_NOT_ALLOCATED 0xC00000A0	An attempt was made to free virtual memory that is not allocated.
STATUS_WORKING_SET_QUOTA 0xC00000A1	The working set is not big enough to allow the requested pages to be locked.
STATUS_MEDIA_WRITE_PROTECTED 0xC00000A2	{Write Protect Error} The disk cannot be written to because it is write-protected. Remove the write protection from the volume %hs in drive %hs.
STATUS_DEVICE_NOT_READY 0xC00000A3	{Drive Not Ready} The drive is not ready for use; its door may be open. Check drive %hs and make sure that a disk is inserted and that the drive door is closed.
STATUS_INVALID_GROUP_ATTRIBUTES 0xC00000A4	The specified attributes are invalid or are incompatible with the attributes for the group as a whole.
STATUS_BAD_IMPERSONATION_LEVEL	A specified impersonation level is invalid. Also used to indicate that a

Value	Meaning
0xC00000A5	required impersonation level was not provided.
STATUS_CANT_OPEN_ANONYMOUS 0xC00000A6	An attempt was made to open an anonymous-level token. Anonymous tokens may not be opened.
STATUS_BAD_VALIDATION_CLASS 0xC00000A7	The validation information class requested was invalid.
STATUS_BAD_TOKEN_TYPE 0xC00000A8	The type of a token object is inappropriate for its attempted use.
STATUS_BAD_MASTER_BOOT_RECORD 0xC00000A9	The type of a token object is inappropriate for its attempted use.
STATUS_INSTRUCTION_MISALIGNMENT 0xC00000AA	An attempt was made to execute an instruction at an unaligned address and the host system does not support unaligned instruction references.
STATUS_INSTANCE_NOT_AVAILABLE 0xC00000AB	The maximum named pipe instance count has been reached.
STATUS_PIPE_NOT_AVAILABLE 0xC00000AC	An instance of a named pipe cannot be found in the listening state.
STATUS_INVALID_PIPE_STATE 0xC00000AD	The named pipe is not in the connected or closing state.
STATUS_PIPE_BUSY 0xC00000AE	The specified pipe is set to complete operations and there are current I/O operations queued so that it cannot be changed to queue operations.
STATUS_ILLEGAL_FUNCTION 0xC00000AF	The specified handle is not open to the server end of the named pipe.
STATUS_PIPE_DISCONNECTED 0xC00000B0	The specified named pipe is in the disconnected state.
STATUS_PIPE_CLOSING 0xC00000B1	The specified named pipe is in the closing state.
STATUS_PIPE_CONNECTED 0xC00000B2	The specified named pipe is in the connected state.
STATUS_PIPE_LISTENING 0xC00000B3	The specified named pipe is in the listening state.
STATUS_INVALID_READ_MODE 0xC00000B4	The specified named pipe is not in message mode.
STATUS_IO_TIMEOUT	{Device Timeout} The specified I/O operation on %hs was not completed



Value	Meaning
0xC00000B5	before the time-out period expired.
STATUS_FILE_FORCED_CLOSED 0xC00000B6	The specified file has been closed by another process.
STATUS_PROFILING_NOT_STARTED 0xC00000B7	Profiling is not started.
STATUS_PROFILING_NOT_STOPPED 0xC00000B8	Profiling is not stopped.
STATUS_COULD_NOT_INTERPRET 0xC00000B9	The passed ACL did not contain the minimum required information.
STATUS_FILE_IS_A_DIRECTORY 0xC00000BA	The file that was specified as a target is a directory, and the caller specified that it could be anything but a directory.
STATUS_NOT_SUPPORTED 0xC00000BB	The request is not supported.
STATUS_REMOTE_NOT_LISTENING 0xC00000BC	This remote computer is not listening.
STATUS_DUPLICATE_NAME 0xC00000BD	A duplicate name exists on the network.
STATUS_BAD_NETWORK_PATH 0xC00000BE	The network path cannot be located.
STATUS_NETWORK_BUSY 0xC00000BF	The network is busy.
STATUS_DEVICE_DOES_NOT_EXIST 0xC00000C0	This device does not exist.
STATUS_TOO_MANY_COMMANDS 0xC00000C1	The network BIOS command limit has been reached.
STATUS_ADAPTER_HARDWARE_ERROR 0xC00000C2	An I/O adapter hardware error has occurred.
STATUS_INVALID_NETWORK_RESPONSE 0xC00000C3	The network responded incorrectly.
STATUS_UNEXPECTED_NETWORK_ERROR 0xC00000C4	An unexpected network error occurred.
STATUS_BAD_REMOTE_ADAPTER 0xC00000C5	The remote adapter is not compatible.
STATUS_PRINT_QUEUE_FULL 0xC00000C6	The print queue is full.

Value	Meaning
STATUS_NO_SPOOL_SPACE 0xC00000C7	Space to store the file that is waiting to be printed is not available on the server.
STATUS_PRINT_CANCELLED 0xC00000C8	The requested print file has been canceled.
STATUS_NETWORK_NAME_DELETED 0xC00000C9	The network name was deleted.
STATUS_NETWORK_ACCESS_DENIED 0xC00000CA	Network access is denied.
STATUS_BAD_DEVICE_TYPE 0xC00000CB	{Incorrect Network Resource Type} The specified device type (LPT, for example) conflicts with the actual device type on the remote resource.
STATUS_BAD_NETWORK_NAME 0xC00000CC	{Network Name Not Found} The specified share name cannot be found on the remote server.
STATUS_TOO_MANY_NAMES 0xC00000CD	The name limit for the network adapter card of the local computer was exceeded.
STATUS_TOO_MANY_SESSIONS 0xC00000CE	The network BIOS session limit was exceeded.
STATUS_SHARING_PAUSED 0xC00000CF	File sharing has been temporarily paused.
STATUS_REQUEST_NOT_ACCEPTED 0xC00000D0	No more connections can be made to this remote computer at this time because the computer has already accepted the maximum number of connections.
STATUS_REDIRECTOR_PAUSED 0xC00000D1	Print or disk redirection is temporarily paused.
STATUS_NET_WRITE_FAULT 0xC00000D2	A network data fault occurred.
STATUS_PROFILING_AT_LIMIT 0xC00000D3	The number of active profiling objects is at the maximum and no more may be started.
STATUS_NOT_SAME_DEVICE 0xC00000D4	{Incorrect Volume} The destination file of a rename request is located on a different device than the source of the rename request.
STATUS_FILE_RENAMED 0xC00000D5	The specified file has been renamed and thus cannot be modified.

Value	Meaning
STATUS_VIRTUAL_CIRCUIT_CLOSED 0xC00000D6	{Network Request Timeout} The session with a remote server has been disconnected because the time-out interval for a request has expired.
STATUS_NO_SECURITY_ON_OBJECT 0xC00000D7	Indicates an attempt was made to operate on the security of an object that does not have security associated with it.
STATUS_CANT_WAIT 0xC00000D8	Used to indicate that an operation cannot continue without blocking for I/O.
STATUS_PIPE_EMPTY 0xC00000D9	Used to indicate that a read operation was done on an empty pipe.
STATUS_CANT_ACCESS_DOMAIN_INFO 0xC00000DA	Configuration information could not be read from the domain controller, either because the machine is unavailable or access has been denied.
STATUS_CANT_TERMINATE_SELF 0xC00000DB	Indicates that a thread attempted to terminate itself by default (called NtTerminateThread with NULL) and it was the last thread in the current process.
STATUS_INVALID_SERVER_STATE 0xC00000DC	Indicates the Sam Server was in the wrong state to perform the desired operation.
STATUS_INVALID_DOMAIN_STATE 0xC00000DD	Indicates the domain was in the wrong state to perform the desired operation.
STATUS_INVALID_DOMAIN_ROLE 0xC00000DE	This operation is only allowed for the primary domain controller of the domain.
STATUS_NO_SUCH_DOMAIN 0xC00000DF	The specified domain did not exist.
STATUS_DOMAIN_EXISTS 0xC00000E0	The specified domain already exists.
STATUS_DOMAIN_LIMIT_EXCEEDED 0xC00000E1	An attempt was made to exceed the limit on the number of domains per server for this release.
STATUS_OPLOCK_NOT_GRANTED 0xC00000E2	An error status returned when the opportunistic lock (oplock) request is denied.
STATUS_INVALID_OPLOCK_PROTOCOL 0xC00000E3	An error status returned when an invalid opportunistic lock (oplock) acknowledgment is received by a file

Value	Meaning
	system.
STATUS_INTERNAL_DB_CORRUPTION 0xC00000E4	This error indicates that the requested operation cannot be completed due to a catastrophic media failure or an on-disk data structure corruption.
STATUS_INTERNAL_ERROR 0xC00000E5	An internal error occurred.
STATUS_GENERIC_NOT_MAPPED 0xC00000E6	Indicates generic access types were contained in an access mask which should already be mapped to non-generic access types.
STATUS_BAD_DESCRIPTOR_FORMAT 0xC00000E7	Indicates a security descriptor is not in the necessary format (absolute or self-relative).
STATUS_INVALID_USER_BUFFER 0xC00000E8	An access to a user buffer failed at an expected point in time. This code is defined because the caller does not want to accept STATUS_ACCESS_VIOLATION in its filter.
STATUS_UNEXPECTED_IO_ERROR 0xC00000E9	If an I/O error that is not defined in the standard FsRtl filter is returned, it is converted to the following error, which is guaranteed to be in the filter. In this case, information is lost; however, the filter correctly handles the exception.
STATUS_UNEXPECTED_MM_CREATE_ERR 0xC00000EA	If an MM error that is not defined in the standard FsRtl filter is returned, it is converted to one of the following errors, which are guaranteed to be in the filter. In this case, information is lost; however, the filter correctly handles the exception.
STATUS_UNEXPECTED_MM_MAP_ERROR 0xC00000EB	If an MM error that is not defined in the standard FsRtl filter is returned, it is converted to one of the following errors, which are guaranteed to be in the filter. In this case, information is lost; however, the filter correctly handles the exception.
STATUS_UNEXPECTED_MM_EXTEND_ERR 0xC00000EC	If an MM error that is not defined in the standard FsRtl filter is returned, it is converted to one of the following errors, which are guaranteed to be in the filter. In this case, information is lost; however, the filter correctly handles the exception.

Value	Meaning
STATUS_NOT_LOGON_PROCESS 0xC00000ED	The requested action is restricted for use by logon processes only. The calling process has not registered as a logon process.
STATUS_LOGON_SESSION_EXISTS 0xC00000EE	An attempt has been made to start a new session manager or LSA logon session by using an ID that is already in use.
STATUS_INVALID_PARAMETER_1 0xC00000EF	An invalid parameter was passed to a service or function as the first argument.
STATUS_INVALID_PARAMETER_2 0xC00000F0	An invalid parameter was passed to a service or function as the second argument.
STATUS_INVALID_PARAMETER_3 0xC00000F1	An invalid parameter was passed to a service or function as the third argument.
STATUS_INVALID_PARAMETER_4 0xC00000F2	An invalid parameter was passed to a service or function as the fourth argument.
STATUS_INVALID_PARAMETER_5 0xC00000F3	An invalid parameter was passed to a service or function as the fifth argument.
STATUS_INVALID_PARAMETER_6 0xC00000F4	An invalid parameter was passed to a service or function as the sixth argument.
STATUS_INVALID_PARAMETER_7 0xC00000F5	An invalid parameter was passed to a service or function as the seventh argument.
STATUS_INVALID_PARAMETER_8 0xC00000F6	An invalid parameter was passed to a service or function as the eighth argument.
STATUS_INVALID_PARAMETER_9 0xC00000F7	An invalid parameter was passed to a service or function as the ninth argument.
STATUS_INVALID_PARAMETER_10 0xC00000F8	An invalid parameter was passed to a service or function as the tenth argument.
STATUS_INVALID_PARAMETER_11 0xC00000F9	An invalid parameter was passed to a service or function as the eleventh argument.
STATUS_INVALID_PARAMETER_12 0xC00000FA	An invalid parameter was passed to a service or function as the twelfth argument.

Value	Meaning
STATUS_REDIRECTOR_NOT_STARTED 0xC00000FB	An attempt was made to access a network file, but the network software was not yet started.
STATUS_REDIRECTOR_STARTED 0xC00000FC	An attempt was made to start the redirector, but the redirector has already been started.
STATUS_STACK_OVERFLOW 0xC00000FD	A new guard page for the stack cannot be created.
STATUS_NO_SUCH_PACKAGE 0xC00000FE	A specified authentication package is unknown.
STATUS_BAD_FUNCTION_TABLE 0xC00000FF	A malformed function table was encountered during an unwind operation.
STATUS_VARIABLE_NOT_FOUND 0xC0000100	Indicates the specified environment variable name was not found in the specified environment block.
STATUS_DIRECTORY_NOT_EMPTY 0xC0000101	Indicates that the directory trying to be deleted is not empty.
STATUS_FILE_CORRUPT_ERROR 0xC0000102	{Corrupt File} The file or directory %hs is corrupt and unreadable. Run the Chkdsk utility.
STATUS_NOT_A_DIRECTORY 0xC0000103	A requested opened file is not a directory.
STATUS_BAD_LOGON_SESSION_STATE 0xC0000104	The logon session is not in a state that is consistent with the requested operation.
STATUS_LOGON_SESSION_COLLISION 0xC0000105	An internal LSA error has occurred. An authentication package has requested the creation of a logon session but the ID of an already existing logon session has been specified.
STATUS_NAME_TOO_LONG 0xC0000106	A specified name string is too long for its intended use.
STATUS_FILES_OPEN 0xC0000107	The user attempted to force close the files on a redirected drive, but there were opened files on the drive, and the user did not specify a sufficient level of force.
STATUS_CONNECTION_IN_USE 0xC0000108	The user attempted to force close the files on a redirected drive, but there were opened directories on the drive, and the user did not specify a sufficient level of force.

Value	Meaning
STATUS_MESSAGE_NOT_FOUND 0xC0000109	RtlFindMessage could not locate the requested message ID in the message table resource.
STATUS_PROCESS_IS_TERMINATING 0xC000010A	An attempt was made to duplicate an object handle into or out of an exiting process.
STATUS_INVALID_LOGON_TYPE 0xC000010B	Indicates an invalid value has been provided for the LogonType requested.
STATUS_NO_GUID_TRANSLATION 0xC000010C	Indicates that an attempt was made to assign protection to a file system file or directory and one of the SIDs in the security descriptor could not be translated into a GUID that could be stored by the file system. This causes the protection attempt to fail, which may cause a file creation attempt to fail.
STATUS_CANNOT_IMPERSONATE 0xC000010D	Indicates that an attempt has been made to impersonate via a named pipe that has not yet been read from.
STATUS_IMAGE_ALREADY_LOADED 0xC000010E	Indicates that the specified image is already loaded.
STATUS_ABIOS_NOT_PRESENT 0xC000010F	STATUS_ABIOS_NOT_PRESENT
STATUS_ABIOS_LID_NOT_EXIST 0xC0000110	STATUS_ABIOS_LID_NOT_EXIST
STATUS_ABIOS_LID_ALREADY_OWNED 0xC0000111	STATUS_ABIOS_LID_ALREADY_OWNED
STATUS_ABIOS_NOT_LID_OWNER 0xC0000112	STATUS_ABIOS_NOT_LID_OWNER
STATUS_ABIOS_INVALID_COMMAND 0xC0000113	STATUS_ABIOS_INVALID_COMMAND
STATUS_ABIOS_INVALID_LID 0xC0000114	STATUS_ABIOS_INVALID_LID
STATUS_ABIOS_SELECTOR_NOT_AVAILABLE 0xC0000115	STATUS_ABIOS_SELECTOR_NOT_AVAILABLE
STATUS_ABIOS_INVALID_SELECTOR 0xC0000116	STATUS_ABIOS_INVALID_SELECTOR
STATUS_NO_LDT 0xC0000117	Indicates that an attempt was made to change the size of the LDT for a process that has no LDT.

Value	Meaning
STATUS_INVALID_LDT_SIZE 0xC0000118	Indicates that an attempt was made to grow an LDT by setting its size, or that the size was not an even number of selectors.
STATUS_INVALID_LDT_OFFSET 0xC0000119	Indicates that the starting value for the LDT information was not an integral multiple of the selector size.
STATUS_INVALID_LDT_DESCRIPTOR 0xC000011A	Indicates that the user supplied an invalid descriptor when trying to set up LDT descriptors.
STATUS_INVALID_IMAGE_NE_FORMAT 0xC000011B	The specified image file did not have the correct format. It appears to be NE format.
STATUS_RXACT_INVALID_STATE 0xC000011C	Indicates that the transaction state of a registry subtree is incompatible with the requested operation. For example, a request has been made to start a new transaction with one already in progress, or a request has been made to apply a transaction when one is not currently in progress.
STATUS_RXACT_COMMIT_FAILURE 0xC000011D	Indicates an error has occurred during a registry transaction commit. The database has been left in an unknown, but probably inconsistent, state. The state of the registry transaction is left as COMMITTING.
STATUS_MAPPED_FILE_SIZE_ZERO 0xC000011E	An attempt was made to map a file of size zero with the maximum size specified as zero.
STATUS_TOO_MANY_OPENED_FILES 0xC000011F	Too many files are opened on a remote server. This error should only be returned by the Windows redirector on a remote drive.
STATUS_CANCELLED 0xC0000120	The I/O request was canceled.
STATUS_CANNOT_DELETE 0xC0000121	An attempt has been made to remove a file or directory that cannot be deleted.
STATUS_INVALID_COMPUTER_NAME 0xC0000122	Indicates a name that was specified as a remote computer name is syntactically invalid.
STATUS_FILE_DELETED 0xC0000123	An I/O request other than close was performed on a file after it was deleted, which can only happen to a request that did not complete before the last handle was closed via NtClose.



Value	Meaning
STATUS_SPECIAL_ACCOUNT 0xC0000124	Indicates an operation that is incompatible with built-in accounts has been attempted on a built-in (special) SAM account. For example, built-in accounts cannot be deleted.
STATUS_SPECIAL_GROUP 0xC0000125	The operation requested may not be performed on the specified group because it is a built-in special group.
STATUS_SPECIAL_USER 0xC0000126	The operation requested may not be performed on the specified user because it is a built-in special user.
STATUS_MEMBERS_PRIMARY_GROUP 0xC0000127	Indicates a member cannot be removed from a group because the group is currently the member's primary group.
STATUS_FILE_CLOSED 0xC0000128	An I/O request other than close and several other special case operations was attempted using a file object that had already been closed.
STATUS_TOO_MANY_THREADS 0xC0000129	Indicates a process has too many threads to perform the requested action. For example, assignment of a primary token may only be performed when a process has zero or one threads.
STATUS_THREAD_NOT_IN_PROCESS 0xC000012A	An attempt was made to operate on a thread within a specific process, but the specified thread is not in the specified process.
STATUS_TOKEN_ALREADY_IN_USE 0xC000012B	An attempt was made to establish a token for use as a primary token but the token is already in use. A token can only be the primary token of one process at a time.
STATUS_PAGEFILE_QUOTA_EXCEEDED 0xC000012C	The page file quota was exceeded.
STATUS_COMMITMENT_LIMIT 0xC000012D	{Out of Virtual Memory} Your system is low on virtual memory. To ensure that Windows runs correctly, increase the size of your virtual memory paging file. For more information, see Help.
STATUS_INVALID_IMAGE_LE_FORMAT 0xC000012E	The specified image file did not have the correct format: it appears to be LE format.
STATUS_INVALID_IMAGE_NOT_MZ 0xC000012F	The specified image file did not have the correct format: it did not have an initial MZ.

Value	Meaning
STATUS_INVALID_IMAGE_PROTECT 0xC0000130	The specified image file did not have the correct format: it did not have a proper e_lfarlc in the MZ header.
STATUS_INVALID_IMAGE_WIN_16 0xC0000131	The specified image file did not have the correct format: it appears to be a 16-bit Windows image.
STATUS_LOGON_SERVER_CONFLICT 0xC0000132	The Netlogon service cannot start because another Netlogon service running in the domain conflicts with the specified role.
STATUS_TIME_DIFFERENCE_AT_DC 0xC0000133	The time at the primary domain controller is different from the time at the backup domain controller or member server by too large an amount.
STATUS_SYNCHRONIZATION_REQUIRED 0xC0000134	The SAM database on a Windows Server is significantly out of synchronization with the copy on the domain controller. A complete synchronization is required.
STATUS_DLL_NOT_FOUND 0xC0000135	{Unable To Locate Component} This application has failed to start because %hs was not found. Reinstalling the application may fix this problem.
STATUS_OPEN_FAILED 0xC0000136	The NtCreateFile API failed. This error should never be returned to an application; it is a place holder for the Windows LAN Manager Redirector to use in its internal error-mapping routines.
STATUS_IO_PRIVILEGE_FAILED 0xC0000137	{Privilege Failed} The I/O permissions for the process could not be changed.
STATUS_ORDINAL_NOT_FOUND 0xC0000138	{Ordinal Not Found} The ordinal %ld could not be located in the dynamic link library %hs.
STATUS_ENTRYPOINT_NOT_FOUND 0xC0000139	{Entry Point Not Found} The procedure entry point %hs could not be located in the dynamic link library %hs.
STATUS_CONTROL_C_EXIT 0xC000013A	{Application Exit by CTRL+C} The application terminated as a result of a CTRL+C.
STATUS_LOCAL_DISCONNECT 0xC000013B	{Virtual Circuit Closed} The network transport on your computer has closed a network connection. There may or may not be I/O requests outstanding.
STATUS_REMOTE_DISCONNECT 0xC000013C	{Virtual Circuit Closed} The network transport on a remote computer has closed a network connection. There may

Value	Meaning
	or may not be I/O requests outstanding.
STATUS_REMOTE_RESOURCES 0xC000013D	{Insufficient Resources on Remote Computer} The remote computer has insufficient resources to complete the network request. For example, the remote computer may not have enough available memory to carry out the request at this time.
STATUS_LINK_FAILED 0xC000013E	{Virtual Circuit Closed} An existing connection (virtual circuit) has been broken at the remote computer. There is probably something wrong with the network software protocol or the network hardware on the remote computer.
STATUS_LINK_TIMEOUT 0xC000013F	{Virtual Circuit Closed} The network transport on your computer has closed a network connection because it had to wait too long for a response from the remote computer.
STATUS_INVALID_CONNECTION 0xC0000140	The connection handle that was given to the transport was invalid.
STATUS_INVALID_ADDRESS 0xC0000141	The address handle that was given to the transport was invalid.
STATUS_DLL_INIT_FAILED 0xC0000142	{DLL Initialization Failed} Initialization of the dynamic link library %hs failed. The process is terminating abnormally.
STATUS_MISSING_SYSTEMFILE 0xC0000143	{Missing System File} The required system file %hs is bad or missing.
STATUS_UNHANDLED_EXCEPTION 0xC0000144	{Application Error} The exception %s (0x%08lx) occurred in the application at location 0x%08lx.
STATUS_APP_INIT_FAILURE 0xC0000145	{Application Error} The application failed to initialize properly (0x%lx). Click OK to terminate the application.
STATUS_PAGEFILE_CREATE_FAILED 0xC0000146	{Unable to Create Paging File} The creation of the paging file %hs failed (%lx). The requested size was %ld.
STATUS_NO_PAGEFILE 0xC0000147	{No Paging File Specified} No paging file was specified in the system configuration.
STATUS_INVALID_LEVEL 0xC0000148	{Incorrect System Call Level} An invalid level was passed into the specified system call.

Value	Meaning
STATUS_WRONG_PASSWORD_CORE 0xC0000149	{Incorrect Password to LAN Manager Server} You specified an incorrect password to a LAN Manager 2.x or MS-NET server.
STATUS_ILLEGAL_FLOAT_CONTEXT 0xC000014A	{EXCEPTION} A real-mode application issued a floating-point instruction and floating-point hardware is not present.
STATUS_PIPE_BROKEN 0xC000014B	The pipe operation has failed because the other end of the pipe has been closed.
STATUS_REGISTRY_CORRUPT 0xC000014C	{The Registry Is Corrupt} The structure of one of the files that contains registry data is corrupt; the image of the file in memory is corrupt; or the file could not be recovered because the alternate copy or log was absent or corrupt.
STATUS_REGISTRY_IO_FAILED 0xC000014D	An I/O operation initiated by the Registry failed and cannot be recovered. The registry could not read in, write out, or flush one of the files that contain the system's image of the registry.
STATUS_NO_EVENT_PAIR 0xC000014E	An event pair synchronization operation was performed using the thread-specific client/server event pair object, but no event pair object was associated with the thread.
STATUS_UNRECOGNIZED_VOLUME 0xC000014F	The volume does not contain a recognized file system. Be sure that all required file system drivers are loaded and that the volume is not corrupt.
STATUS_SERIAL_NO_DEVICE_INITED 0xC0000150	No serial device was successfully initialized. The serial driver will unload.
STATUS_NO_SUCH_ALIAS 0xC0000151	The specified local group does not exist.
STATUS_MEMBER_NOT_IN_ALIAS 0xC0000152	The specified account name is not a member of the group.
STATUS_MEMBER_IN_ALIAS 0xC0000153	The specified account name is already a member of the group.
STATUS_ALIAS_EXISTS 0xC0000154	The specified local group already exists.
STATUS_LOGON_NOT_GRANTED 0xC0000155	A requested type of logon (for example, interactive, network, and service) is not granted by the local security policy of the target system. Ask the system

Value	Meaning
	administrator to grant the necessary form of logon.
STATUS_TOO_MANY_SECRETS 0xC0000156	The maximum number of secrets that may be stored in a single system was exceeded. The length and number of secrets is limited to satisfy U.S. State Department export restrictions.
STATUS_SECRET_TOO_LONG 0xC0000157	The length of a secret exceeds the maximum allowable length. The length and number of secrets is limited to satisfy U.S. State Department export restrictions.
STATUS_INTERNAL_DB_ERROR 0xC0000158	The local security authority (LSA) database contains an internal inconsistency.
STATUS_FULLSCREEN_MODE 0xC0000159	The requested operation cannot be performed in full-screen mode.
STATUS_TOO_MANY_CONTEXT_IDS 0xC000015A	During a logon attempt, the user's security context accumulated too many security IDs. This is a very unusual situation. Remove the user from some global or local groups to reduce the number of security IDs to incorporate into the security context.
STATUS_LOGON_TYPE_NOT_GRANTED 0xC000015B	A user has requested a type of logon (for example, interactive or network) that has not been granted. An administrator has control over who may logon interactively and through the network.
STATUS_NOT_REGISTRY_FILE 0xC000015C	The system has attempted to load or restore a file into the registry, and the specified file is not in the format of a registry file.
STATUS_NT_CROSS_ENCRYPTION_REQUIRED 0xC000015D	An attempt was made to change a user password in the security account manager without providing the necessary Windows cross-encrypted password.
STATUS_DOMAIN_CTRLR_CONFIG_ERROR 0xC000015E	A Windows Server has an incorrect configuration.
STATUS_FT_MISSING_MEMBER 0xC000015F	An attempt was made to explicitly access the secondary copy of information via a device control to the fault tolerance driver and the secondary copy is not present in the system.

Value	Meaning
STATUS_ILL_FORMED_SERVICE_ENTRY 0xC0000160	A configuration registry node that represents a driver service entry was ill-formed and did not contain the required value entries.
STATUS_ILLEGAL_CHARACTER 0xC0000161	An illegal character was encountered. For a multibyte character set, this includes a lead byte without a succeeding trail byte. For the Unicode character set this includes the characters 0xFFFF and 0xFFFE.
STATUS_UNMAPPABLE_CHARACTER 0xC0000162	No mapping for the Unicode character exists in the target multibyte code page.
STATUS_UNDEFINED_CHARACTER 0xC0000163	The Unicode character is not defined in the Unicode character set that is installed on the system.
STATUS_FLOPPY_VOLUME 0xC0000164	The paging file cannot be created on a floppy disk.
STATUS_FLOPPY_ID_MARK_NOT_FOUND 0xC0000165	{Floppy Disk Error} While accessing a floppy disk, an ID address mark was not found.
STATUS_FLOPPY_WRONG_CYLINDER 0xC0000166	{Floppy Disk Error} While accessing a floppy disk, the track address from the sector ID field was found to be different from the track address that is maintained by the controller.
STATUS_FLOPPY_UNKNOWN_ERROR 0xC0000167	{Floppy Disk Error} The floppy disk controller reported an error that is not recognized by the floppy disk driver.
STATUS_FLOPPY_BAD_REGISTERS 0xC0000168	{Floppy Disk Error} While accessing a floppy-disk, the controller returned inconsistent results via its registers.
STATUS_DISK_RECALIBRATE_FAILED 0xC0000169	{Hard Disk Error} While accessing the hard disk, a recalibrate operation failed, even after retries.
STATUS_DISK_OPERATION_FAILED 0xC000016A	{Hard Disk Error} While accessing the hard disk, a disk operation failed even after retries.
STATUS_DISK_RESET_FAILED 0xC000016B	{Hard Disk Error} While accessing the hard disk, a disk controller reset was needed, but even that failed.
STATUS_SHARED_IRQ_BUSY 0xC000016C	An attempt was made to open a device that was sharing an interrupt request (IRQ) with other devices. At least one other device that uses that IRQ was

Value	Meaning
	already opened. Two concurrent opens of devices that share an IRQ and only work via interrupts is not supported for the particular bus type that the devices use.
STATUS_FT_ORPHANING 0xC000016D	{FT Orphaning} A disk that is part of a fault-tolerant volume can no longer be accessed.
STATUS_BIOS_FAILED_TO_CONNECT_INTERRUPT 0xC000016E	The basic input/output system (BIOS) failed to connect a system interrupt to the device or bus for which the device is connected.
STATUS_PARTITION_FAILURE 0xC0000172	The tape could not be partitioned.
STATUS_INVALID_BLOCK_LENGTH 0xC0000173	When accessing a new tape of a multi-volume partition, the current blocksize is incorrect.
STATUS_DEVICE_NOT_PARTITIONED 0xC0000174	The tape partition information could not be found when loading a tape.
STATUS_UNABLE_TO_LOCK_MEDIA 0xC0000175	An attempt to lock the eject media mechanism failed.
STATUS_UNABLE_TO_UNLOAD_MEDIA 0xC0000176	An attempt to unload media failed.
STATUS_EOM_OVERFLOW 0xC0000177	The physical end of tape was detected.
STATUS_NO_MEDIA 0xC0000178	{No Media} There is no media in the drive. Insert media into drive %hs.
STATUS_NO_SUCH_MEMBER 0xC000017A	A member could not be added to or removed from the local group because the member does not exist.
STATUS_INVALID_MEMBER 0xC000017B	A new member could not be added to a local group because the member has the wrong account type.
STATUS_KEY_DELETED 0xC000017C	An illegal operation was attempted on a registry key that has been marked for deletion.
STATUS_NO_LOG_SPACE 0xC000017D	The system could not allocate the required space in a registry log.
STATUS_TOO_MANY_SIDS 0xC000017E	Too many SIDs have been specified.
STATUS_LM_CROSS_ENCRYPTION_REQUIRED	An attempt was made to change a user

Value	Meaning
0xC000017F	password in the security account manager without providing the necessary LM cross-encrypted password.
STATUS_KEY_HAS_CHILDREN 0xC0000180	An attempt was made to create a symbolic link in a registry key that already has subkeys or values.
STATUS_CHILD_MUST_BE_VOLATILE 0xC0000181	An attempt was made to create a stable subkey under a volatile parent key.
STATUS_DEVICE_CONFIGURATION_ERROR 0xC0000182	The I/O device is configured incorrectly or the configuration parameters to the driver are incorrect.
STATUS_DRIVER_INTERNAL_ERROR 0xC0000183	An error was detected between two drivers or within an I/O driver.
STATUS_INVALID_DEVICE_STATE 0xC0000184	The device is not in a valid state to perform this request.
STATUS_IO_DEVICE_ERROR 0xC0000185	The I/O device reported an I/O error.
STATUS_DEVICE_PROTOCOL_ERROR 0xC0000186	A protocol error was detected between the driver and the device.
STATUS_BACKUP_CONTROLLER 0xC0000187	This operation is only allowed for the primary domain controller of the domain.
STATUS_LOG_FILE_FULL 0xC0000188	The log file space is insufficient to support this operation.
STATUS_TOO_LATE 0xC0000189	A write operation was attempted to a volume after it was dismounted.
STATUS_NO_TRUST_LSA_SECRET 0xC000018A	The workstation does not have a trust secret for the primary domain in the local LSA database.
STATUS_NO_TRUST_SAM_ACCOUNT 0xC000018B	The SAM database on the Windows Server does not have a computer account for this workstation trust relationship.
STATUS_TRUSTED_DOMAIN_FAILURE 0xC000018C	The logon request failed because the trust relationship between the primary domain and the trusted domain failed.
STATUS_TRUSTED_RELATIONSHIP_FAILURE 0xC000018D	The logon request failed because the trust relationship between this workstation and the primary domain failed.



Value	Meaning
STATUS_EVENTLOG_FILE_CORRUPT 0xC000018E	The Eventlog log file is corrupt.
STATUS_EVENTLOG_CANT_START 0xC000018F	No Eventlog log file could be opened. The Eventlog service did not start.
STATUS_TRUST_FAILURE 0xC0000190	The network logon failed. This may be because the validation authority cannot be reached.
STATUS_MUTANT_LIMIT_EXCEEDED 0xC0000191	An attempt was made to acquire a mutant such that its maximum count would have been exceeded.
STATUS_NETLOGON_NOT_STARTED 0xC0000192	An attempt was made to logon, but the NetLogon service was not started.
STATUS_ACCOUNT_EXPIRED 0xC0000193	The user account has expired.
STATUS_POSSIBLE_DEADLOCK 0xC0000194	{EXCEPTION} Possible deadlock condition.
STATUS_NETWORK_CREDENTIAL_CONFLICT 0xC0000195	Multiple connections to a server or shared resource by the same user, using more than one user name, are not allowed. Disconnect all previous connections to the server or shared resource and try again.
STATUS_REMOTE_SESSION_LIMIT 0xC0000196	An attempt was made to establish a session to a network server, but there are already too many sessions established to that server.
STATUS_EVENTLOG_FILE_CHANGED 0xC0000197	The log file has changed between reads.
STATUS_NOLOGON_INTERDOMAIN_TRUST_ACCOUNT 0xC0000198	The account used is an interdomain trust account. Use your global user account or local user account to access this server.
STATUS_NOLOGON_WORKSTATION_TRUST_ACCOUNT 0xC0000199	The account used is a computer account. Use your global user account or local user account to access this server.
STATUS_NOLOGON_SERVER_TRUST_ACCOUNT 0xC000019A	The account used is a server trust account. Use your global user account or local user account to access this server.
STATUS_DOMAIN_TRUST_INCONSISTENT 0xC000019B	The name or SID of the specified domain is inconsistent with the trust information for that domain.

Value	Meaning
STATUS_FS_DRIVER_REQUIRED 0xC000019C	A volume has been accessed for which a file system driver is required that has not yet been loaded.
STATUS_IMAGE_ALREADY_LOADED_AS_DLL 0xC000019D	Indicates that the specified image is already loaded as a DLL.
STATUS_NETWORK_OPEN_RESTRICTION 0xC0000201	A remote open failed because the network open restrictions were not satisfied.
STATUS_NO_USER_SESSION_KEY 0xC0000202	There is no user session key for the specified logon session.
STATUS_USER_SESSION_DELETED 0xC0000203	The remote user session has been deleted.
STATUS_RESOURCE_LANG_NOT_FOUND 0xC0000204	Indicates the specified resource language ID cannot be found in the image file.
STATUS_INSUFF_SERVER_RESOURCES 0xC0000205	Insufficient server resources exist to complete the request.
STATUS_INVALID_BUFFER_SIZE 0xC0000206	The size of the buffer is invalid for the specified operation.
STATUS_INVALID_ADDRESS_COMPONENT 0xC0000207	The transport rejected the specified network address as invalid.
STATUS_INVALID_ADDRESS_WILDCARD 0xC0000208	The transport rejected the specified network address due to invalid use of a wildcard.
STATUS_TOO_MANY_ADDRESSES 0xC0000209	The transport address could not be opened because all the available addresses are in use.
STATUS_ADDRESS_ALREADY_EXISTS 0xC000020A	The transport address could not be opened because it already exists.
STATUS_ADDRESS_CLOSED 0xC000020B	The transport address is now closed.
STATUS_CONNECTION_DISCONNECTED 0xC000020C	The transport connection is now disconnected.
STATUS_CONNECTION_RESET 0xC000020D	The transport connection has been reset.
STATUS_TOO_MANY_NODES 0xC000020E	The transport cannot dynamically acquire any more nodes.
STATUS_TRANSACTION_ABORTED	The transport aborted a pending

Value	Meaning
0xC000020F	transaction.
STATUS_TRANSACTION_TIMED_OUT 0xC0000210	The transport timed out a request that is waiting for a response.
STATUS_TRANSACTION_NO_RELEASE 0xC0000211	The transport did not receive a release for a pending response.
STATUS_TRANSACTION_NO_MATCH 0xC0000212	The transport did not find a transaction that matches the specific token.
STATUS_TRANSACTION_RESPONDED 0xC0000213	The transport had previously responded to a transaction request.
STATUS_TRANSACTION_INVALID_ID 0xC0000214	The transport does not recognize the specified transaction request ID.
STATUS_TRANSACTION_INVALID_TYPE 0xC0000215	The transport does not recognize the specified transaction request type.
STATUS_NOT_SERVER_SESSION 0xC0000216	The transport can only process the specified request on the server side of a session.
STATUS_NOT_CLIENT_SESSION 0xC0000217	The transport can only process the specified request on the client side of a session.
STATUS_CANNOT_LOAD_REGISTRY_FILE 0xC0000218	{Registry File Failure} The registry cannot load the hive (file): %hs or its log or alternate. It is corrupt, absent, or not writable.
STATUS_DEBUG_ATTACH_FAILED 0xC0000219	{Unexpected Failure in DebugActiveProcess} An unexpected failure occurred while processing a DebugActiveProcess API request. You may choose OK to terminate the process, or Cancel to ignore the error.
STATUS_SYSTEM_PROCESS_TERMINATED 0xC000021A	{Fatal System Error} The %hs system process terminated unexpectedly with a status of 0x%08x (0x%08x 0x%08x). The system has been shut down.
STATUS_DATA_NOT_ACCEPTED 0xC000021B	{Data Not Accepted} The TDI client could not handle the data received during an indication.
STATUS_NO_BROWSER_SERVERS_FOUND 0xC000021C	{Unable to Retrieve Browser Server List} The list of servers for this workgroup is not currently available.
STATUS_VDM_HARD_ERROR 0xC000021D	NTVDM encountered a hard error.

Value	Meaning
STATUS_DRIVER_CANCEL_TIMEOUT 0xC000021E	{Cancel Timeout} The driver %hs failed to complete a canceled I/O request in the allotted time.
STATUS_REPLY_MESSAGE_MISMATCH 0xC000021F	{Reply Message Mismatch} An attempt was made to reply to an LPC message, but the thread specified by the client ID in the message was not waiting on that message.
STATUS_MAPPED_ALIGNMENT 0xC0000220	{Mapped View Alignment Incorrect} An attempt was made to map a view of a file, but either the specified base address or the offset into the file were not aligned on the proper allocation granularity.
STATUS_IMAGE_CHECKSUM_MISMATCH 0xC0000221	{Bad Image Checksum} The image %hs is possibly corrupt. The header checksum does not match the computed checksum.
STATUS_LOST_WRITEBEHIND_DATA 0xC0000222	{Delayed Write Failed} Windows was unable to save all the data for the file %hs. The data has been lost. This error may be caused by a failure of your computer hardware or network connection. Try to save this file elsewhere.
STATUS_CLIENT_SERVER_PARAMETERS_INVALID 0xC0000223	The parameters passed to the server in the client/server shared memory window were invalid. Too much data may have been put in the shared memory window.
STATUS_PASSWORD_MUST_CHANGE 0xC0000224	The user password must be changed before logging on the first time.
STATUS_NOT_FOUND 0xC0000225	The object was not found.
STATUS_NOT_TINY_STREAM 0xC0000226	The stream is not a tiny stream.
STATUS_RECOVERY_FAILURE 0xC0000227	A transaction recovery failed.
STATUS_STACK_OVERFLOW_READ 0xC0000228	The request must be handled by the stack overflow code.
STATUS_FAIL_CHECK 0xC0000229	A consistency check failed.
STATUS_DUPLICATE_OBJECTID	The attempt to insert the ID in the index failed because the ID is already in

Value	Meaning
0xC000022A	the index.
STATUS_OBJECTID_EXISTS 0xC000022B	The attempt to set the object ID failed because the object already has an ID.
STATUS_CONVERT_TO_LARGE 0xC000022C	Internal OFS status codes indicating how an allocation operation is handled. Either it is retried after the containing oNode is moved or the extent stream is converted to a large stream.
STATUS_RETRY 0xC000022D	The request needs to be retried.
STATUS_FOUND_OUT_OF_SCOPE 0xC000022E	The attempt to find the object found an object on the volume that matches by ID; however, it is out of the scope of the handle that is used for the operation.
STATUS_ALLOCATE_BUCKET 0xC000022F	The bucket array must be grown. Retry the transaction after doing so.
STATUS_PROPSET_NOT_FOUND 0xC0000230	The specified property set does not exist on the object.
STATUS_MARSHALL_OVERFLOW 0xC0000231	The user/kernel marshaling buffer has overflowed.
STATUS_INVALID_VARIANT 0xC0000232	The supplied variant structure contains invalid data.
STATUS_DOMAIN_CONTROLLER_NOT_FOUND 0xC0000233	A domain controller for this domain was not found.
STATUS_ACCOUNT_LOCKED_OUT 0xC0000234	The user account has been automatically locked because too many invalid logon attempts or password change attempts have been requested.
STATUS_HANDLE_NOT_CLOSABLE 0xC0000235	NtClose was called on a handle that was protected from close via NtSetInformationObject.
STATUS_CONNECTION_REFUSED 0xC0000236	The transport-connection attempt was refused by the remote system.
STATUS_GRACEFUL_DISCONNECT 0xC0000237	The transport connection was gracefully closed.
STATUS_ADDRESS_ALREADY_ASSOCIATED 0xC0000238	The transport endpoint already has an address associated with it.
STATUS_ADDRESS_NOT_ASSOCIATED 0xC0000239	An address has not yet been associated with the transport endpoint.

Value	Meaning
STATUS_CONNECTION_INVALID 0xC000023A	An operation was attempted on a nonexistent transport connection.
STATUS_CONNECTION_ACTIVE 0xC000023B	An invalid operation was attempted on an active transport connection.
STATUS_NETWORK_UNREACHABLE 0xC000023C	The remote network is not reachable by the transport.
STATUS_HOST_UNREACHABLE 0xC000023D	The remote system is not reachable by the transport.
STATUS_PROTOCOL_UNREACHABLE 0xC000023E	The remote system does not support the transport protocol.
STATUS_PORT_UNREACHABLE 0xC000023F	No service is operating at the destination port of the transport on the remote system.
STATUS_REQUEST_ABORTED 0xC0000240	The request was aborted.
STATUS_CONNECTION_ABORTED 0xC0000241	The transport connection was aborted by the local system.
STATUS_BAD_COMPRESSION_BUFFER 0xC0000242	The specified buffer contains ill-formed data.
STATUS_USER_MAPPED_FILE 0xC0000243	The requested operation cannot be performed on a file with a user mapped section open.
STATUS_AUDIT_FAILED 0xC0000244	{Audit Failed} An attempt to generate a security audit failed.
STATUS_TIMER_RESOLUTION_NOT_SET 0xC0000245	The timer resolution was not previously set by the current process.
STATUS_CONNECTION_COUNT_LIMIT 0xC0000246	A connection to the server could not be made because the limit on the number of concurrent connections for this account has been reached.
STATUS_LOGIN_TIME_RESTRICTION 0xC0000247	Attempting to log on during an unauthorized time of day for this account.
STATUS_LOGIN_WKSTA_RESTRICTION 0xC0000248	The account is not authorized to log on from this station.
STATUS_IMAGE_MP_UP_MISMATCH 0xC0000249	{UP/MP Image Mismatch} The image %hs has been modified for use on a uniprocessor system, but you are running it on a multiprocessor machine.

Value	Meaning
	Reinstall the image file.
STATUS_INSUFFICIENT_LOGON_INFO 0xC0000250	There is insufficient account information to log you on.
STATUS_BAD_DLL_ENTRYPOINT 0xC0000251	{Invalid DLL Entrypoint} The dynamic link library %hs is not written correctly. The stack pointer has been left in an inconsistent state. The entry point should be declared as WINAPI or STDCALL. Select YES to fail the DLL load. Select NO to continue execution. Selecting NO may cause the application to operate incorrectly.
STATUS_BAD_SERVICE_ENTRYPOINT 0xC0000252	{Invalid Service Callback Entrypoint} The %hs service is not written correctly. The stack pointer has been left in an inconsistent state. The callback entry point should be declared as WINAPI or STDCALL. Selecting OK will cause the service to continue operation. However, the service process may operate incorrectly.
STATUS_LPC_REPLY_LOST 0xC0000253	The server received the messages but did not send a reply.
STATUS_IP_ADDRESS_CONFLICT1 0xC0000254	There is an IP address conflict with another system on the network.
STATUS_IP_ADDRESS_CONFLICT2 0xC0000255	There is an IP address conflict with another system on the network.
STATUS_REGISTRY_QUOTA_LIMIT 0xC0000256	{Low On Registry Space} The system has reached the maximum size that is allowed for the system part of the registry. Additional storage requests will be ignored.
STATUS_PATH_NOT_COVERED 0xC0000257	The contacted server does not support the indicated part of the DFS namespace.
STATUS_NO_CALLBACK_ACTIVE 0xC0000258	A callback return system service cannot be executed when no callback is active.
STATUS_LICENSE_QUOTA_EXCEEDED 0xC0000259	The service being accessed is licensed for a particular number of connections. No more connections can be made to the service at this time because the service has already accepted the maximum number of connections.
STATUS_PWD_TOO_SHORT 0xC000025A	The password provided is too short to meet the policy of your user account.

Value	Meaning
	Choose a longer password.
STATUS_PWD_TOO_RECENT 0xC000025B	The policy of your user account does not allow you to change passwords too frequently. This is done to prevent users from changing back to a familiar, but potentially discovered, password. If you feel your password has been compromised, contact your administrator immediately to have a new one assigned.
STATUS_PWD_HISTORY_CONFLICT 0xC000025C	You have attempted to change your password to one that you have used in the past. The policy of your user account does not allow this. Select a password that you have not previously used.
STATUS_PLUGPLAY_NO_DEVICE 0xC000025E	You have attempted to load a legacy device driver while its device instance had been disabled.
STATUS_UNSUPPORTED_COMPRESSION 0xC000025F	The specified compression format is unsupported.
STATUS_INVALID_HW_PROFILE 0xC0000260	The specified hardware profile configuration is invalid.
STATUS_INVALID_PLUGPLAY_DEVICE_PATH 0xC0000261	The specified Plug and Play registry device path is invalid.
STATUS_DRIVER_ORDINAL_NOT_FOUND 0xC0000262	{Driver Entry Point Not Found} The %hs device driver could not locate the ordinal %ld in driver %hs.
STATUS_DRIVER_ENTRYPOINT_NOT_FOUND 0xC0000263	{Driver Entry Point Not Found} The %hs device driver could not locate the entry point %hs in driver %hs.
STATUS_RESOURCE_NOT_OWNED 0xC0000264	{Application Error} The application attempted to release a resource it did not own. Click OK to terminate the application.
STATUS_TOO_MANY_LINKS 0xC0000265	An attempt was made to create more links on a file than the file system supports.
STATUS_QUOTA_LIST_INCONSISTENT 0xC0000266	The specified quota list is internally inconsistent with its descriptor.
STATUS_FILE_IS_OFFLINE 0xC0000267	The specified file has been relocated to offline storage.
STATUS_EVALUATION_EXPIRATION	{Windows Evaluation Notification} The evaluation period for this installation of



Value	Meaning
0xC0000268	Windows has expired. This system will shutdown in 1 hour. To restore access to this installation of Windows, upgrade this installation by using a licensed distribution of this product.
STATUS_ILLEGAL_DLL_RELOCATION 0xC0000269	{Illegal System DLL Relocation} The system DLL %hs was relocated in memory. The application will not run properly. The relocation occurred because the DLL %hs occupied an address range that is reserved for Windows system DLLs. The vendor supplying the DLL should be contacted for a new DLL.
STATUS_LICENSE_VIOLATION 0xC000026A	{License Violation} The system has detected tampering with your registered product type. This is a violation of your software license. Tampering with the product type is not permitted.
STATUS_DLL_INIT_FAILED_LOGOFF 0xC000026B	{DLL Initialization Failed} The application failed to initialize because the window station is shutting down.
STATUS_DRIVER_UNABLE_TO_LOAD 0xC000026C	{Unable to Load Device Driver} %hs device driver could not be loaded. Error Status was 0x%x.
STATUS_DFS_UNAVAILABLE 0xC000026D	DFS is unavailable on the contacted server.
STATUS_VOLUME_DISMOUNTED 0xC000026E	An operation was attempted to a volume after it was dismounted.
STATUS_WX86_INTERNAL_ERROR 0xC000026F	An internal error occurred in the Win32 x86 emulation subsystem.
STATUS_WX86_FLOAT_STACK_CHECK 0xC0000270	Win32 x86 emulation subsystem floating-point stack check.
STATUS_VALIDATE_CONTINUE 0xC0000271	The validation process needs to continue on to the next step.
STATUS_NO_MATCH 0xC0000272	There was no match for the specified key in the index.
STATUS_NO_MORE_MATCHES 0xC0000273	There are no more matches for the current index enumeration.
STATUS_NOT_A_REPARSE_POINT 0xC0000275	The NTFS file or directory is not a reparse point.
STATUS_IO_REPARSE_TAG_INVALID	The Windows I/O reparse tag passed for

Value	Meaning
0xC0000276	the NTFS reparse point is invalid.
STATUS_IO_REPARSE_TAG_MISMATCH 0xC0000277	The Windows I/O reparse tag does not match the one that is in the NTFS reparse point.
STATUS_IO_REPARSE_DATA_INVALID 0xC0000278	The user data passed for the NTFS reparse point is invalid.
STATUS_IO_REPARSE_TAG_NOT_HANDLED 0xC0000279	The layered file system driver for this I/O tag did not handle it when needed.
STATUS_REPARSE_POINT_NOT_RESOLVED 0xC0000280	The NTFS symbolic link could not be resolved even though the initial file name is valid.
STATUS_DIRECTORY_IS_A_REPARSE_POINT 0xC0000281	The NTFS directory is a reparse point.
STATUS_RANGE_LIST_CONFLICT 0xC0000282	The range could not be added to the range list because of a conflict.
STATUS_SOURCE_ELEMENT_EMPTY 0xC0000283	The specified medium changer source element contains no media.
STATUS_DESTINATION_ELEMENT_FULL 0xC0000284	The specified medium changer destination element already contains media.
STATUS_ILLEGAL_ELEMENT_ADDRESS 0xC0000285	The specified medium changer element does not exist.
STATUS_MAGAZINE_NOT_PRESENT 0xC0000286	The specified element is contained in a magazine that is no longer present.
STATUS_REINITIALIZATION_NEEDED 0xC0000287	The device requires re-initialization due to hardware errors.
STATUS_ENCRYPTION_FAILED 0xC000028A	The file encryption attempt failed.
STATUS_DECRYPTION_FAILED 0xC000028B	The file decryption attempt failed.
STATUS_RANGE_NOT_FOUND 0xC000028C	The specified range could not be found in the range list.
STATUS_NO_RECOVERY_POLICY 0xC000028D	There is no encryption recovery policy configured for this system.
STATUS_NO_EFS 0xC000028E	The required encryption driver is not loaded for this system.
STATUS_WRONG_EFS	The file was encrypted with a different

Value	Meaning
0xC000028F	encryption driver than is currently loaded.
STATUS_NO_USER_KEYS 0xC0000290	There are no EFS keys defined for the user.
STATUS_FILE_NOT_ENCRYPTED 0xC0000291	The specified file is not encrypted.
STATUS_NOT_EXPORT_FORMAT 0xC0000292	The specified file is not in the defined EFS export format.
STATUS_FILE_ENCRYPTED 0xC0000293	The specified file is encrypted and the user does not have the ability to decrypt it.
STATUS_WMI_GUID_NOT_FOUND 0xC0000295	The GUID passed was not recognized as valid by a WMI data provider.
STATUS_WMI_INSTANCE_NOT_FOUND 0xC0000296	The instance name passed was not recognized as valid by a WMI data provider.
STATUS_WMI_ITEMID_NOT_FOUND 0xC0000297	The data item ID passed was not recognized as valid by a WMI data provider.
STATUS_WMI_TRY_AGAIN 0xC0000298	The WMI request could not be completed and should be retried.
STATUS_SHARED_POLICY 0xC0000299	The policy object is shared and can only be modified at the root.
STATUS_POLICY_OBJECT_NOT_FOUND 0xC000029A	The policy object does not exist when it should.
STATUS_POLICY_ONLY_IN_DS 0xC000029B	The requested policy information only lives in the Ds.
STATUS_VOLUME_NOT_UPGRADED 0xC000029C	The volume must be upgraded to enable this feature.
STATUS_REMOTE_STORAGE_NOT_ACTIVE 0xC000029D	The remote storage service is not operational at this time.
STATUS_REMOTE_STORAGE_MEDIA_ERROR 0xC000029E	The remote storage service encountered a media error.
STATUS_NO_TRACKING_SERVICE 0xC000029F	The tracking (workstation) service is not running.
STATUS_SERVER_SID_MISMATCH 0xC00002A0	The server process is running under a SID that is different from the SID that is required by client.

Value	Meaning
STATUS_DS_NO_ATTRIBUTE_OR_VALUE 0xC00002A1	The specified directory service attribute or value does not exist.
STATUS_DS_INVALID_ATTRIBUTE_SYNTAX 0xC00002A2	The attribute syntax specified to the directory service is invalid.
STATUS_DS_ATTRIBUTE_TYPE_UNDEFINED 0xC00002A3	The attribute type specified to the directory service is not defined.
STATUS_DS_ATTRIBUTE_OR_VALUE_EXISTS 0xC00002A4	The specified directory service attribute or value already exists.
STATUS_DS_BUSY 0xC00002A5	The directory service is busy.
STATUS_DS_UNAVAILABLE 0xC00002A6	The directory service is unavailable.
STATUS_DS_NO_RIDS_ALLOCATED 0xC00002A7	The directory service was unable to allocate a relative identifier.
STATUS_DS_NO_MORE_RIDS 0xC00002A8	The directory service has exhausted the pool of relative identifiers.
STATUS_DS_INCORRECT_ROLE_OWNER 0xC00002A9	The requested operation could not be performed because the directory service is not the master for that type of operation.
STATUS_DS_RIDMGR_INIT_ERROR 0xC00002AA	The directory service was unable to initialize the subsystem that allocates relative identifiers.
STATUS_DS_OBJ_CLASS_VIOLATION 0xC00002AB	The requested operation did not satisfy one or more constraints that are associated with the class of the object.
STATUS_DS_CANT_ON_NON_LEAF 0xC00002AC	The directory service can perform the requested operation only on a leaf object.
STATUS_DS_CANT_ON_RDN 0xC00002AD	The directory service cannot perform the requested operation on the Relatively Defined Name (RDN) attribute of an object.
STATUS_DS_CANT_MOD_OBJ_CLASS 0xC00002AE	The directory service detected an attempt to modify the object class of an object.
STATUS_DS_CROSS_DOM_MOVE_FAILED 0xC00002AF	An error occurred while performing a cross domain move operation.
STATUS_DS_GC_NOT_AVAILABLE 0xC00002B0	Unable to contact the global catalog server.

Value	Meaning
STATUS_DIRECTORY_SERVICE_REQUIRED 0xC00002B1	The requested operation requires a directory service, and none was available.
STATUS_REPARSE_ATTRIBUTE_CONFLICT 0xC00002B2	The reparse attribute cannot be set because it is incompatible with an existing attribute.
STATUS_CANT_ENABLE_DENY_ONLY 0xC00002B3	A group marked "use for deny only" cannot be enabled.
STATUS_FLOAT_MULTIPLE_FAULTS 0xC00002B4	{EXCEPTION} Multiple floating-point faults.
STATUS_FLOAT_MULTIPLE_TRAPS 0xC00002B5	{EXCEPTION} Multiple floating-point traps.
STATUS_DEVICE_REMOVED 0xC00002B6	The device has been removed.
STATUS_JOURNAL_DELETE_IN_PROGRESS 0xC00002B7	The volume change journal is being deleted.
STATUS_JOURNAL_NOT_ACTIVE 0xC00002B8	The volume change journal is not active.
STATUS_NOINTERFACE 0xC00002B9	The requested interface is not supported.
STATUS_DS_ADMIN_LIMIT_EXCEEDED 0xC00002C1	A directory service resource limit has been exceeded.
STATUS_DRIVER_FAILED_SLEEP 0xC00002C2	{System Standby Failed} The driver %hs does not support standby mode. Updating this driver may allow the system to go to standby mode.
STATUS_MUTUAL_AUTHENTICATION_FAILED 0xC00002C3	Mutual Authentication failed. The server password is out of date at the domain controller.
STATUS_CORRUPT_SYSTEM_FILE 0xC00002C4	The system file %1 has become corrupt and has been replaced.
STATUS_DATATYPE_MISALIGNMENT_ERROR 0xC00002C5	{EXCEPTION} Alignment Error A data type misalignment error was detected in a load or store instruction.
STATUS_WMI_READ_ONLY 0xC00002C6	The WMI data item or data block is read-only.
STATUS_WMI_SET_FAILURE 0xC00002C7	The WMI data item or data block could not be changed.

Value	Meaning
STATUS_COMMITMENT_MINIMUM 0xC00002C8	{Virtual Memory Minimum Too Low} Your system is low on virtual memory. Windows is increasing the size of your virtual memory paging file. During this process, memory requests for some applications may be denied. For more information, see Help.
STATUS_REG_NAT_CONSUMPTION 0xC00002C9	{EXCEPTION} Register NaT consumption faults. A NaT value is consumed on a non-speculative instruction.
STATUS_TRANSPORT_FULL 0xC00002CA	The transport element of the medium changer contains media, which is causing the operation to fail.
STATUS_DS_SAM_INIT_FAILURE 0xC00002CB	Security Accounts Manager initialization failed because of the following error: %hs Error Status: 0x%x. Click OK to shut down this system and restart in Directory Services Restore Mode. Check the event log for more detailed information.
STATUS_ONLY_IF_CONNECTED 0xC00002CC	This operation is supported only when you are connected to the server.
STATUS_DS_SENSITIVE_GROUP_VIOLATION 0xC00002CD	Only an administrator can modify the membership list of an administrative group.
STATUS_PNP_RESTART_ENUMERATION 0xC00002CE	A device was removed so enumeration must be restarted.
STATUS_JOURNAL_ENTRY_DELETED 0xC00002CF	The journal entry has been deleted from the journal.
STATUS_DS_CANT_MOD_PRIMARYGROUPID 0xC00002D0	Cannot change the primary group ID of a domain controller account.
STATUS_SYSTEM_IMAGE_BAD_SIGNATURE 0xC00002D1	{Fatal System Error} The system image %s is not properly signed. The file has been replaced with the signed file. The system has been shut down.
STATUS_PNP_REBOOT_REQUIRED 0xC00002D2	The device will not start without a reboot.
STATUS_POWER_STATE_INVALID 0xC00002D3	The power state of the current device cannot support this request.
STATUS_DS_INVALID_GROUP_TYPE 0xC00002D4	The specified group type is invalid.

Value	Meaning
STATUS_DS_NO_NEST_GLOBALGROUP_IN_MIXEDDOMAIN 0xC00002D5	In a mixed domain, no nesting of a global group if the group is security enabled.
STATUS_DS_NO_NEST_LOCALGROUP_IN_MIXEDDOMAIN 0xC00002D6	In a mixed domain, cannot nest local groups with other local groups, if the group is security enabled.
STATUS_DS_GLOBAL_CANT_HAVE_LOCAL_MEMBER 0xC00002D7	A global group cannot have a local group as a member.
STATUS_DS_GLOBAL_CANT_HAVE_UNIVERSAL_MEMBER 0xC00002D8	A global group cannot have a universal group as a member.
STATUS_DS_UNIVERSAL_CANT_HAVE_LOCAL_MEMBER 0xC00002D9	A universal group cannot have a local group as a member.
STATUS_DS_GLOBAL_CANT_HAVE_CROSSDOMAIN_MEMBER 0xC00002DA	A global group cannot have a cross-domain member.
STATUS_DS_LOCAL_CANT_HAVE_CROSSDOMAIN_LOCAL_MEMBER 0xC00002DB	A local group cannot have another cross-domain local group as a member.
STATUS_DS_HAVE_PRIMARY_MEMBERS 0xC00002DC	Cannot change to a security-disabled group because primary members are in this group.
STATUS_WMI_NOT_SUPPORTED 0xC00002DD	The WMI operation is not supported by the data block or method.
STATUS_INSUFFICIENT_POWER 0xC00002DE	There is not enough power to complete the requested operation.
STATUS_SAM_NEED_BOOTKEY_PASSWORD 0xC00002DF	The Security Accounts Manager needs to get the boot password.
STATUS_SAM_NEED_BOOTKEY_FLOPPY 0xC00002E0	The Security Accounts Manager needs to get the boot key from the floppy disk.
STATUS_DS_CANT_START 0xC00002E1	The directory service cannot start.
STATUS_DS_INIT_FAILURE 0xC00002E2	The directory service could not start because of the following error: %hs Error Status: 0x%x. Click OK to shut down this system and restart in Directory Services Restore Mode. Check the event log for more detailed information.
STATUS_SAM_INIT_FAILURE 0xC00002E3	The Security Accounts Manager initialization failed because of the following error: %hs Error Status:

Value	Meaning
	0x%x. Click OK to shut down this system and restart in Safe Mode. Check the event log for more detailed information.
STATUS_DS_GC_REQUIRED 0xC00002E4	The requested operation can be performed only on a global catalog server.
STATUS_DS_LOCAL_MEMBER_OF_LOCAL_ONLY 0xC00002E5	A local group can only be a member of other local groups in the same domain.
STATUS_DS_NO_FPO_IN_UNIVERSAL_GROUPS 0xC00002E6	Foreign security principals cannot be members of universal groups.
STATUS_DS_MACHINE_ACCOUNT_QUOTA_EXCEEDED 0xC00002E7	Your computer could not be joined to the domain. You have exceeded the maximum number of computer accounts you are allowed to create in this domain. Contact your system administrator to have this limit reset or increased.
STATUS_MULTIPLE_FAULT_VIOLATION 0xC00002E8	STATUS_MULTIPLE_FAULT_VIOLATION
STATUS_CURRENT_DOMAIN_NOT_ALLOWED 0xC00002E9	This operation cannot be performed on the current domain.
STATUS_CANNOT_MAKE 0xC00002EA	The directory or file cannot be created.
STATUS_SYSTEM_SHUTDOWN 0xC00002EB	The system is in the process of shutting down.
STATUS_DS_INIT_FAILURE_CONSOLE 0xC00002EC	Directory Services could not start because of the following error: %hs Error Status: 0x%x. Click OK to shut down the system. You can use the recovery console to diagnose the system further.
STATUS_DS_SAM_INIT_FAILURE_CONSOLE 0xC00002ED	Security Accounts Manager initialization failed because of the following error: %hs Error Status: 0x%x. Click OK to shut down the system. You can use the recovery console to diagnose the system further.
STATUS_UNFINISHED_CONTEXT_DELETED 0xC00002EE	A security context was deleted before the context was completed. This is considered a logon failure.
STATUS_NO_TGT_REPLY 0xC00002EF	The client is trying to negotiate a context and the server requires user-to-user but did not send a TGT reply.



Value	Meaning
STATUS_OBJECTID_NOT_FOUND 0xC00002F0	An object ID was not found in the file.
STATUS_NO_IP_ADDRESSES 0xC00002F1	Unable to accomplish the requested task because the local machine does not have any IP addresses.
STATUS_WRONG_CREDENTIAL_HANDLE 0xC00002F2	The supplied credential handle does not match the credential that is associated with the security context.
STATUS_CRYPTO_SYSTEM_INVALID 0xC00002F3	The crypto system or checksum function is invalid because a required function is unavailable.
STATUS_MAX_REFERRALS_EXCEEDED 0xC00002F4	The number of maximum ticket referrals has been exceeded.
STATUS_MUST_BE_KDC 0xC00002F5	The local machine must be a Kerberos KDC (domain controller) and it is not.
STATUS_STRONG_CRYPTO_NOT_SUPPORTED 0xC00002F6	The other end of the security negotiation requires strong crypto but it is not supported on the local machine.
STATUS_TOO_MANY_PRINCIPALS 0xC00002F7	The KDC reply contained more than one principal name.
STATUS_NO_PA_DATA 0xC00002F8	Expected to find PA data for a hint of what etype to use, but it was not found.
STATUS_PKINIT_NAME_MISMATCH 0xC00002F9	The client certificate does not contain a valid UPN, or does not match the client name in the logon request. Contact your administrator.
STATUS_SMARTCARD_LOGON_REQUIRED 0xC00002FA	Smart card logon is required and was not used.
STATUS_KDC_INVALID_REQUEST 0xC00002FB	An invalid request was sent to the KDC.
STATUS_KDC_UNABLE_TO_REFER 0xC00002FC	The KDC was unable to generate a referral for the service requested.
STATUS_KDC_UNKNOWN_ETYPE 0xC00002FD	The encryption type requested is not supported by the KDC.
STATUS_SHUTDOWN_IN_PROGRESS 0xC00002FE	A system shutdown is in progress.
STATUS_SERVER_SHUTDOWN_IN_PROGRESS 0xC00002FF	The server machine is shutting down.

Value	Meaning
STATUS_NOT_SUPPORTED_ON_SBS 0xC0000300	This operation is not supported on a computer running Windows Server 2003 for Small Business Server.
STATUS_WMI_GUID_DISCONNECTED 0xC0000301	The WMI GUID is no longer available.
STATUS_WMI_ALREADY_DISABLED 0xC0000302	Collection or events for the WMI GUID is already disabled.
STATUS_WMI_ALREADY_ENABLED 0xC0000303	Collection or events for the WMI GUID is already enabled.
STATUS_MFT_TOO_FRAGMENTED 0xC0000304	The master file table on the volume is too fragmented to complete this operation.
STATUS_COPY_PROTECTION_FAILURE 0xC0000305	Copy protection failure.
STATUS_CSS_AUTHENTICATION_FAILURE 0xC0000306	Copy protection error—DVD CSS Authentication failed.
STATUS_CSS_KEY_NOT_PRESENT 0xC0000307	Copy protection error—The specified sector does not contain a valid key.
STATUS_CSS_KEY_NOT_ESTABLISHED 0xC0000308	Copy protection error—DVD session key not established.
STATUS_CSS_SCRAMBLED_SECTOR 0xC0000309	Copy protection error—The read failed because the sector is encrypted.
STATUS_CSS_REGION_MISMATCH 0xC000030A	Copy protection error—The region of the specified DVD does not correspond to the region setting of the drive.
STATUS_CSS_RESETS_EXHAUSTED 0xC000030B	Copy protection error—The region setting of the drive may be permanent.
STATUS_PKINIT_FAILURE 0xC0000320	The Kerberos protocol encountered an error while validating the KDC certificate during smart card logon. There is more information in the system event log.
STATUS_SMARTCARD_SUBSYSTEM_FAILURE 0xC0000321	The Kerberos protocol encountered an error while attempting to use the smart card subsystem.
STATUS_NO_KERB_KEY 0xC0000322	The target server does not have acceptable Kerberos credentials.
STATUS_HOST_DOWN 0xC0000350	The transport determined that the remote system is down.

Value	Meaning
STATUS_UNSUPPORTED_PREAUTH 0xC0000351	An unsupported pre-authentication mechanism was presented to the Kerberos package.
STATUS_EFS_ALG_BLOB_TOO_BIG 0xC0000352	The encryption algorithm that is used on the source file needs a bigger key buffer than the one that is used on the destination file.
STATUS_PORT_NOT_SET 0xC0000353	An attempt to remove a processes DebugPort was made, but a port was not already associated with the process.
STATUS_DEBUGGER_INACTIVE 0xC0000354	An attempt to do an operation on a debug port failed because the port is in the process of being deleted.
STATUS_DS_VERSION_CHECK_FAILURE 0xC0000355	This version of Windows is not compatible with the behavior version of the directory forest, domain, or domain controller.
STATUS_AUDITING_DISABLED 0xC0000356	The specified event is currently not being audited.
STATUS_PRENT4_MACHINE_ACCOUNT 0xC0000357	The machine account was created prior to Windows NT 4.0. The account needs to be recreated.
STATUS_DS_AG_CANT_HAVE_UNIVERSAL_MEMBER 0xC0000358	An account group cannot have a universal group as a member.
STATUS_INVALID_IMAGE_WIN_32 0xC0000359	The specified image file did not have the correct format; it appears to be a 32-bit Windows image.
STATUS_INVALID_IMAGE_WIN_64 0xC000035A	The specified image file did not have the correct format; it appears to be a 64-bit Windows image.
STATUS_BAD_BINDINGS 0xC000035B	The client's supplied SSPI channel bindings were incorrect.
STATUS_NETWORK_SESSION_EXPIRED 0xC000035C	The client session has expired; so the client must re-authenticate to continue accessing the remote resources.
STATUS_APPHELP_BLOCK 0xC000035D	The AppHelp dialog box canceled; thus preventing the application from starting.
STATUS_ALL_SIDS_FILTERED 0xC000035E	The SID filtering operation removed all SIDs.
STATUS_NOT_SAFE_MODE_DRIVER 0xC000035F	The driver was not loaded because the system is starting in safe mode.

Value	Meaning
STATUS_ACCESS_DISABLED_BY_POLICY_DEFAULT 0xC0000361	Access to %1 has been restricted by your Administrator by the default software restriction policy level.
STATUS_ACCESS_DISABLED_BY_POLICY_PATH 0xC0000362	Access to %1 has been restricted by your Administrator by location with policy rule %2 placed on path %3.
STATUS_ACCESS_DISABLED_BY_POLICY_PUBLISHER 0xC0000363	Access to %1 has been restricted by your Administrator by software publisher policy.
STATUS_ACCESS_DISABLED_BY_POLICY_OTHER 0xC0000364	Access to %1 has been restricted by your Administrator by policy rule %2.
STATUS_FAILED_DRIVER_ENTRY 0xC0000365	The driver was not loaded because it failed its initialization call.
STATUS_DEVICE_ENUMERATION_ERROR 0xC0000366	The device encountered an error while applying power or reading the device configuration. This may be caused by a failure of your hardware or by a poor connection.
STATUS_MOUNT_POINT_NOT_RESOLVED 0xC0000368	The create operation failed because the name contained at least one mount point that resolves to a volume to which the specified device object is not attached.
STATUS_INVALID_DEVICE_OBJECT_PARAMETER 0xC0000369	The device object parameter is either not a valid device object or is not attached to the volume that is specified by the file name.
STATUS_MCA_OCCURED 0xC000036A	A machine check error has occurred. Check the system event log for additional information.
STATUS_DRIVER_BLOCKED_CRITICAL 0xC000036B	Driver %2 has been blocked from loading.
STATUS_DRIVER_BLOCKED 0xC000036C	Driver %2 has been blocked from loading.
STATUS_DRIVER_DATABASE_ERROR 0xC000036D	There was error [%2] processing the driver database.
STATUS_SYSTEM_HIVE_TOO_LARGE 0xC000036E	System hive size has exceeded its limit.
STATUS_INVALID_IMPORT_OF_NON_DLL 0xC000036F	A dynamic link library (DLL) referenced a module that was neither a DLL nor the process's executable image.
STATUS_NO_SECRETS	The local account store does not contain

Value	Meaning
0xC0000371	secret material for the specified account.
STATUS_ACCESS_DISABLED_NO_SAFER_UI_BY_POLICY 0xC0000372	Access to %1 has been restricted by your Administrator by policy rule %2.
STATUS_FAILED_STACK_SWITCH 0xC0000373	The system was not able to allocate enough memory to perform a stack switch.
STATUS_HEAP_CORRUPTION 0xC0000374	A heap has been corrupted.
STATUS_SMARTCARD_WRONG_PIN 0xC0000380	An incorrect PIN was presented to the smart card.
STATUS_SMARTCARD_CARD_BLOCKED 0xC0000381	The smart card is blocked.
STATUS_SMARTCARD_CARD_NOT_AUTHENTICATED 0xC0000382	No PIN was presented to the smart card.
STATUS_SMARTCARD_NO_CARD 0xC0000383	No smart card is available.
STATUS_SMARTCARD_NO_KEY_CONTAINER 0xC0000384	The requested key container does not exist on the smart card.
STATUS_SMARTCARD_NO_CERTIFICATE 0xC0000385	The requested certificate does not exist on the smart card.
STATUS_SMARTCARD_NO_KEYSET 0xC0000386	The requested keyset does not exist.
STATUS_SMARTCARD_IO_ERROR 0xC0000387	A communication error with the smart card has been detected.
STATUS_DOWNGRADE_DETECTED 0xC0000388	The system detected a possible attempt to compromise security. Ensure that you can contact the server that authenticated you.
STATUS_SMARTCARD_CERT_REVOKED 0xC0000389	The smart card certificate used for authentication has been revoked. Contact your system administrator. There may be additional information in the event log.
STATUS_ISSUING_CA_UNTRUSTED 0xC000038A	An untrusted certificate authority was detected while processing the smart card certificate that is used for authentication. Contact your system administrator.
STATUS_REVOCATION_OFFLINE_C	The revocation status of the smart card

Value	Meaning
0xC000038B	certificate that is used for authentication could not be determined. Contact your system administrator.
STATUS_PKINIT_CLIENT_FAILURE 0xC000038C	The smart card certificate used for authentication was not trusted. Contact your system administrator.
STATUS_SMARTCARD_CERT_EXPIRED 0xC000038D	The smart card certificate used for authentication has expired. Contact your system administrator.
STATUS_DRIVER_FAILED_PRIOR_UNLOAD 0xC000038E	The driver could not be loaded because a previous version of the driver is still in memory.
STATUS_SMARTCARD_SILENT_CONTEXT 0xC000038F	The smart card provider could not perform the action because the context was acquired as silent.
STATUS_PER_USER_TRUST_QUOTA_EXCEEDED 0xC0000401	The delegated trust creation quota of the current user has been exceeded.
STATUS_ALL_USER_TRUST_QUOTA_EXCEEDED 0xC0000402	The total delegated trust creation quota has been exceeded.
STATUS_USER_DELETE_TRUST_QUOTA_EXCEEDED 0xC0000403	The delegated trust deletion quota of the current user has been exceeded.
STATUS_DS_NAME_NOT_UNIQUE 0xC0000404	The requested name already exists as a unique identifier.
STATUS_DS_DUPLICATE_ID_FOUND 0xC0000405	The requested object has a non-unique identifier and cannot be retrieved.
STATUS_DS_GROUP_CONVERSION_ERROR 0xC0000406	The group cannot be converted due to attribute restrictions on the requested group type.
STATUS_VOLSnap_PREPARE_HIBERNATE 0xC0000407	{Volume Shadow Copy Service} Wait while the Volume Shadow Copy Service prepares volume %hs for hibernation.
STATUS_USER2USER_REQUIRED 0xC0000408	Kerberos sub-protocol User2User is required.
STATUS_STACK_BUFFER_OVERRUN 0xC0000409	The system detected an overrun of a stack-based buffer in this application. This overrun could potentially allow a malicious user to gain control of this application.
STATUS_NO_S4U_PROT_SUPPORT 0xC000040A	The Kerberos subsystem encountered an error. A service for user protocol request was made against a domain controller which does not support

Value	Meaning
	service for user.
STATUS_CROSSREALM_DELEGATION_FAILURE 0xC000040B	An attempt was made by this server to make a Kerberos constrained delegation request for a target that is outside the server realm. This action is not supported and the resulting error indicates a misconfiguration on the allowed-to-delegate-to list for this server. Contact your administrator.
STATUS_REVOCATION_OFFLINE_KDC 0xC000040C	The revocation status of the domain controller certificate used for smart card authentication could not be determined. There is additional information in the system event log. Contact your system administrator.
STATUS_ISSUING_CA_UNTRUSTED_KDC 0xC000040D	An untrusted certificate authority was detected while processing the domain controller certificate used for authentication. There is additional information in the system event log. Contact your system administrator.
STATUS_KDC_CERT_EXPIRED 0xC000040E	The domain controller certificate used for smart card logon has expired. Contact your system administrator with the contents of your system event log.
STATUS_KDC_CERT_REVOKED 0xC000040F	The domain controller certificate used for smart card logon has been revoked. Contact your system administrator with the contents of your system event log.
STATUS_PARAMETER_QUOTA_EXCEEDED 0xC0000410	Data present in one of the parameters is more than the function can operate on.
STATUS_HIBERNATION_FAILURE 0xC0000411	The system has failed to hibernate (The error code is %hs). Hibernation will be disabled until the system is restarted.
STATUS_DELAY_LOAD_FAILED 0xC0000412	An attempt to delay-load a .dll or get a function address in a delay-loaded .dll failed.
STATUS_AUTHENTICATION_FIREWALL_FAILED 0xC0000413	Logon Failure: The machine you are logging onto is protected by an authentication firewall. The specified account is not allowed to authenticate to the machine.
STATUS_VDM_DISALLOWED 0xC0000414	%hs is a 16-bit application. You do not have permissions to execute 16-bit applications. Check your permissions with your system administrator.

Value	Meaning
STATUS_HUNG_DISPLAY_DRIVER_THREAD 0xC0000415	{Display Driver Stopped Responding} The %hs display driver has stopped working normally. Save your work and reboot the system to restore full display functionality. The next time you reboot the machine a dialog will be displayed giving you a chance to report this failure to Microsoft.
STATUS_INSUFFICIENT_RESOURCE_FOR_SPECIFIED_SHARED_SECTION_SIZE 0xC0000416	The Desktop heap encountered an error while allocating session memory. There is more information in the system event log.
STATUS_INVALID_CRUNTIME_PARAMETER 0xC0000417	An invalid parameter was passed to a C runtime function.
STATUS_NTLM_BLOCKED 0xC0000418	The authentication failed because NTLM was blocked.
STATUS_ASSERTION_FAILURE 0xC0000420	STATUS_ASSERTION_FAILURE
STATUS_VERIFIER_STOP 0xC0000421	Application verifier has found an error in the current process.
STATUS_CALLBACK_POP_STACK 0xC0000423	STATUS_CALLBACK_POP_STACK
STATUS_INCOMPATIBLE_DRIVER_BLOCKED 0xC0000424	%2 has been blocked from loading due to incompatibility with this system. Contact your software vendor for a compatible version of the driver.
STATUS_HIVE_UNLOADED 0xC0000425	Illegal operation attempted on a registry key which has already been unloaded.
STATUS_COMPRESSION_DISABLED 0xC0000426	Compression is disabled for this volume.
STATUS_FILE_SYSTEM_LIMITATION 0xC0000427	The requested operation could not be completed due to a file system limitation.
STATUS_INVALID_IMAGE_HASH 0xC0000428	The hash for image %hs cannot be found in the system catalogs. The image is likely corrupt or the victim of tampering.
STATUS_NOT_CAPABLE 0xC0000429	The implementation is not capable of performing the request.
STATUS_REQUEST_OUT_OF_SEQUENCE 0xC000042A	The requested operation is out of order with respect to other operations.



Value	Meaning
STATUS_IMPLEMENTATION_LIMIT 0xC000042B	An operation attempted to exceed an implementation-defined limit.
STATUS_ELEVATION_REQUIRED 0xC000042C	The requested operation requires elevation.
STATUS_BEYOND_VDL 0xC0000432	The operation was attempted beyond the valid data length of the file.
STATUS_ENCOUNTED_WRITE_IN_PROGRESS 0xC0000433	The attempted write operation encountered a write already in progress for some portion of the range.
STATUS_PTE_CHANGED 0xC0000434	The page fault mappings changed in the middle of processing a fault so the operation must be retried.
STATUS_PURGE_FAILED 0xC0000435	The attempt to purge this file from memory failed to purge some or all the data from memory.
STATUS_CRED_REQUIRES_CONFIRMATION 0xC0000440	The requested credential requires confirmation.
STATUS_CS_ENCRYPTION_INVALID_SERVER_RESPONSE 0xC0000441	The remote server sent an invalid response for a file being opened with Client Side Encryption.
STATUS_CS_ENCRYPTION_UNSUPPORTED_SERVER 0xC0000442	Client Side Encryption is not supported by the remote server even though it claims to support it.
STATUS_CS_ENCRYPTION_EXISTING_ENCRYPTED_FILE 0xC0000443	File is encrypted and should be opened in Client Side Encryption mode.
STATUS_CS_ENCRYPTION_NEW_ENCRYPTED_FILE 0xC0000444	A new encrypted file is being created and a \$EFS needs to be provided.
STATUS_CS_ENCRYPTION_FILE_NOT_CSE 0xC0000445	The SMB client requested a CSE FSCTL on a non-CSE file.
STATUS_INVALID_LABEL 0xC0000446	Indicates a particular Security ID may not be assigned as the label of an object.
STATUS_DRIVER_PROCESS_TERMINATED 0xC0000450	The process hosting the driver for this device has terminated.
STATUS_AMBIGUOUS_SYSTEM_DEVICE 0xC0000451	The requested system device cannot be identified due to multiple indistinguishable devices potentially matching the identification criteria.
STATUS_SYSTEM_DEVICE_NOT_FOUND 0xC0000452	The requested system device cannot be found.

Value	Meaning
STATUS_RESTART_BOOT_APPLICATION 0xC0000453	This boot application must be restarted.
STATUS_INVALID_TASK_NAME 0xC0000500	The specified task name is invalid.
STATUS_INVALID_TASK_INDEX 0xC0000501	The specified task index is invalid.
STATUS_THREAD_ALREADY_IN_TASK 0xC0000502	The specified thread is already joining a task.
STATUS_CALLBACK_BYPASS 0xC0000503	A callback has requested to bypass native code.
STATUS_PORT_CLOSED 0xC0000700	The ALPC port is closed.
STATUS_MESSAGE_LOST 0xC0000701	The ALPC message requested is no longer available.
STATUS_INVALID_MESSAGE 0xC0000702	The ALPC message supplied is invalid.
STATUS_REQUEST_CANCELED 0xC0000703	The ALPC message has been canceled.
STATUS_RECURSIVE_DISPATCH 0xC0000704	Invalid recursive dispatch attempt.
STATUS_LPC_RECEIVE_BUFFER_EXPECTED 0xC0000705	No receive buffer has been supplied in a synchronous request.
STATUS_LPC_INVALID_CONNECTION_USAGE 0xC0000706	The connection port is used in an invalid context.
STATUS_LPC_REQUESTS_NOT_ALLOWED 0xC0000707	The ALPC port does not accept new request messages.
STATUS_RESOURCE_IN_USE 0xC0000708	The resource requested is already in use.
STATUS_HARDWARE_MEMORY_ERROR 0xC0000709	The hardware has reported an uncorrectable memory error.
STATUS_THREADPOOL_HANDLE_EXCEPTION 0xC000070A	Status 0x%08x was returned, waiting on handle 0x%x for wait 0x%p, in waiter 0x%p.
STATUS_THREADPOOL_SET_EVENT_ON_COMPLETION_FAILED 0xC000070B	After a callback to 0x%p(0x%p), a completion call to Set event(0x%p) failed with status 0x%08x.
STATUS_THREADPOOL_RELEASE_SEMAPHORE_ON_COMPLETION_	After a callback to 0x%p(0x%p), a

Value	Meaning
FAILED 0xC000070C	completion call to ReleaseSemaphore(0x%p, %d) failed with status 0x%08x.
STATUS_THREADPOOL_RELEASE_MUTEX_ON_COMPLETION_FAILED 0xC000070D	After a callback to 0x%p(0x%p), a completion call to ReleaseMutex(%p) failed with status 0x%08x.
STATUS_THREADPOOL_FREE_LIBRARY_ON_COMPLETION_FAILED 0xC000070E	After a callback to 0x%p(0x%p), a completion call to FreeLibrary(%p) failed with status 0x%08x.
STATUS_THREADPOOL_RELEASED_DURING_OPERATION 0xC000070F	The thread pool 0x%p was released while a thread was posting a callback to 0x%p(0x%p) to it.
STATUS_CALLBACK_RETURNED_WHILE_IMPERSONATING 0xC0000710	A thread pool worker thread is impersonating a client, after a callback to 0x%p(0x%p). This is unexpected, indicating that the callback is missing a call to revert the impersonation.
STATUS_APC_RETURNED_WHILE_IMPERSONATING 0xC0000711	A thread pool worker thread is impersonating a client, after executing an APC. This is unexpected, indicating that the APC is missing a call to revert the impersonation.
STATUS_PROCESS_IS_PROTECTED 0xC0000712	Either the target process, or the target thread's containing process, is a protected process.
STATUS_MCA_EXCEPTION 0xC0000713	A thread is getting dispatched with MCA EXCEPTION because of MCA.
STATUS_CERTIFICATE_MAPPING_NOT_UNIQUE 0xC0000714	The client certificate account mapping is not unique.
STATUS_SYMLINK_CLASS_DISABLED 0xC0000715	The symbolic link cannot be followed because its type is disabled.
STATUS_INVALID_IDN_NORMALIZATION 0xC0000716	Indicates that the specified string is not valid for IDN normalization.
STATUS_NO_UNICODE_TRANSLATION 0xC0000717	No mapping for the Unicode character exists in the target multi-byte code page.
STATUS_ALREADY_REGISTERED 0xC0000718	The provided callback is already registered.
STATUS_CONTEXT_MISMATCH 0xC0000719	The provided context did not match the target.
STATUS_PORT_ALREADY_HAS_COMPLETION_LIST	The specified port already has a completion list.

Value	Meaning
0xC000071A	
STATUS_CALLBACK_RETURNED_THREAD_PRIORITY 0xC000071B	A threadpool worker thread entered a callback at thread base priority 0x%x and exited at priority 0x%x. This is unexpected, indicating that the callback missed restoring the priority.
STATUS_INVALID_THREAD 0xC000071C	An invalid thread, handle %p, is specified for this operation. Possibly, a threadpool worker thread was specified.
STATUS_CALLBACK_RETURNED_TRANSACTION 0xC000071D	A threadpool worker thread entered a callback, which left transaction state. This is unexpected, indicating that the callback missed clearing the transaction.
STATUS_CALLBACK_RETURNED_LDR_LOCK 0xC000071E	A threadpool worker thread entered a callback, which left the loader lock held. This is unexpected, indicating that the callback missed releasing the lock.
STATUS_CALLBACK_RETURNED_LANG 0xC000071F	A threadpool worker thread entered a callback, which left with preferred languages set. This is unexpected, indicating that the callback missed clearing them.
STATUS_CALLBACK_RETURNED_PRI_BACK 0xC0000720	A threadpool worker thread entered a callback, which left with background priorities set. This is unexpected, indicating that the callback missed restoring the original priorities.
STATUS_CALLBACK_RETURNED_THREAD_AFFINITY >0xC0000721	A threadpool worker thread entered a callback at thread affinity %p and exited at affinity %p. This is unexpected, indicating that the callback missed restoring the priority.
STATUS_DISK_REPAIR_DISABLED 0xC0000800	The attempted operation required self healing to be enabled.
STATUS_DS_DOMAIN_RENAME_IN_PROGRESS 0xC0000801	The directory service cannot perform the requested operation because a domain rename operation is in progress.
STATUS_DISK_QUOTA_EXCEEDED 0xC0000802	An operation failed because the storage quota was exceeded.
STATUS_CONTENT_BLOCKED 0xC0000804	An operation failed because the content was blocked.
STATUS_BAD_CLUSTERS	The operation could not be completed

Value	Meaning
0xC0000805	due to bad clusters on disk.
STATUS_VOLUME_DIRTY 0xC0000806	The operation could not be completed because the volume is dirty. Please run the Chkdsk utility and try again.
STATUS_FILE_CHECKED_OUT 0xC0000901	This file is checked out or locked for editing by another user.
STATUS_CHECKOUT_REQUIRED 0xC0000902	The file must be checked out before saving changes.
STATUS_BAD_FILE_TYPE 0xC0000903	The file type being saved or retrieved has been blocked.
STATUS_FILE_TOO_LARGE 0xC0000904	The file size exceeds the limit allowed and cannot be saved.
STATUS_FORMS_AUTH_REQUIRED 0xC0000905	Access Denied. Before opening files in this location, you must first browse to the e.g. site and select the option to log on automatically.
STATUS_VIRUS_INFECTED 0xC0000906	The operation did not complete successfully because the file contains a virus.
STATUS_VIRUS_DELETED 0xC0000907	This file contains a virus and cannot be opened. Due to the nature of this virus, the file has been removed from this location.
STATUS_BAD_MCFG_TABLE 0xC0000908	The resources required for this device conflict with the MCFG table.
STATUS_WOW_ASSERTION 0xC0009898	WOW Assertion Error.
STATUS_INVALID_SIGNATURE 0xC000A000	The cryptographic signature is invalid.
STATUS_HMAC_NOT_SUPPORTED 0xC000A001	The cryptographic provider does not support HMAC.
STATUS_IPSEC_QUEUE_OVERFLOW 0xC000A010	The IPsec queue overflowed.
STATUS_ND_QUEUE_OVERFLOW 0xC000A011	The neighbor discovery queue overflowed.
STATUS_HOPLIMIT_EXCEEDED 0xC000A012	An Internet Control Message Protocol (ICMP) hop limit exceeded error was received.
STATUS_PROTOCOL_NOT_SUPPORTED	The protocol is not installed on the local

Value	Meaning
0xC000A013	machine.
STATUS_LOST_WRITEBEHIND_DATA_NETWORK_DISCONNECTED 0xC000A080	{Delayed Write Failed} Windows was unable to save all the data for the file %hs; the data has been lost. This error may be caused by network connectivity issues. Try to save this file elsewhere.
STATUS_LOST_WRITEBEHIND_DATA_NETWORK_SERVER_ERROR 0xC000A081	{Delayed Write Failed} Windows was unable to save all the data for the file %hs; the data has been lost. This error was returned by the server on which the file exists. Try to save this file elsewhere.
STATUS_LOST_WRITEBEHIND_DATA_LOCAL_DISK_ERROR 0xC000A082	{Delayed Write Failed} Windows was unable to save all the data for the file %hs; the data has been lost. This error may be caused if the device has been removed or the media is write-protected.
STATUS_XML_PARSE_ERROR 0xC000A083	Windows was unable to parse the requested XML data.
STATUS_XMLDSIG_ERROR 0xC000A084	An error was encountered while processing an XML digital signature.
STATUS_WRONG_COMPARTMENT 0xC000A085	This indicates that the caller made the connection request in the wrong routing compartment.
STATUS_AUTHIP_FAILURE 0xC000A086	This indicates that there was an AuthIP failure when attempting to connect to the remote host.
DBG_NO_STATE_CHANGE 0xC0010001	The debugger did not perform a state change.
DBG_APP_NOT_IDLE 0xC0010002	The debugger found that the application is not idle.
RPC_NT_INVALID_STRING_BINDING 0xC0020001	The string binding is invalid.
RPC_NT_WRONG_KIND_OF_BINDING 0xC0020002	The binding handle is not the correct type.
RPC_NT_INVALID_BINDING 0xC0020003	The binding handle is invalid.
RPC_NT_PROTSEQ_NOT_SUPPORTED 0xC0020004	The RPC protocol sequence is not supported.
RPC_NT_INVALID_RPC_PROTSEQ	The RPC protocol sequence is invalid.

Value	Meaning
0xC0020005	
RPC_NT_INVALID_STRING_UUID 0xC0020006	The string UUID is invalid.
RPC_NT_INVALID_ENDPOINT_FORMAT 0xC0020007	The endpoint format is invalid.
RPC_NT_INVALID_NET_ADDR 0xC0020008	The network address is invalid.
RPC_NT_NO_ENDPOINT_FOUND 0xC0020009	No endpoint was found.
RPC_NT_INVALID_TIMEOUT 0xC002000A	The time-out value is invalid.
RPC_NT_OBJECT_NOT_FOUND 0xC002000B	The object UUID was not found.
RPC_NT_ALREADY_REGISTERED 0xC002000C	The object UUID has already been registered.
RPC_NT_TYPE_ALREADY_REGISTERED 0xC002000D	The type UUID has already been registered.
RPC_NT_ALREADY_LISTENING 0xC002000E	The RPC server is already listening.
RPC_NT_NO_PROTSEQS_REGISTERED 0xC002000F	No protocol sequences have been registered.
RPC_NT_NOT_LISTENING 0xC0020010	The RPC server is not listening.
RPC_NT_UNKNOWN_MGR_TYPE 0xC0020011	The manager type is unknown.
RPC_NT_UNKNOWN_IF 0xC0020012	The interface is unknown.
RPC_NT_NO_BINDINGS 0xC0020013	There are no bindings.
RPC_NT_NO_PROTSEQS 0xC0020014	There are no protocol sequences.
RPC_NT_CANT_CREATE_ENDPOINT 0xC0020015	The endpoint cannot be created.
RPC_NT_OUT_OF_RESOURCES 0xC0020016	Insufficient resources are available to complete this operation.

Value	Meaning
RPC_NT_SERVER_UNAVAILABLE 0xC0020017	The RPC server is unavailable.
RPC_NT_SERVER_TOO_BUSY 0xC0020018	The RPC server is too busy to complete this operation.
RPC_NT_INVALID_NETWORK_OPTIONS 0xC0020019	The network options are invalid.
RPC_NT_NO_CALL_ACTIVE 0xC002001A	No RPCs are active on this thread.
RPC_NT_CALL_FAILED 0xC002001B	The RPC failed.
RPC_NT_CALL_FAILED_DNE 0xC002001C	The RPC failed and did not execute.
RPC_NT_PROTOCOL_ERROR 0xC002001D	An RPC protocol error occurred.
RPC_NT_UNSUPPORTED_TRANS_SYN 0xC002001F	The RPC server does not support the transfer syntax.
RPC_NT_UNSUPPORTED_TYPE 0xC0020021	The type UUID is not supported.
RPC_NT_INVALID_TAG 0xC0020022	The tag is invalid.
RPC_NT_INVALID_BOUND 0xC0020023	The array bounds are invalid.
RPC_NT_NO_ENTRY_NAME 0xC0020024	The binding does not contain an entry name.
RPC_NT_INVALID_NAME_SYNTAX 0xC0020025	The name syntax is invalid.
RPC_NT_UNSUPPORTED_NAME_SYNTAX 0xC0020026	The name syntax is not supported.
RPC_NT_UUID_NO_ADDRESS 0xC0020028	No network address is available to construct a UUID.
RPC_NT_DUPLICATE_ENDPOINT 0xC0020029	The endpoint is a duplicate.
RPC_NT_UNKNOWN_AUTHN_TYPE 0xC002002A	The authentication type is unknown.
RPC_NT_MAX_CALLS_TOO_SMALL	The maximum number of calls is too small.



Value	Meaning
0xC002002B	
RPC_NT_STRING_TOO_LONG 0xC002002C	The string is too long.
RPC_NT_PROTSEQ_NOT_FOUND 0xC002002D	The RPC protocol sequence was not found.
RPC_NT_PROCNUM_OUT_OF_RANGE 0xC002002E	The procedure number is out of range.
RPC_NT_BINDING_HAS_NO_AUTH 0xC002002F	The binding does not contain any authentication information.
RPC_NT_UNKNOWN_AUTHN_SERVICE 0xC0020030	The authentication service is unknown.
RPC_NT_UNKNOWN_AUTHN_LEVEL 0xC0020031	The authentication level is unknown.
RPC_NT_INVALID_AUTH_IDENTITY 0xC0020032	The security context is invalid.
RPC_NT_UNKNOWN_AUTHZ_SERVICE 0xC0020033	The authorization service is unknown.
EPT_NT_INVALID_ENTRY 0xC0020034	The entry is invalid.
EPT_NT_CANT_PERFORM_OP 0xC0020035	The operation cannot be performed.
EPT_NT_NOT_REGISTERED 0xC0020036	No more endpoints are available from the endpoint mapper.
RPC_NT_NOTHING_TO_EXPORT 0xC0020037	No interfaces have been exported.
RPC_NT_INCOMPLETE_NAME 0xC0020038	The entry name is incomplete.
RPC_NT_INVALID_VERS_OPTION 0xC0020039	The version option is invalid.
RPC_NT_NO_MORE_MEMBERS 0xC002003A	There are no more members.
RPC_NT_NOT_ALL_OBJS_UNEXPORTED 0xC002003B	There is nothing to unexport.
RPC_NT_INTERFACE_NOT_FOUND 0xC002003C	The interface was not found.

Value	Meaning
RPC_NT_ENTRY_ALREADY_EXISTS 0xC002003D	The entry already exists.
RPC_NT_ENTRY_NOT_FOUND 0xC002003E	The entry was not found.
RPC_NT_NAME_SERVICE_UNAVAILABLE 0xC002003F	The name service is unavailable.
RPC_NT_INVALID_NAF_ID 0xC0020040	The network address family is invalid.
RPC_NT_CANNOT_SUPPORT 0xC0020041	The requested operation is not supported.
RPC_NT_NO_CONTEXT_AVAILABLE 0xC0020042	No security context is available to allow impersonation.
RPC_NT_INTERNAL_ERROR 0xC0020043	An internal error occurred in the RPC.
RPC_NT_ZERO_DIVIDE 0xC0020044	The RPC server attempted to divide an integer by zero.
RPC_NT_ADDRESS_ERROR 0xC0020045	An addressing error occurred in the RPC server.
RPC_NT_FP_DIV_ZERO 0xC0020046	A floating point operation at the RPC server caused a divide by zero.
RPC_NT_FP_UNDERFLOW 0xC0020047	A floating point underflow occurred at the RPC server.
RPC_NT_FP_OVERFLOW 0xC0020048	A floating point overflow occurred at the RPC server.
RPC_NT_CALL_IN_PROGRESS 0xC0020049	An RPC is already in progress for this thread.
RPC_NT_NO_MORE_BINDINGS 0xC002004A	There are no more bindings.
RPC_NT_GROUP_MEMBER_NOT_FOUND 0xC002004B	The group member was not found.
EPT_NT_CANT_CREATE 0xC002004C	The endpoint mapper database entry could not be created.
RPC_NT_INVALID_OBJECT 0xC002004D	The object UUID is the nil UUID.
RPC_NT_NO_INTERFACES	No interfaces have been registered.

Value	Meaning
0xC002004F	
RPC_NT_CALL_CANCELLED 0xC0020050	The RPC was canceled.
RPC_NT_BINDING_INCOMPLETE 0xC0020051	The binding handle does not contain all the required information.
RPC_NT_COMM_FAILURE 0xC0020052	A communications failure occurred during an RPC.
RPC_NT_UNSUPPORTED_AUTHN_LEVEL 0xC0020053	The requested authentication level is not supported.
RPC_NT_NO_PRINC_NAME 0xC0020054	No principal name was registered.
RPC_NT_NOT_RPC_ERROR 0xC0020055	The error specified is not a valid Windows RPC error code.
RPC_NT_SEC_PKG_ERROR 0xC0020057	A security package-specific error occurred.
RPC_NT_NOT_CANCELLED 0xC0020058	The thread was not canceled.
RPC_NT_INVALID_ASYNC_HANDLE 0xC0020062	Invalid asynchronous RPC handle.
RPC_NT_INVALID_ASYNC_CALL 0xC0020063	Invalid asynchronous RPC call handle for this operation.
RPC_NT_PROXY_ACCESS_DENIED 0xC0020064	Access to the HTTP proxy is denied.
RPC_NT_NO_MORE_ENTRIES 0xC0030001	The list of RPC servers available for auto-handle binding has been exhausted.
RPC_NT_SS_CHAR_TRANS_OPEN_FAIL 0xC0030002	The file designated by DCERPCCHARTRANS cannot be opened.
RPC_NT_SS_CHAR_TRANS_SHORT_FILE 0xC0030003	The file containing the character translation table has fewer than 512 bytes.
RPC_NT_SS_IN_NULL_CONTEXT 0xC0030004	A null context handle is passed as an [in] parameter.
RPC_NT_SS_CONTEXT_MISMATCH 0xC0030005	The context handle does not match any known context handles.
RPC_NT_SS_CONTEXT_DAMAGED 0xC0030006	The context handle changed during a call.

Value	Meaning
RPC_NT_SS_HANDLES_MISMATCH 0xC0030007	The binding handles passed to an RPC do not match.
RPC_NT_SS_CANNOT_GET_CALL_HANDLE 0xC0030008	The stub is unable to get the call handle.
RPC_NT_NULL_REF_POINTER 0xC0030009	A null reference pointer was passed to the stub.
RPC_NT_ENUM_VALUE_OUT_OF_RANGE 0xC003000A	The enumeration value is out of range.
RPC_NT_BYTE_COUNT_TOO_SMALL 0xC003000B	The byte count is too small.
RPC_NT_BAD_STUB_DATA 0xC003000C	The stub received bad data.
RPC_NT_INVALID_ES_ACTION 0xC0030059	Invalid operation on the encoding/decoding handle.
RPC_NT_WRONG_ES_VERSION 0xC003005A	Incompatible version of the serializing package.
RPC_NT_WRONG_STUB_VERSION 0xC003005B	Incompatible version of the RPC stub.
RPC_NT_INVALID_PIPE_OBJECT 0xC003005C	The RPC pipe object is invalid or corrupt.
RPC_NT_INVALID_PIPE_OPERATION 0xC003005D	An invalid operation was attempted on an RPC pipe object.
RPC_NT_WRONG_PIPE_VERSION 0xC003005E	Unsupported RPC pipe version.
RPC_NT_PIPE_CLOSED 0xC003005F	The RPC pipe object has already been closed.
RPC_NT_PIPE_DISCIPLINE_ERROR 0xC0030060	The RPC call completed before all pipes were processed.
RPC_NT_PIPE_EMPTY 0xC0030061	No more data is available from the RPC pipe.
STATUS_PNP_BAD_MPS_TABLE 0xC0040035	A device is missing in the system BIOS MPS table. This device will not be used. Contact your system vendor for a system BIOS update.
STATUS_PNP_TRANSLATION_FAILED 0xC0040036	A translator failed to translate resources.

Value	Meaning
STATUS_PNP_IRQ_TRANSLATION_FAILED 0xC0040037	An IRQ translator failed to translate resources.
STATUS_PNP_INVALID_ID 0xC0040038	Driver %2 returned an invalid ID for a child device (%3).
STATUS_IO_REISSUE_AS_CACHED 0xC0040039	Reissue the given operation as a cached I/O operation
STATUS_CTX_WINSTATION_NAME_INVALID 0xC00A0001	Session name %1 is invalid.
STATUS_CTX_INVALID_PD 0xC00A0002	The protocol driver %1 is invalid.
STATUS_CTX_PD_NOT_FOUND 0xC00A0003	The protocol driver %1 was not found in the system path.
STATUS_CTX_CLOSE_PENDING 0xC00A0006	A close operation is pending on the terminal connection.
STATUS_CTX_NO_OUTBUF 0xC00A0007	No free output buffers are available.
STATUS_CTX_MODEM_INF_NOT_FOUND 0xC00A0008	The MODEM.INF file was not found.
STATUS_CTX_INVALID_MODEMNAME 0xC00A0009	The modem (%1) was not found in the MODEM.INF file.
STATUS_CTX_RESPONSE_ERROR 0xC00A000A	The modem did not accept the command sent to it. Verify that the configured modem name matches the attached modem.
STATUS_CTX_MODEM_RESPONSE_TIMEOUT 0xC00A000B	The modem did not respond to the command sent to it. Verify that the modem cable is properly attached and the modem is turned on.
STATUS_CTX_MODEM_RESPONSE_NO_CARRIER 0xC00A000C	Carrier detection has failed or the carrier has been dropped due to disconnection.
STATUS_CTX_MODEM_RESPONSE_NO_DIALTONE 0xC00A000D	A dial tone was not detected within the required time. Verify that the phone cable is properly attached and functional.
STATUS_CTX_MODEM_RESPONSE_BUSY 0xC00A000E	A busy signal was detected at a remote site on callback.
STATUS_CTX_MODEM_RESPONSE_VOICE 0xC00A000F	A voice was detected at a remote site on callback.

Value	Meaning
STATUS_CTX_TD_ERROR 0xC00A0010	Transport driver error.
STATUS_CTX_LICENSE_CLIENT_INVALID 0xC00A0012	The client you are using is not licensed to use this system. Your logon request is denied.
STATUS_CTX_LICENSE_NOT_AVAILABLE 0xC00A0013	The system has reached its licensed logon limit. Try again later.
STATUS_CTX_LICENSE_EXPIRED 0xC00A0014	The system license has expired. Your logon request is denied.
STATUS_CTX_WINSTATION_NOT_FOUND 0xC00A0015	The specified session cannot be found.
STATUS_CTX_WINSTATION_NAME_COLLISION 0xC00A0016	The specified session name is already in use.
STATUS_CTX_WINSTATION_BUSY 0xC00A0017	The requested operation cannot be completed because the terminal connection is currently processing a connect, disconnect, reset, or delete operation.
STATUS_CTX_BAD_VIDEO_MODE 0xC00A0018	An attempt has been made to connect to a session whose video mode is not supported by the current client.
STATUS_CTX_GRAPHICS_INVALID 0xC00A0022	The application attempted to enable DOS graphics mode. DOS graphics mode is not supported.
STATUS_CTX_NOT_CONSOLE 0xC00A0024	The requested operation can be performed only on the system console. This is most often the result of a driver or system DLL requiring direct console access.
STATUS_CTX_CLIENT_QUERY_TIMEOUT 0xC00A0026	The client failed to respond to the server connect message.
STATUS_CTX_CONSOLE_DISCONNECT 0xC00A0027	Disconnecting the console session is not supported.
STATUS_CTX_CONSOLE_CONNECT 0xC00A0028	Reconnecting a disconnected session to the console is not supported.
STATUS_CTX_SHADOW_DENIED 0xC00A002A	The request to control another session remotely was denied.
STATUS_CTX_WINSTATION_ACCESS_DENIED 0xC00A002B	A process has requested access to a session, but has not been granted those access rights.

Value	Meaning
STATUS_CTX_INVALID_WD 0xC00A002E	The terminal connection driver %1 is invalid.
STATUS_CTX_WD_NOT_FOUND 0xC00A002F	The terminal connection driver %1 was not found in the system path.
STATUS_CTX_SHADOW_INVALID 0xC00A0030	The requested session cannot be controlled remotely. You cannot control your own session, a session that is trying to control your session, a session that has no user logged on, or other sessions from the console.
STATUS_CTX_SHADOW_DISABLED 0xC00A0031	The requested session is not configured to allow remote control.
STATUS_RDP_PROTOCOL_ERROR 0xC00A0032	The RDP protocol component %2 detected an error in the protocol stream and has disconnected the client.
STATUS_CTX_CLIENT_LICENSE_NOT_SET 0xC00A0033	Your request to connect to this terminal server has been rejected. Your terminal server client license number has not been entered for this copy of the terminal client. Contact your system administrator for help in entering a valid, unique license number for this terminal server client. Click OK to continue.
STATUS_CTX_CLIENT_LICENSE_IN_USE 0xC00A0034	Your request to connect to this terminal server has been rejected. Your terminal server client license number is currently being used by another user. Contact your system administrator to obtain a new copy of the terminal server client with a valid, unique license number. Click OK to continue.
STATUS_CTX_SHADOW_ENDED_BY_MODE_CHANGE 0xC00A0035	The remote control of the console was terminated because the display mode was changed. Changing the display mode in a remote control session is not supported.
STATUS_CTX_SHADOW_NOT_RUNNING 0xC00A0036	Remote control could not be terminated because the specified session is not currently being remotely controlled.
STATUS_CTX_LOGON_DISABLED 0xC00A0037	Your interactive logon privilege has been disabled. Contact your system administrator.
STATUS_CTX_SECURITY_LAYER_ERROR 0xC00A0038	The terminal server security layer detected an error in the protocol stream and has disconnected the client.

Value	Meaning
STATUS_TS_INCOMPATIBLE_SESSIONS 0xC00A0039	The target session is incompatible with the current session.
STATUS_MUI_FILE_NOT_FOUND 0xC00B0001	The resource loader failed to find an MUI file.
STATUS_MUI_INVALID_FILE 0xC00B0002	The resource loader failed to load an MUI file because the file failed to pass validation.
STATUS_MUI_INVALID_RC_CONFIG 0xC00B0003	The RC manifest is corrupted with garbage data, is an unsupported version, or is missing a required item.
STATUS_MUI_INVALID_LOCALE_NAME 0xC00B0004	The RC manifest has an invalid culture name.
STATUS_MUI_INVALID_ULTIMATEFALLBACK_NAME 0xC00B0005	The RC manifest has an invalid ultimate fallback name.
STATUS_MUI_FILE_NOT_LOADED 0xC00B0006	The resource loader cache does not have a loaded MUI entry.
STATUS_RESOURCE_ENUM_USER_STOP 0xC00B0007	The user stopped resource enumeration.
STATUS_CLUSTER_INVALID_NODE 0xC0130001	The cluster node is not valid.
STATUS_CLUSTER_NODE_EXISTS 0xC0130002	The cluster node already exists.
STATUS_CLUSTER_JOIN_IN_PROGRESS 0xC0130003	A node is in the process of joining the cluster.
STATUS_CLUSTER_NODE_NOT_FOUND 0xC0130004	The cluster node was not found.
STATUS_CLUSTER_LOCAL_NODE_NOT_FOUND 0xC0130005	The cluster local node information was not found.
STATUS_CLUSTER_NETWORK_EXISTS 0xC0130006	The cluster network already exists.
STATUS_CLUSTER_NETWORK_NOT_FOUND 0xC0130007	The cluster network was not found.
STATUS_CLUSTER_NETINTERFACE_EXISTS 0xC0130008	The cluster network interface already exists.
STATUS_CLUSTER_NETINTERFACE_NOT_FOUND 0xC0130009	The cluster network interface was not found.



Value	Meaning
STATUS_CLUSTER_INVALID_REQUEST 0xC013000A	The cluster request is not valid for this object.
STATUS_CLUSTER_INVALID_NETWORK_PROVIDER 0xC013000B	The cluster network provider is not valid.
STATUS_CLUSTER_NODE_DOWN 0xC013000C	The cluster node is down.
STATUS_CLUSTER_NODE_UNREACHABLE 0xC013000D	The cluster node is not reachable.
STATUS_CLUSTER_NODE_NOT_MEMBER 0xC013000E	The cluster node is not a member of the cluster.
STATUS_CLUSTER_JOIN_NOT_IN_PROGRESS 0xC013000F	A cluster join operation is not in progress.
STATUS_CLUSTER_INVALID_NETWORK 0xC0130010	The cluster network is not valid.
STATUS_CLUSTER_NO_NET_ADAPTERS 0xC0130011	No network adapters are available.
STATUS_CLUSTER_NODE_UP 0xC0130012	The cluster node is up.
STATUS_CLUSTER_NODE_PAUSED 0xC0130013	The cluster node is paused.
STATUS_CLUSTER_NODE_NOT_PAUSED 0xC0130014	The cluster node is not paused.
STATUS_CLUSTER_NO_SECURITY_CONTEXT 0xC0130015	No cluster security context is available.
STATUS_CLUSTER_NETWORK_NOT_INTERNAL 0xC0130016	The cluster network is not configured for internal cluster communication.
STATUS_CLUSTER_POISONED 0xC0130017	The cluster node has been poisoned.
STATUS_ACPI_INVALID_OPCODE 0xC0140001	An attempt was made to run an invalid AML opcode.
STATUS_ACPI_STACK_OVERFLOW 0xC0140002	The AML interpreter stack has overflowed.
STATUS_ACPI_ASSERT_FAILED 0xC0140003	An inconsistent state has occurred.
STATUS_ACPI_INVALID_INDEX	An attempt was made to access an array outside its bounds.

Value	Meaning
0xC0140004	
STATUS_ACPI_INVALID_ARGUMENT 0xC0140005	A required argument was not specified.
STATUS_ACPI_FATAL 0xC0140006	A fatal error has occurred.
STATUS_ACPI_INVALID_SUPERNAME 0xC0140007	An invalid SuperName was specified.
STATUS_ACPI_INVALID_ARGTYPE 0xC0140008	An argument with an incorrect type was specified.
STATUS_ACPI_INVALID_OBJTYPE 0xC0140009	An object with an incorrect type was specified.
STATUS_ACPI_INVALID_TARGETTYPE 0xC014000A	A target with an incorrect type was specified.
STATUS_ACPI_INCORRECT_ARGUMENT_COUNT 0xC014000B	An incorrect number of arguments was specified.
STATUS_ACPI_ADDRESS_NOT_MAPPED 0xC014000C	An address failed to translate.
STATUS_ACPI_INVALID_EVENTTYPE 0xC014000D	An incorrect event type was specified.
STATUS_ACPI_HANDLER_COLLISION 0xC014000E	A handler for the target already exists.
STATUS_ACPI_INVALID_DATA 0xC014000F	Invalid data for the target was specified.
STATUS_ACPI_INVALID_REGION 0xC0140010	An invalid region for the target was specified.
STATUS_ACPI_INVALID_ACCESS_SIZE 0xC0140011	An attempt was made to access a field outside the defined range.
STATUS_ACPI_ACQUIRE_GLOBAL_LOCK 0xC0140012	The global system lock could not be acquired.
STATUS_ACPI_ALREADY_INITIALIZED 0xC0140013	An attempt was made to reinitialize the ACPI subsystem.
STATUS_ACPI_NOT_INITIALIZED 0xC0140014	The ACPI subsystem has not been initialized.
STATUS_ACPI_INVALID_MUTEX_LEVEL 0xC0140015	An incorrect mutex was specified.

Value	Meaning
STATUS_ACPI_MUTEX_NOT_OWNED 0xC0140016	The mutex is not currently owned.
STATUS_ACPI_MUTEX_NOT_OWNER 0xC0140017	An attempt was made to access the mutex by a process that was not the owner.
STATUS_ACPI_RS_ACCESS 0xC0140018	An error occurred during an access to region space.
STATUS_ACPI_INVALID_TABLE 0xC0140019	An attempt was made to use an incorrect table.
STATUS_ACPI_REG_HANDLER_FAILED 0xC0140020	The registration of an ACPI event failed.
STATUS_ACPI_POWER_REQUEST_FAILED 0xC0140021	An ACPI power object failed to transition state.
STATUS_SXS_SECTION_NOT_FOUND 0xC0150001	The requested section is not present in the activation context.
STATUS_SXS_CANT_GEN_ACTCTX 0xC0150002	Windows was unable to process the application binding information. Refer to the system event log for further information.
STATUS_SXS_INVALID_ACTCTXDATA_FORMAT 0xC0150003	The application binding data format is invalid.
STATUS_SXS_ASSEMBLY_NOT_FOUND 0xC0150004	The referenced assembly is not installed on the system.
STATUS_SXS_MANIFEST_FORMAT_ERROR 0xC0150005	The manifest file does not begin with the required tag and format information.
STATUS_SXS_MANIFEST_PARSE_ERROR 0xC0150006	The manifest file contains one or more syntax errors.
STATUS_SXS_ACTIVATION_CONTEXT_DISABLED 0xC0150007	The application attempted to activate a disabled activation context.
STATUS_SXS_KEY_NOT_FOUND 0xC0150008	The requested lookup key was not found in any active activation context.
STATUS_SXS_VERSION_CONFLICT 0xC0150009	A component version required by the application conflicts with another component version that is already active.
STATUS_SXS_WRONG_SECTION_TYPE 0xC015000A	The type requested activation context section does not match the query API used.

Value	Meaning
STATUS_SXS_THREAD_QUERIES_DISABLED 0xC015000B	Lack of system resources has required isolated activation to be disabled for the current thread of execution.
STATUS_SXS_ASSEMBLY_MISSING 0xC015000C	The referenced assembly could not be found.
STATUS_SXS_PROCESS_DEFAULT_ALREADY_SET 0xC015000E	An attempt to set the process default activation context failed because the process default activation context was already set.
STATUS_SXS_EARLY_DEACTIVATION 0xC015000F	The activation context being deactivated is not the most recently activated one.
STATUS_SXS_INVALID_DEACTIVATION 0xC0150010	The activation context being deactivated is not active for the current thread of execution.
STATUS_SXS_MULTIPLE_DEACTIVATION 0xC0150011	The activation context being deactivated has already been deactivated.
STATUS_SXS_SYSTEM_DEFAULT_ACTIVATION_CONTEXT_EMPTY 0xC0150012	The activation context of the system default assembly could not be generated.
STATUS_SXS_PROCESS_TERMINATION_REQUESTED 0xC0150013	A component used by the isolation facility has requested that the process be terminated.
STATUS_SXS_CORRUPT_ACTIVATION_STACK 0xC0150014	The activation context activation stack for the running thread of execution is corrupt.
STATUS_SXS_CORRUPTION 0xC0150015	The application isolation metadata for this process or thread has become corrupt.
STATUS_SXS_INVALID_IDENTITY_ATTRIBUTE_VALUE 0xC0150016	The value of an attribute in an identity is not within the legal range.
STATUS_SXS_INVALID_IDENTITY_ATTRIBUTE_NAME 0xC0150017	The name of an attribute in an identity is not within the legal range.
STATUS_SXS_IDENTITY_DUPLICATE_ATTRIBUTE 0xC0150018	An identity contains two definitions for the same attribute.
STATUS_SXS_IDENTITY_PARSE_ERROR 0xC0150019	The identity string is malformed. This may be due to a trailing comma, more than two unnamed attributes, a missing attribute name, or a missing attribute value.
STATUS_SXS_COMPONENT_STORE_CORRUPT 0xC015001A	The component store has become corrupted.

Value	Meaning
STATUS_SXS_FILE_HASH_MISMATCH 0xC015001B	A component's file does not match the verification information present in the component manifest.
STATUS_SXS_MANIFEST_IDENTITY_SAME_BUT_CONTENTS_DIFFERENT 0xC015001C	The identities of the manifests are identical, but their contents are different.
STATUS_SXS_IDENTITIES_DIFFERENT 0xC015001D	The component identities are different.
STATUS_SXS_ASSEMBLY_IS_NOT_A_DEPLOYMENT 0xC015001E	The assembly is not a deployment.
STATUS_SXS_FILE_NOT_PART_OF_ASSEMBLY 0xC015001F	The file is not a part of the assembly.
STATUS_ADVANCED_INSTALLER_FAILED 0xC0150020	An advanced installer failed during setup or servicing.
STATUS_XML_ENCODING_MISMATCH 0xC0150021	The character encoding in the XML declaration did not match the encoding used in the document.
STATUS_SXS_MANIFEST_TOO_BIG 0xC0150022	The size of the manifest exceeds the maximum allowed.
STATUS_SXS_SETTING_NOT_REGISTERED 0xC0150023	The setting is not registered.
STATUS_SXS_TRANSACTION_CLOSURE_INCOMPLETE 0xC0150024	One or more required transaction members are not present.
STATUS_SMI_PRIMITIVE_INSTALLER_FAILED 0xC0150025	The SMI primitive installer failed during setup or servicing.
STATUS_GENERIC_COMMAND_FAILED 0xC0150026	A generic command executable returned a result that indicates failure.
STATUS_SXS_FILE_HASH_MISSING 0xC0150027	A component is missing file verification information in its manifest.
STATUS_TRANSACTIONAL_CONFLICT 0xC0190001	The function attempted to use a name that is reserved for use by another transaction.
STATUS_INVALID_TRANSACTION 0xC0190002	The transaction handle associated with this operation is invalid.
STATUS_TRANSACTION_NOT_ACTIVE 0xC0190003	The requested operation was made in the context of a transaction that is no longer active.
STATUS_TM_INITIALIZATION_FAILED	The transaction manager was unable to

Value	Meaning
0xC0190004	be successfully initialized. Transacted operations are not supported.
STATUS_RM_NOT_ACTIVE 0xC0190005	Transaction support within the specified file system resource manager was not started or was shut down due to an error.
STATUS_RM_METADATA_CORRUPT 0xC0190006	The metadata of the resource manager has been corrupted. The resource manager will not function.
STATUS_TRANSACTION_NOT_JOINED 0xC0190007	The resource manager attempted to prepare a transaction that it has not successfully joined.
STATUS_DIRECTORY_NOT_RM 0xC0190008	The specified directory does not contain a file system resource manager.
STATUS_TRANSACTIONS_UNSUPPORTED_REMOTE 0xC019000A	The remote server or share does not support transacted file operations.
STATUS_LOG_RESIZE_INVALID_SIZE 0xC019000B	The requested log size for the file system resource manager is invalid.
STATUS_REMOTE_FILE_VERSION_MISMATCH 0xC019000C	The remote server sent mismatching version number or Fid for a file opened with transactions.
STATUS_CRM_PROTOCOL_ALREADY_EXISTS 0xC019000F	The resource manager tried to register a protocol that already exists.
STATUS_TRANSACTION_PROPAGATION_FAILED 0xC0190010	The attempt to propagate the transaction failed.
STATUS_CRM_PROTOCOL_NOT_FOUND 0xC0190011	The requested propagation protocol was not registered as a CRM.
STATUS_TRANSACTION_SUPERIOR_EXISTS 0xC0190012	The transaction object already has a superior enlistment, and the caller attempted an operation that would have created a new superior. Only a single superior enlistment is allowed.
STATUS_TRANSACTION_REQUEST_NOT_VALID 0xC0190013	The requested operation is not valid on the transaction object in its current state.
STATUS_TRANSACTION_NOT_REQUESTED 0xC0190014	The caller has called a response API, but the response is not expected because the transaction manager did not issue the corresponding request to the caller.
STATUS_TRANSACTION_ALREADY_ABORTED 0xC0190015	It is too late to perform the requested operation, because the transaction has

Value	Meaning
	already been aborted.
STATUS_TRANSACTION_ALREADY_COMMITTED 0xC0190016	It is too late to perform the requested operation, because the transaction has already been committed.
STATUS_TRANSACTION_INVALID_MARSHALL_BUFFER 0xC0190017	The buffer passed in to NtPushTransaction or NtPullTransaction is not in a valid format.
STATUS_CURRENT_TRANSACTION_NOT_VALID 0xC0190018	The current transaction context associated with the thread is not a valid handle to a transaction object.
STATUS_LOG_GROWTH_FAILED 0xC0190019	An attempt to create space in the transactional resource manager's log failed. The failure status has been recorded in the event log.
STATUS_OBJECT_NO_LONGER_EXISTS 0xC0190021	The object (file, stream, or link) that corresponds to the handle has been deleted by a transaction savepoint rollback.
STATUS_STREAM_MINIVERSION_NOT_FOUND 0xC0190022	The specified file miniversion was not found for this transacted file open.
STATUS_STREAM_MINIVERSION_NOT_VALID 0xC0190023	The specified file miniversion was found but has been invalidated. The most likely cause is a transaction savepoint rollback.
STATUS_MINIVERSION_INACCESSIBLE_FROM_SPECIFIED_TRANSACTION 0xC0190024	A miniversion may be opened only in the context of the transaction that created it.
STATUS_CANT_OPEN_MINIVERSION_WITH_MODIFY_INTENT 0xC0190025	It is not possible to open a miniversion with modify access.
STATUS_CANT_CREATE_MORE_STREAM_MINIVERSIONS 0xC0190026	It is not possible to create any more miniversions for this stream.
STATUS_HANDLE_NO_LONGER_VALID 0xC0190028	The handle has been invalidated by a transaction. The most likely cause is the presence of memory mapping on a file or an open handle when the transaction ended or rolled back to savepoint.
STATUS_LOG_CORRUPTION_DETECTED 0xC0190030	The log data is corrupt.
STATUS_RM_DISCONNECTED 0xC0190032	The transaction outcome is unavailable because the resource manager responsible for it is disconnected.
STATUS_ENLISTMENT_NOT_SUPERIOR	The request was rejected because the enlistment in question is not a superior

Value	Meaning
0xC0190033	enlistment.
STATUS_FILE_IDENTITY_NOT_PERSISTENT 0xC0190036	The file cannot be opened in a transaction because its identity depends on the outcome of an unresolved transaction.
STATUS_CANT_BREAK_TRANSACTIONAL_DEPENDENCY 0xC0190037	The operation cannot be performed because another transaction is depending on this property not changing.
STATUS_CANT_CROSS_RM_BOUNDARY 0xC0190038	The operation would involve a single file with two transactional resource managers and is, therefore, not allowed.
STATUS_TXF_DIR_NOT_EMPTY 0xC0190039	The \$Txf directory must be empty for this operation to succeed.
STATUS_INDOUBT_TRANSACTIONS_EXIST 0xC019003A	The operation would leave a transactional resource manager in an inconsistent state and is therefore not allowed.
STATUS_TM_VOLATILE 0xC019003B	The operation could not be completed because the transaction manager does not have a log.
STATUS_ROLLBACK_TIMER_EXPIRED 0xC019003C	A rollback could not be scheduled because a previously scheduled rollback has already executed or been queued for execution.
STATUS_TXF_ATTRIBUTE_CORRUPT 0xC019003D	The transactional metadata attribute on the file or directory %hs is corrupt and unreadable.
STATUS_EFS_NOT_ALLOWED_IN_TRANSACTION 0xC019003E	The encryption operation could not be completed because a transaction is active.
STATUS_TRANSACTIONAL_OPEN_NOT_ALLOWED 0xC019003F	This object is not allowed to be opened in a transaction.
STATUS_TRANSACTED_MAPPING_UNSUPPORTED_REMOTE 0xC0190040	Memory mapping (creating a mapped section) a remote file under a transaction is not supported.
STATUS_TRANSACTION_REQUIRED_PROMOTION 0xC0190043	Promotion was required to allow the resource manager to enlist, but the transaction was set to disallow it.
STATUS_CANNOT_EXECUTE_FILE_IN_TRANSACTION 0xC0190044	This file is open for modification in an unresolved transaction and may be opened for execute only by a transacted reader.



Value	Meaning
STATUS_TRANSACTIONS_NOT_FROZEN 0xC0190045	The request to thaw frozen transactions was ignored because transactions were not previously frozen.
STATUS_TRANSACTION_FREEZE_IN_PROGRESS 0xC0190046	Transactions cannot be frozen because a freeze is already in progress.
STATUS_NOT_SNAPSHOT_VOLUME 0xC0190047	The target volume is not a snapshot volume. This operation is valid only on a volume mounted as a snapshot.
STATUS_NO_SAVEPOINT_WITH_OPEN_FILES 0xC0190048	The savepoint operation failed because files are open on the transaction, which is not permitted.
STATUS_SPARSE_NOT_ALLOWED_IN_TRANSACTION 0xC0190049	The sparse operation could not be completed because a transaction is active on the file.
STATUS_TM_IDENTITY_MISMATCH 0xC019004A	The call to create a transaction manager object failed because the Tm Identity that is stored in the log file does not match the Tm Identity that was passed in as an argument.
STATUS_FLOATED_SECTION 0xC019004B	I/O was attempted on a section object that has been floated as a result of a transaction ending. There is no valid data.
STATUS_CANNOT_ACCEPT_TRANSACTED_WORK 0xC019004C	The transactional resource manager cannot currently accept transacted work due to a transient condition, such as low resources.
STATUS_CANNOT_ABORT_TRANSACTIONS 0xC019004D	The transactional resource manager had too many transactions outstanding that could not be aborted. The transactional resource manager has been shut down.
STATUS_TRANSACTION_NOT_FOUND 0xC019004E	The specified transaction was unable to be opened because it was not found.
STATUS_RESOURCEMANAGER_NOT_FOUND 0xC019004F	The specified resource manager was unable to be opened because it was not found.
STATUS_ENLISTMENT_NOT_FOUND 0xC0190050	The specified enlistment was unable to be opened because it was not found.
STATUS_TRANSACTIONMANAGER_NOT_FOUND 0xC0190051	The specified transaction manager was unable to be opened because it was not found.
STATUS_TRANSACTIONMANAGER_NOT_ONLINE 0xC0190052	The specified resource manager was unable to create an enlistment because its associated transaction manager is

Value	Meaning
	not online.
STATUS_TRANSACTIONMANAGER_RECOVERY_NAME_COLLISION 0xC0190053	The specified transaction manager was unable to create the objects contained in its log file in the Ob namespace. Therefore, the transaction manager was unable to recover.
STATUS_TRANSACTION_NOT_ROOT 0xC0190054	The call to create a superior enlistment on this transaction object could not be completed because the transaction object specified for the enlistment is a subordinate branch of the transaction. Only the root of the transaction can be enlisted as a superior.
STATUS_TRANSACTION_OBJECT_EXPIRED 0xC0190055	Because the associated transaction manager or resource manager has been closed, the handle is no longer valid.
STATUS_COMPRESSION_NOT_ALLOWED_IN_TRANSACTION 0xC0190056	The compression operation could not be completed because a transaction is active on the file.
STATUS_TRANSACTION_RESPONSE_NOT_ENLISTED 0xC0190057	The specified operation could not be performed on this superior enlistment because the enlistment was not created with the corresponding completion response in the NotificationMask.
STATUS_TRANSACTION_RECORD_TOO_LONG 0xC0190058	The specified operation could not be performed because the record to be logged was too long. This can occur because either there are too many enlistments on this transaction or the combined RecoveryInformation being logged on behalf of those enlistments is too long.
STATUS_NO_LINK_TRACKING_IN_TRANSACTION 0xC0190059	The link-tracking operation could not be completed because a transaction is active.
STATUS_OPERATION_NOT_SUPPORTED_IN_TRANSACTION 0xC019005A	This operation cannot be performed in a transaction.
STATUS_TRANSACTION_INTEGRITY_VIOLATED 0xC019005B	The kernel transaction manager had to abort or forget the transaction because it blocked forward progress.
STATUS_LOG_SECTOR_INVALID 0xC01A0001	The log service found an invalid log sector.
STATUS_LOG_SECTOR_PARITY_INVALID 0xC01A0002	The log service encountered a log sector with invalid block parity.
STATUS_LOG_SECTOR_REMAPPED	The log service encountered a

Value	Meaning
0xC01A0003	remapped log sector.
STATUS_LOG_BLOCK_INCOMPLETE 0xC01A0004	The log service encountered a partial or incomplete log block.
STATUS_LOG_INVALID_RANGE 0xC01A0005	The log service encountered an attempt to access data outside the active log range.
STATUS_LOG_BLOCKS_EXHAUSTED 0xC01A0006	The log service user-log marshaling buffers are exhausted.
STATUS_LOG_READ_CONTEXT_INVALID 0xC01A0007	The log service encountered an attempt to read from a marshaling area with an invalid read context.
STATUS_LOG_RESTART_INVALID 0xC01A0008	The log service encountered an invalid log restart area.
STATUS_LOG_BLOCK_VERSION 0xC01A0009	The log service encountered an invalid log block version.
STATUS_LOG_BLOCK_INVALID 0xC01A000A	The log service encountered an invalid log block.
STATUS_LOG_READ_MODE_INVALID 0xC01A000B	The log service encountered an attempt to read the log with an invalid read mode.
STATUS_LOG_METADATA_CORRUPT 0xC01A000D	The log service encountered a corrupted metadata file.
STATUS_LOG_METADATA_INVALID 0xC01A000E	The log service encountered a metadata file that could not be created by the log file system.
STATUS_LOG_METADATA_INCONSISTENT 0xC01A000F	The log service encountered a metadata file with inconsistent data.
STATUS_LOG_RESERVATION_INVALID 0xC01A0010	The log service encountered an attempt to erroneously allocate or dispose reservation space.
STATUS_LOG_CANT_DELETE 0xC01A0011	The log service cannot delete the log file or the file system container.
STATUS_LOG_CONTAINER_LIMIT_EXCEEDED 0xC01A0012	The log service has reached the maximum allowable containers allocated to a log file.
STATUS_LOG_START_OF_LOG 0xC01A0013	The log service has attempted to read or write backward past the start of the log.
STATUS_LOG_POLICY_ALREADY_INSTALLED	The log policy could not be installed because a policy of the same type is

Value	Meaning
0xC01A0014	already present.
STATUS_LOG_POLICY_NOT_INSTALLED 0xC01A0015	The log policy in question was not installed at the time of the request.
STATUS_LOG_POLICY_INVALID 0xC01A0016	The installed set of policies on the log is invalid.
STATUS_LOG_POLICY_CONFLICT 0xC01A0017	A policy on the log in question prevented the operation from completing.
STATUS_LOG_PINNED_ARCHIVE_TAIL 0xC01A0018	The log space cannot be reclaimed because the log is pinned by the archive tail.
STATUS_LOG_RECORD_NONEXISTENT 0xC01A0019	The log record is not a record in the log file.
STATUS_LOG_RECORDS_RESERVED_INVALID 0xC01A001A	The number of reserved log records or the adjustment of the number of reserved log records is invalid.
STATUS_LOG_SPACE_RESERVED_INVALID 0xC01A001B	The reserved log space or the adjustment of the log space is invalid.
STATUS_LOG_TAIL_INVALID 0xC01A001C	A new or existing archive tail or the base of the active log is invalid.
STATUS_LOG_FULL 0xC01A001D	The log space is exhausted.
STATUS_LOG_MULTIPLEXED 0xC01A001E	The log is multiplexed; no direct writes to the physical log are allowed.
STATUS_LOG_DEDICATED 0xC01A001F	The operation failed because the log is dedicated.
STATUS_LOG_ARCHIVE_NOT_IN_PROGRESS 0xC01A0020	The operation requires an archive context.
STATUS_LOG_ARCHIVE_IN_PROGRESS 0xC01A0021	Log archival is in progress.
STATUS_LOG_EPHEMERAL 0xC01A0022	The operation requires a nonephemeral log, but the log is ephemeral.
STATUS_LOG_NOT_ENOUGH_CONTAINERS 0xC01A0023	The log must have at least two containers before it can be read from or written to.
STATUS_LOG_CLIENT_ALREADY_REGISTERED 0xC01A0024	A log client has already registered on the stream.

Value	Meaning
STATUS_LOG_CLIENT_NOT_REGISTERED 0xC01A0025	A log client has not been registered on the stream.
STATUS_LOG_FULL_HANDLER_IN_PROGRESS 0xC01A0026	A request has already been made to handle the log full condition.
STATUS_LOG_CONTAINER_READ_FAILED 0xC01A0027	The log service encountered an error when attempting to read from a log container.
STATUS_LOG_CONTAINER_WRITE_FAILED 0xC01A0028	The log service encountered an error when attempting to write to a log container.
STATUS_LOG_CONTAINER_OPEN_FAILED 0xC01A0029	The log service encountered an error when attempting to open a log container.
STATUS_LOG_CONTAINER_STATE_INVALID 0xC01A002A	The log service encountered an invalid container state when attempting a requested action.
STATUS_LOG_STATE_INVALID 0xC01A002B	The log service is not in the correct state to perform a requested action.
STATUS_LOG_PINNED 0xC01A002C	The log space cannot be reclaimed because the log is pinned.
STATUS_LOG_METADATA_FLUSH_FAILED 0xC01A002D	The log metadata flush failed.
STATUS_LOG_INCONSISTENT_SECURITY 0xC01A002E	Security on the log and its containers is inconsistent.
STATUS_LOG_APPENDED_FLUSH_FAILED 0xC01A002F	Records were appended to the log or reservation changes were made, but the log could not be flushed.
STATUS_LOG_PINNED_RESERVATION 0xC01A0030	The log is pinned due to reservation consuming most of the log space. Free some reserved records to make space available.
STATUS_VIDEO_HUNG_DISPLAY_DRIVER_THREAD 0xC01B00EA	{Display Driver Stopped Responding} The %hs display driver has stopped working normally. Save your work and reboot the system to restore full display functionality. The next time you reboot the computer, a dialog box will allow you to upload data about this failure to Microsoft.
STATUS_FLT_NO_HANDLER_DEFINED 0xC01C0001	A handler was not defined by the filter for this operation.

Value	Meaning
STATUS_FLT_CONTEXT_ALREADY_DEFINED 0xC01C0002	A context is already defined for this object.
STATUS_FLT_INVALID_ASYNCHRONOUS_REQUEST 0xC01C0003	Asynchronous requests are not valid for this operation.
STATUS_FLT_DISALLOW_FAST_IO 0xC01C0004	This is an internal error code used by the filter manager to determine if a fast I/O operation should be forced down the input/output request packet (IRP) path. Minifilters should never return this value.
STATUS_FLT_INVALID_NAME_REQUEST 0xC01C0005	An invalid name request was made. The name requested cannot be retrieved at this time.
STATUS_FLT_NOT_SAFE_TO_POST_OPERATION 0xC01C0006	Posting this operation to a worker thread for further processing is not safe at this time because it could lead to a system deadlock.
STATUS_FLT_NOT_INITIALIZED 0xC01C0007	The Filter Manager was not initialized when a filter tried to register. Make sure that the Filter Manager is loaded as a driver.
STATUS_FLT_FILTER_NOT_READY 0xC01C0008	The filter is not ready for attachment to volumes because it has not finished initializing (FltStartFiltering has not been called).
STATUS_FLT_POST_OPERATION_CLEANUP 0xC01C0009	The filter must clean up any operation-specific context at this time because it is being removed from the system before the operation is completed by the lower drivers.
STATUS_FLT_INTERNAL_ERROR 0xC01C000A	The Filter Manager had an internal error from which it cannot recover; therefore, the operation has failed. This is usually the result of a filter returning an invalid value from a pre-operation callback.
STATUS_FLT_DELETING_OBJECT 0xC01C000B	The object specified for this action is in the process of being deleted; therefore, the action requested cannot be completed at this time.
STATUS_FLT_MUST_BE_NONPAGED_POOL 0xC01C000C	A nonpaged pool must be used for this type of context.
STATUS_FLT_DUPLICATE_ENTRY 0xC01C000D	A duplicate handler definition has been provided for an operation.
STATUS_FLT_CBDQ_DISABLED	The callback data queue has been

Value	Meaning
0xC01C000E	disabled.
STATUS_FLT_DO_NOT_ATTACH 0xC01C000F	Do not attach the filter to the volume at this time.
STATUS_FLT_DO_NOT_DETACH 0xC01C0010	Do not detach the filter from the volume at this time.
STATUS_FLT_INSTANCE_ALTITUDE_COLLISION 0xC01C0011	An instance already exists at this altitude on the volume specified.
STATUS_FLT_INSTANCE_NAME_COLLISION 0xC01C0012	An instance already exists with this name on the volume specified.
STATUS_FLT_FILTER_NOT_FOUND 0xC01C0013	The system could not find the filter specified.
STATUS_FLT_VOLUME_NOT_FOUND 0xC01C0014	The system could not find the volume specified.
STATUS_FLT_INSTANCE_NOT_FOUND 0xC01C0015	The system could not find the instance specified.
STATUS_FLT_CONTEXT_ALLOCATION_NOT_FOUND 0xC01C0016	No registered context allocation definition was found for the given request.
STATUS_FLT_INVALID_CONTEXT_REGISTRATION 0xC01C0017	An invalid parameter was specified during context registration.
STATUS_FLT_NAME_CACHE_MISS 0xC01C0018	The name requested was not found in the Filter Manager name cache and could not be retrieved from the file system.
STATUS_FLT_NO_DEVICE_OBJECT 0xC01C0019	The requested device object does not exist for the given volume.
STATUS_FLT_VOLUME_ALREADY_MOUNTED 0xC01C001A	The specified volume is already mounted.
STATUS_FLT_ALREADY_ENLISTED 0xC01C001B	The specified transaction context is already enlisted in a transaction.
STATUS_FLT_CONTEXT_ALREADY_LINKED 0xC01C001C	The specified context is already attached to another object.
STATUS_FLT_NO_WAITER_FOR_REPLY 0xC01C0020	No waiter is present for the filter's reply to this message.
STATUS_MONITOR_NO_DESCRIPTOR 0xC01D0001	A monitor descriptor could not be obtained.
STATUS_MONITOR_UNKNOWN_DESCRIPTOR_FORMAT	This release does not support the

Value	Meaning
0xC01D0002	format of the obtained monitor descriptor.
STATUS_MONITOR_INVALID_DESCRIPTOR_CHECKSUM 0xC01D0003	The checksum of the obtained monitor descriptor is invalid.
STATUS_MONITOR_INVALID_STANDARD_TIMING_BLOCK 0xC01D0004	The monitor descriptor contains an invalid standard timing block.
STATUS_MONITOR_WMI_DATABLOCK_REGISTRATION_FAILED 0xC01D0005	WMI data-block registration failed for one of the MSMonitorClass WMI subclasses.
STATUS_MONITOR_INVALID_SERIAL_NUMBER_MONDSC_BLOCK 0xC01D0006	The provided monitor descriptor block is either corrupted or does not contain the monitor's detailed serial number.
STATUS_MONITOR_INVALID_USER_FRIENDLY_MONDSC_BLOCK 0xC01D0007	The provided monitor descriptor block is either corrupted or does not contain the monitor's user-friendly name.
STATUS_MONITOR_NO_MORE_DESCRIPTOR_DATA 0xC01D0008	There is no monitor descriptor data at the specified (offset or size) region.
STATUS_MONITOR_INVALID_DETAILED_TIMING_BLOCK 0xC01D0009	The monitor descriptor contains an invalid detailed timing block.
STATUS_GRAPHICS_NOT_EXCLUSIVE_MODE_OWNER 0xC01E0000	Exclusive mode ownership is needed to create an unmanaged primary allocation.
STATUS_GRAPHICS_INSUFFICIENT_DMA_BUFFER 0xC01E0001	The driver needs more DMA buffer space to complete the requested operation.
STATUS_GRAPHICS_INVALID_DISPLAY_ADAPTER 0xC01E0002	The specified display adapter handle is invalid.
STATUS_GRAPHICS_ADAPTER_WAS_RESET 0xC01E0003	The specified display adapter and all of its state have been reset.
STATUS_GRAPHICS_INVALID_DRIVER_MODEL 0xC01E0004	The driver stack does not match the expected driver model.
STATUS_GRAPHICS_PRESENT_MODE_CHANGED 0xC01E0005	Present happened but ended up into the changed desktop mode.
STATUS_GRAPHICS_PRESENT_OCCLUDED 0xC01E0006	Nothing to present due to desktop occlusion.
STATUS_GRAPHICS_PRESENT_DENIED 0xC01E0007	Not able to present due to denial of desktop access.
STATUS_GRAPHICS_CANNOTCOLORCONVERT 0xC01E0008	Not able to present with color conversion.



Value	Meaning
STATUS_GRAPHICS_NO_VIDEO_MEMORY 0xC01E0100	Not enough video memory is available to complete the operation.
STATUS_GRAPHICS_CANT_LOCK_MEMORY 0xC01E0101	Could not probe and lock the underlying memory of an allocation.
STATUS_GRAPHICS_ALLOCATION_BUSY 0xC01E0102	The allocation is currently busy.
STATUS_GRAPHICS_TOO_MANY_REFERENCES 0xC01E0103	An object being referenced has already reached the maximum reference count and cannot be referenced further.
STATUS_GRAPHICS_TRY_AGAIN_LATER 0xC01E0104	A problem could not be solved due to an existing condition. Try again later.
STATUS_GRAPHICS_TRY_AGAIN_NOW 0xC01E0105	A problem could not be solved due to an existing condition. Try again now.
STATUS_GRAPHICS_ALLOCATION_INVALID 0xC01E0106	The allocation is invalid.
STATUS_GRAPHICS_UNSWIZZLING_APERTURE_UNAVAILABLE 0xC01E0107	No more unswizzling apertures are currently available.
STATUS_GRAPHICS_UNSWIZZLING_APERTURE_UNSUPPORTED 0xC01E0108	The current allocation cannot be unswizzled by an aperture.
STATUS_GRAPHICS_CANT_EVICT_PINNED_ALLOCATION 0xC01E0109	The request failed because a pinned allocation cannot be evicted.
STATUS_GRAPHICS_INVALID_ALLOCATION_USAGE 0xC01E0110	The allocation cannot be used from its current segment location for the specified operation.
STATUS_GRAPHICS_CANT_RENDER_LOCKED_ALLOCATION 0xC01E0111	A locked allocation cannot be used in the current command buffer.
STATUS_GRAPHICS_ALLOCATION_CLOSED 0xC01E0112	The allocation being referenced has been closed permanently.
STATUS_GRAPHICS_INVALID_ALLOCATION_INSTANCE 0xC01E0113	An invalid allocation instance is being referenced.
STATUS_GRAPHICS_INVALID_ALLOCATION_HANDLE 0xC01E0114	An invalid allocation handle is being referenced.
STATUS_GRAPHICS_WRONG_ALLOCATION_DEVICE 0xC01E0115	The allocation being referenced does not belong to the current device.
STATUS_GRAPHICS_ALLOCATION_CONTENT_LOST 0xC01E0116	The specified allocation lost its content.

Value	Meaning
STATUS_GRAPHICS_GPU_EXCEPTION_ON_DEVICE 0xC01E0200	A GPU exception was detected on the given device. The device cannot be scheduled.
STATUS_GRAPHICS_INVALID_VIDPN_TOPOLOGY 0xC01E0300	The specified VidPN topology is invalid.
STATUS_GRAPHICS_VIDPN_TOPOLOGY_NOT_SUPPORTED 0xC01E0301	The specified VidPN topology is valid but is not supported by this model of the display adapter.
STATUS_GRAPHICS_VIDPN_TOPOLOGY_CURRENTLY_NOT_SUPPORTED 0xC01E0302	The specified VidPN topology is valid but is not currently supported by the display adapter due to allocation of its resources.
STATUS_GRAPHICS_INVALID_VIDPN 0xC01E0303	The specified VidPN handle is invalid.
STATUS_GRAPHICS_INVALID_VIDEO_PRESENT_SOURCE 0xC01E0304	The specified video present source is invalid.
STATUS_GRAPHICS_INVALID_VIDEO_PRESENT_TARGET 0xC01E0305	The specified video present target is invalid.
STATUS_GRAPHICS_VIDPN_MODALITY_NOT_SUPPORTED 0xC01E0306	The specified VidPN modality is not supported (for example, at least two of the pinned modes are not co-functional).
STATUS_GRAPHICS_INVALID_VIDPN_SOURCEMODESET 0xC01E0308	The specified VidPN source mode set is invalid.
STATUS_GRAPHICS_INVALID_VIDPN_TARGETMODESET 0xC01E0309	The specified VidPN target mode set is invalid.
STATUS_GRAPHICS_INVALID_FREQUENCY 0xC01E030A	The specified video signal frequency is invalid.
STATUS_GRAPHICS_INVALID_ACTIVE_REGION 0xC01E030B	The specified video signal active region is invalid.
STATUS_GRAPHICS_INVALID_TOTAL_REGION 0xC01E030C	The specified video signal total region is invalid.
STATUS_GRAPHICS_INVALID_VIDEO_PRESENT_SOURCE_MODE 0xC01E0310	The specified video present source mode is invalid.
STATUS_GRAPHICS_INVALID_VIDEO_PRESENT_TARGET_MODE 0xC01E0311	The specified video present target mode is invalid.
STATUS_GRAPHICS_PINNED_MODE_MUST_REMAIN_IN_SET 0xC01E0312	The pinned mode must remain in the set on the VidPN's co-functional modality enumeration.

Value	Meaning
STATUS_GRAPHICS_PATH_ALREADY_IN_TOPOLOGY 0xC01E0313	The specified video present path is already in the VidPN's topology.
STATUS_GRAPHICS_MODE_ALREADY_IN_MODESET 0xC01E0314	The specified mode is already in the mode set.
STATUS_GRAPHICS_INVALID_VIDEOPRESENTSOURCESET 0xC01E0315	The specified video present source set is invalid.
STATUS_GRAPHICS_INVALID_VIDEOPRESENTTARGETSET 0xC01E0316	The specified video present target set is invalid.
STATUS_GRAPHICS_SOURCE_ALREADY_IN_SET 0xC01E0317	The specified video present source is already in the video present source set.
STATUS_GRAPHICS_TARGET_ALREADY_IN_SET 0xC01E0318	The specified video present target is already in the video present target set.
STATUS_GRAPHICS_INVALID_VIDPN_PRESENT_PATH 0xC01E0319	The specified VidPN present path is invalid.
STATUS_GRAPHICS_NO_RECOMMENDED_VIDPN_TOPOLOGY 0xC01E031A	The miniport has no recommendation for augmenting the specified VidPN's topology.
STATUS_GRAPHICS_INVALID_MONITOR_FREQUENCYRANGESET 0xC01E031B	The specified monitor frequency range set is invalid.
STATUS_GRAPHICS_INVALID_MONITOR_FREQUENCYRANGE 0xC01E031C	The specified monitor frequency range is invalid.
STATUS_GRAPHICS_FREQUENCYRANGE_NOT_IN_SET 0xC01E031D	The specified frequency range is not in the specified monitor frequency range set.
STATUS_GRAPHICS_FREQUENCYRANGE_ALREADY_IN_SET 0xC01E031F	The specified frequency range is already in the specified monitor frequency range set.
STATUS_GRAPHICS_STALE_MODESET 0xC01E0320	The specified mode set is stale. Reacquire the new mode set.
STATUS_GRAPHICS_INVALID_MONITOR_SOURCEMODESET 0xC01E0321	The specified monitor source mode set is invalid.
STATUS_GRAPHICS_INVALID_MONITOR_SOURCE_MODE 0xC01E0322	The specified monitor source mode is invalid.
STATUS_GRAPHICS_NO_RECOMMENDED_FUNCTIONAL_VIDPN 0xC01E0323	The miniport does not have a recommendation regarding the request to provide a functional VidPN given the current display adapter configuration.
STATUS_GRAPHICS_MODE_ID_MUST_BE_UNIQUE	The ID of the specified mode is being

Value	Meaning
0xC01E0324	used by another mode in the set.
STATUS_GRAPHICS_EMPTY_ADAPTER_MONITOR_MODE_SUPPORT_INTERSECTION 0xC01E0325	The system failed to determine a mode that is supported by both the display adapter and the monitor connected to it.
STATUS_GRAPHICS_VIDEO_PRESENT_TARGETS_LESS_THAN_SOURCES 0xC01E0326	The number of video present targets must be greater than or equal to the number of video present sources.
STATUS_GRAPHICS_PATH_NOT_IN_TOPOLOGY 0xC01E0327	The specified present path is not in the VidPN's topology.
STATUS_GRAPHICS_ADAPTER_MUST_HAVE_AT_LEAST_ONE_SOURCE 0xC01E0328	The display adapter must have at least one video present source.
STATUS_GRAPHICS_ADAPTER_MUST_HAVE_AT_LEAST_ONE_TARGET 0xC01E0329	The display adapter must have at least one video present target.
STATUS_GRAPHICS_INVALID_MONITORDESCRIPTORSET 0xC01E032A	The specified monitor descriptor set is invalid.
STATUS_GRAPHICS_INVALID_MONITORDESCRIPTOR 0xC01E032B	The specified monitor descriptor is invalid.
STATUS_GRAPHICS_MONITORDESCRIPTOR_NOT_IN_SET 0xC01E032C	The specified descriptor is not in the specified monitor descriptor set.
STATUS_GRAPHICS_MONITORDESCRIPTOR_ALREADY_IN_SET 0xC01E032D	The specified descriptor is already in the specified monitor descriptor set.
STATUS_GRAPHICS_MONITORDESCRIPTOR_ID_MUST_BE_UNIQUE 0xC01E032E	The ID of the specified monitor descriptor is being used by another descriptor in the set.
STATUS_GRAPHICS_INVALID_VIDPN_TARGET_SUBSET_TYPE 0xC01E032F	The specified video present target subset type is invalid.
STATUS_GRAPHICS_RESOURCES_NOT_RELATED 0xC01E0330	Two or more of the specified resources are not related to each other, as defined by the interface semantics.
STATUS_GRAPHICS_SOURCE_ID_MUST_BE_UNIQUE 0xC01E0331	The ID of the specified video present source is being used by another source in the set.
STATUS_GRAPHICS_TARGET_ID_MUST_BE_UNIQUE 0xC01E0332	The ID of the specified video present target is being used by another target in the set.
STATUS_GRAPHICS_NO_AVAILABLE_VIDPN_TARGET 0xC01E0333	The specified VidPN source cannot be used because there is no available

Value	Meaning
	VidPN target to connect it to.
STATUS_GRAPHICS_MONITOR_COULD_NOT_BE_ASSOCIATED_WITH_ADAPTER 0xC01E0334	The newly arrived monitor could not be associated with a display adapter.
STATUS_GRAPHICS_NO_VIDPNMGR 0xC01E0335	The particular display adapter does not have an associated VidPN manager.
STATUS_GRAPHICS_NO_ACTIVE_VIDPN 0xC01E0336	The VidPN manager of the particular display adapter does not have an active VidPN.
STATUS_GRAPHICS_STALE_VIDPN_TOPOLOGY 0xC01E0337	The specified VidPN topology is stale; obtain the new topology.
STATUS_GRAPHICS_MONITOR_NOT_CONNECTED 0xC01E0338	No monitor is connected on the specified video present target.
STATUS_GRAPHICS_SOURCE_NOT_IN_TOPOLOGY 0xC01E0339	The specified source is not part of the specified VidPN's topology.
STATUS_GRAPHICS_INVALID_PRIMARYSURFACE_SIZE 0xC01E033A	The specified primary surface size is invalid.
STATUS_GRAPHICS_INVALID_VISIBLEREGION_SIZE 0xC01E033B	The specified visible region size is invalid.
STATUS_GRAPHICS_INVALID_STRIDE 0xC01E033C	The specified stride is invalid.
STATUS_GRAPHICS_INVALID_PIXELFORMAT 0xC01E033D	The specified pixel format is invalid.
STATUS_GRAPHICS_INVALID_COLORBASIS 0xC01E033E	The specified color basis is invalid.
STATUS_GRAPHICS_INVALID_PIXELVALUEACCESSMODE 0xC01E033F	The specified pixel value access mode is invalid.
STATUS_GRAPHICS_TARGET_NOT_IN_TOPOLOGY 0xC01E0340	The specified target is not part of the specified VidPN's topology.
STATUS_GRAPHICS_NO_DISPLAY_MODE_MANAGEMENT_SUPPORT 0xC01E0341	Failed to acquire the display mode management interface.
STATUS_GRAPHICS_VIDPN_SOURCE_IN_USE 0xC01E0342	The specified VidPN source is already owned by a DMM client and cannot be used until that client releases it.
STATUS_GRAPHICS_CANT_ACCESS_ACTIVE_VIDPN 0xC01E0343	The specified VidPN is active and cannot be accessed.
STATUS_GRAPHICS_INVALID_PATH_IMPORTANCE_ORDINAL	The specified VidPN's present path

Value	Meaning
0xC01E0344	importance ordinal is invalid.
STATUS_GRAPHICS_INVALID_PATH_CONTENT_GEOMETRY_TRANSFORMATION 0xC01E0345	The specified VidPN's present path content geometry transformation is invalid.
STATUS_GRAPHICS_PATH_CONTENT_GEOMETRY_TRANSFORMATION_NOT_SUPPORTED 0xC01E0346	The specified content geometry transformation is not supported on the respective VidPN present path.
STATUS_GRAPHICS_INVALID_GAMMA_RAMP 0xC01E0347	The specified gamma ramp is invalid.
STATUS_GRAPHICS_GAMMA_RAMP_NOT_SUPPORTED 0xC01E0348	The specified gamma ramp is not supported on the respective VidPN present path.
STATUS_GRAPHICS_MULTISAMPLING_NOT_SUPPORTED 0xC01E0349	Multisampling is not supported on the respective VidPN present path.
STATUS_GRAPHICS_MODE_NOT_IN_MODESET 0xC01E034A	The specified mode is not in the specified mode set.
STATUS_GRAPHICS_INVALID_VIDPN_TOPOLOGY_RECOMMENDATION_REASON 0xC01E034D	The specified VidPN topology recommendation reason is invalid.
STATUS_GRAPHICS_INVALID_PATH_CONTENT_TYPE 0xC01E034E	The specified VidPN present path content type is invalid.
STATUS_GRAPHICS_INVALID_COPYPROTECTION_TYPE 0xC01E034F	The specified VidPN present path copy protection type is invalid.
STATUS_GRAPHICS_UNASSIGNED_MODESET_ALREADY_EXISTS 0xC01E0350	Only one unassigned mode set can exist at any one time for a particular VidPN source or target.
STATUS_GRAPHICS_INVALID_SCANLINE_ORDERING 0xC01E0352	The specified scan line ordering type is invalid.
STATUS_GRAPHICS_TOPOLOGY_CHANGES_NOT_ALLOWED 0xC01E0353	The topology changes are not allowed for the specified VidPN.
STATUS_GRAPHICS_NO_AVAILABLE_IMPORTANCE_ORDINALS 0xC01E0354	All available importance ordinals are being used in the specified topology.
STATUS_GRAPHICS_INCOMPATIBLE_PRIVATE_FORMAT 0xC01E0355	The specified primary surface has a different private-format attribute than the current primary surface.
STATUS_GRAPHICS_INVALID_MODE_PRUNING_ALGORITHM 0xC01E0356	The specified mode-pruning algorithm is invalid.
STATUS_GRAPHICS_INVALID_MONITOR_CAPABILITY_ORIGIN	The specified monitor-capability origin is

Value	Meaning
0xC01E0357	invalid.
STATUS_GRAPHICS_INVALID_MONITOR_FREQUENCYRANGE_CONSTRAINT 0xC01E0358	The specified monitor-frequency range constraint is invalid.
STATUS_GRAPHICS_MAX_NUM_PATHS_REACHED 0xC01E0359	The maximum supported number of present paths has been reached.
STATUS_GRAPHICS_CANCEL_VIDPN_TOPOLOGY_AUGMENTATION 0xC01E035A	The miniport requested that augmentation be canceled for the specified source of the specified VidPN's topology.
STATUS_GRAPHICS_INVALID_CLIENT_TYPE 0xC01E035B	The specified client type was not recognized.
STATUS_GRAPHICS_CLIENTVIDPN_NOT_SET 0xC01E035C	The client VidPN is not set on this adapter (for example, no user mode-initiated mode changes have taken place on this adapter).
STATUS_GRAPHICS_SPECIFIED_CHILD_ALREADY_CONNECTED 0xC01E0400	The specified display adapter child device already has an external device connected to it.
STATUS_GRAPHICS_CHILD_DESCRIPTOR_NOT_SUPPORTED 0xC01E0401	The display adapter child device does not support reporting a descriptor.
STATUS_GRAPHICS_NOT_A_LINKED_ADAPTER 0xC01E0430	The display adapter is not linked to any other adapters.
STATUS_GRAPHICS_LEADLINK_NOT_ENUMERATED 0xC01E0431	The lead adapter in a linked configuration was not enumerated yet.
STATUS_GRAPHICS_CHAINLINKS_NOT_ENUMERATED 0xC01E0432	Some chain adapters in a linked configuration have not yet been enumerated.
STATUS_GRAPHICS_ADAPTER_CHAIN_NOT_READY 0xC01E0433	The chain of linked adapters is not ready to start because of an unknown failure.
STATUS_GRAPHICS_CHAINLINKS_NOT_STARTED 0xC01E0434	An attempt was made to start a lead link display adapter when the chain links had not yet started.
STATUS_GRAPHICS_CHAINLINKS_NOT_POWERED_ON 0xC01E0435	An attempt was made to turn on a lead link display adapter when the chain links were turned off.
STATUS_GRAPHICS_INCONSISTENT_DEVICE_LINK_STATE 0xC01E0436	The adapter link was found in an inconsistent state. Not all adapters are in an expected PNP/power state.
STATUS_GRAPHICS_NOT_POST_DEVICE_DRIVER	The driver trying to start is not the

Value	Meaning
0xC01E0438	same as the driver for the posted display adapter.
STATUS_GRAPHICS_ADAPTER_ACCESS_NOT_EXCLUDED 0xC01E043B	An operation is being attempted that requires the display adapter to be in a quiescent state.
STATUS_GRAPHICS_OPM_PROTECTED_OUTPUT_DOES_NOT_HAVE_COPP_SEMANTICS 0xC01E051C	<p>The DxgkDdiOPMGetCOPPCompatibleInformation, DxgkDdiOPMGetInformation, or DxgkDdiOPMConfigureProtectedOutput function failed. This error is returned only if a protected output has OPM semantics.</p> <p>DxgkDdiOPMGetCOPPCompatibleInformation always returns this error if a protected output has OPM semantics.</p> <p>DxgkDdiOPMGetInformation returns this error code if the caller requested COPP-specific information.</p> <p>DxgkDdiOPMConfigureProtectedOutput returns this error when the caller tries to use a COPP-specific command.</p>
STATUS_GRAPHICS_OPM_INVALID_INFORMATION_REQUEST 0xC01E051D	The DxgkDdiOPMGetInformation and DxgkDdiOPMGetCOPPCompatibleInformation functions return this error code if the passed-in sequence number is not the expected sequence number or the passed-in OMAC value is invalid.
STATUS_GRAPHICS_OPM_DRIVER_INTERNAL_ERROR 0xC01E051E	The function failed because an unexpected error occurred inside a display driver.
STATUS_GRAPHICS_OPM_PROTECTED_OUTPUT_DOES_NOT_HAVE_OPM_SEMANTICS 0xC01E051F	<p>The DxgkDdiOPMGetCOPPCompatibleInformation, DxgkDdiOPMGetInformation, or DxgkDdiOPMConfigureProtectedOutput function failed. This error is returned only if a protected output has COPP semantics.</p> <p>DxgkDdiOPMGetCOPPCompatibleInformation returns this error code if the caller requested OPM-specific information.</p> <p>DxgkDdiOPMGetInformation always returns this error if a protected output has COPP semantics.</p> <p>DxgkDdiOPMConfigureProtectedOutput returns this error when the caller tries to use an OPM-specific command.</p>
STATUS_GRAPHICS_OPM_SIGNALING_NOT_SUPPORTED 0xC01E0520	The DxgkDdiOPMGetCOPPCompatibleInformation and DxgkDdiOPMConfigureProtectedOutput



Value	Meaning
	functions return this error if the display driver does not support the DXGKMDT_OPM_GET_ACP_AND_CGMSA_SIGNALING and DXGKMDT_OPM_SET_ACP_AND_CGMSA_SIGNALING GUIDs.
STATUS_GRAPHICS_OPM_INVALID_CONFIGURATION_REQUEST 0xC01E0521	The DxgkDdiOPMConfigureProtectedOutput function returns this error code if the passed-in sequence number is not the expected sequence number or the passed-in OMAC value is invalid.
STATUS_GRAPHICS_OPM_NOT_SUPPORTED 0xC01E0500	The driver does not support OPM.
STATUS_GRAPHICS_COPP_NOT_SUPPORTED 0xC01E0501	The driver does not support COPP.
STATUS_GRAPHICS_UAB_NOT_SUPPORTED 0xC01E0502	The driver does not support UAB.
STATUS_GRAPHICS_OPM_INVALID_ENCRYPTED_PARAMETERS 0xC01E0503	The specified encrypted parameters are invalid.
STATUS_GRAPHICS_OPM_PARAMETER_ARRAY_TOO_SMALL 0xC01E0504	An array passed to a function cannot hold all of the data that the function wants to put in it.
STATUS_GRAPHICS_OPM_NO_PROTECTED_OUTPUTS_EXIST 0xC01E0505	The GDI display device passed to this function does not have any active protected outputs.
STATUS_GRAPHICS_PVP_NO_DISPLAY_DEVICE_CORRESPONDS_TO_NAME 0xC01E0506	The PVP cannot find an actual GDI display device that corresponds to the passed-in GDI display device name.
STATUS_GRAPHICS_PVP_DISPLAY_DEVICE_NOT_ATTACHED_TO_DESKTOP 0xC01E0507	This function failed because the GDI display device passed to it was not attached to the Windows desktop.
STATUS_GRAPHICS_PVP_MIRRORING_DEVICES_NOT_SUPPORTED 0xC01E0508	The PVP does not support mirroring display devices because they do not have any protected outputs.
STATUS_GRAPHICS_OPM_INVALID_POINTER 0xC01E050A	The function failed because an invalid pointer parameter was passed to it. A pointer parameter is invalid if it is null, is not correctly aligned, or it points to an invalid address or a kernel mode address.
STATUS_GRAPHICS_OPM_INTERNAL_ERROR 0xC01E050B	An internal error caused an operation to fail.

Value	Meaning
STATUS_GRAPHICS_OPM_INVALID_HANDLE 0xC01E050C	The function failed because the caller passed in an invalid OPM user-mode handle.
STATUS_GRAPHICS_PVP_NO_MONITORS_CORRESPOND_TO_DISPLAY_DEVICE 0xC01E050D	This function failed because the GDI device passed to it did not have any monitors associated with it.
STATUS_GRAPHICS_PVP_INVALID_CERTIFICATE_LENGTH 0xC01E050E	A certificate could not be returned because the certificate buffer passed to the function was too small.
STATUS_GRAPHICS_OPM_SPANNING_MODE_ENABLED 0xC01E050F	DxgkDdiOpmCreateProtectedOutput() could not create a protected output because the video present yarget is in spanning mode.
STATUS_GRAPHICS_OPM_THEATER_MODE_ENABLED 0xC01E0510	DxgkDdiOpmCreateProtectedOutput() could not create a protected output because the video present target is in theater mode.
STATUS_GRAPHICS_PVP_HFS_FAILED 0xC01E0511	The function call failed because the display adapter's hardware functionality scan (HFS) failed to validate the graphics hardware.
STATUS_GRAPHICS_OPM_INVALID_SRM 0xC01E0512	The HDCP SRM passed to this function did not comply with section 5 of the HDCP 1.1 specification.
STATUS_GRAPHICS_OPM_OUTPUT_DOES_NOT_SUPPORT_HDCP 0xC01E0513	The protected output cannot enable the HDCP system because it does not support it.
STATUS_GRAPHICS_OPM_OUTPUT_DOES_NOT_SUPPORT_ACP 0xC01E0514	The protected output cannot enable analog copy protection because it does not support it.
STATUS_GRAPHICS_OPM_OUTPUT_DOES_NOT_SUPPORT_CGMSA 0xC01E0515	The protected output cannot enable the CGMS-A protection technology because it does not support it.
STATUS_GRAPHICS_OPM_HDCP_SRM_NEVER_SET 0xC01E0516	DxgkDdiOPMGetInformation() cannot return the version of the SRM being used because the application never successfully passed an SRM to the protected output.
STATUS_GRAPHICS_OPM_RESOLUTION_TOO_HIGH 0xC01E0517	DxgkDdiOPMConfigureProtectedOutput() cannot enable the specified output protection technology because the output's screen resolution is too high.
STATUS_GRAPHICS_OPM_ALL_HDCP_HARDWARE_ALREADY_IN_USE 0xC01E0518	DxgkDdiOPMConfigureProtectedOutput() cannot enable HDCP because other physical outputs are using the display

Value	Meaning
	adapter's HDCP hardware.
STATUS_GRAPHICS_OPM_PROTECTED_OUTPUT_NO_LONGER_EXISTS 0xC01E051A	The operating system asynchronously destroyed this OPM-protected output because the operating system state changed. This error typically occurs because the monitor PDO associated with this protected output was removed or stopped, the protected output's session became a nonconsole session, or the protected output's desktop became inactive.
STATUS_GRAPHICS_OPM_SESSION_TYPE_CHANGE_IN_PROGRESS 0xC01E051B	OPM functions cannot be called when a session is changing its type. Three types of sessions currently exist: console, disconnected, and remote (RDP or ICA).
STATUS_GRAPHICS_I2C_NOT_SUPPORTED 0xC01E0580	The monitor connected to the specified video output does not have an I2C bus.
STATUS_GRAPHICS_I2C_DEVICE_DOES_NOT_EXIST 0xC01E0581	No device on the I2C bus has the specified address.
STATUS_GRAPHICS_I2C_ERROR_TRANSMITTING_DATA 0xC01E0582	An error occurred while transmitting data to the device on the I2C bus.
STATUS_GRAPHICS_I2C_ERROR_RECEIVING_DATA 0xC01E0583	An error occurred while receiving data from the device on the I2C bus.
STATUS_GRAPHICS_DDCCI_VCP_NOT_SUPPORTED 0xC01E0584	The monitor does not support the specified VCP code.
STATUS_GRAPHICS_DDCCI_INVALID_DATA 0xC01E0585	The data received from the monitor is invalid.
STATUS_GRAPHICS_DDCCI_MONITOR_RETURNED_INVALID_TIMING_STATUS_BYTE 0xC01E0586	A function call failed because a monitor returned an invalid timing status byte when the operating system used the DDC/CI get timing report and timing message command to get a timing report from a monitor.
STATUS_GRAPHICS_DDCCI_INVALID_CAPABILITIES_STRING 0xC01E0587	A monitor returned a DDC/CI capabilities string that did not comply with the ACCESS.bus 3.0, DDC/CI 1.1, or MCCS 2 Revision 1 specification.
STATUS_GRAPHICS_MCA_INTERNAL_ERROR 0xC01E0588	An internal error caused an operation to fail.
STATUS_GRAPHICS_DDCCI_INVALID_MESSAGE_COMMAND 0xC01E0589	An operation failed because a DDC/CI message had an invalid value in its command field.
STATUS_GRAPHICS_DDCCI_INVALID_MESSAGE_LENGTH	This error occurred because a DDC/CI

Value	Meaning
0xC01E058A	message had an invalid value in its length field.
STATUS_GRAPHICS_DDCCI_INVALID_MESSAGE_CHECKSUM 0xC01E058B	This error occurred because the value in a DDC/CI message's checksum field did not match the message's computed checksum value. This error implies that the data was corrupted while it was being transmitted from a monitor to a computer.
STATUS_GRAPHICS_INVALID_PHYSICAL_MONITOR_HANDLE 0xC01E058C	This function failed because an invalid monitor handle was passed to it.
STATUS_GRAPHICS_MONITOR_NO_LONGER_EXISTS 0xC01E058D	The operating system asynchronously destroyed the monitor that corresponds to this handle because the operating system's state changed. This error typically occurs because the monitor PDO associated with this handle was removed or stopped, or a display mode change occurred. A display mode change occurs when Windows sends a WM_DISPLAYCHANGE message to applications.
STATUS_GRAPHICS_ONLY_CONSOLE_SESSION_SUPPORTED 0xC01E05E0	This function can be used only if a program is running in the local console session. It cannot be used if a program is running on a remote desktop session or on a terminal server session.
STATUS_GRAPHICS_NO_DISPLAY_DEVICE_CORRESPONDS_TO_NAME 0xC01E05E1	This function cannot find an actual GDI display device that corresponds to the specified GDI display device name.
STATUS_GRAPHICS_DISPLAY_DEVICE_NOT_ATTACHED_TO_DESKTOP 0xC01E05E2	The function failed because the specified GDI display device was not attached to the Windows desktop.
STATUS_GRAPHICS_MIRRORING_DEVICES_NOT_SUPPORTED 0xC01E05E3	This function does not support GDI mirroring display devices because GDI mirroring display devices do not have any physical monitors associated with them.
STATUS_GRAPHICS_INVALID_POINTER 0xC01E05E4	The function failed because an invalid pointer parameter was passed to it. A pointer parameter is invalid if it is null, is not correctly aligned, or points to an invalid address or to a kernel mode address.
STATUS_GRAPHICS_NO_MONITORS_CORRESPOND_TO_DISPLAY_DEVICE 0xC01E05E5	This function failed because the GDI device passed to it did not have a monitor associated with it.

Value	Meaning
STATUS_GRAPHICS_PARAMETER_ARRAY_TOO_SMALL 0xC01E05E6	An array passed to the function cannot hold all of the data that the function must copy into the array.
STATUS_GRAPHICS_INTERNAL_ERROR 0xC01E05E7	An internal error caused an operation to fail.
STATUS_GRAPHICS_SESSION_TYPE_CHANGE_IN_PROGRESS 0xC01E05E8	The function failed because the current session is changing its type. This function cannot be called when the current session is changing its type. Three types of sessions currently exist: console, disconnected, and remote (RDP or ICA).
STATUS_FVE_LOCKED_VOLUME 0xC0210000	The volume must be unlocked before it can be used.
STATUS_FVE_NOT_ENCRYPTED 0xC0210001	The volume is fully decrypted and no key is available.
STATUS_FVE_BAD_INFORMATION 0xC0210002	The control block for the encrypted volume is not valid.
STATUS_FVE_TOO_SMALL 0xC0210003	Not enough free space remains on the volume to allow encryption.
STATUS_FVE_FAILED_WRONG_FS 0xC0210004	The partition cannot be encrypted because the file system is not supported.
STATUS_FVE_FAILED_BAD_FS 0xC0210005	The file system is inconsistent. Run the Check Disk utility.
STATUS_FVE_FS_NOT_EXTENDED 0xC0210006	The file system does not extend to the end of the volume.
STATUS_FVE_FS_MOUNTED 0xC0210007	This operation cannot be performed while a file system is mounted on the volume.
STATUS_FVE_NO_LICENSE 0xC0210008	BitLocker Drive Encryption is not included with this version of Windows.
STATUS_FVE_ACTION_NOT_ALLOWED 0xC0210009	The requested action was denied by the FVE control engine.
STATUS_FVE_BAD_DATA 0xC021000A	The data supplied is malformed.
STATUS_FVE_VOLUME_NOT_BOUND 0xC021000B	The volume is not bound to the system.
STATUS_FVE_NOT_DATA_VOLUME	The volume specified is not a data

Value	Meaning
0xC021000C	volume.
STATUS_FVE_CONV_READ_ERROR 0xC021000D	A read operation failed while converting the volume.
STATUS_FVE_CONV_WRITE_ERROR 0xC021000E	A write operation failed while converting the volume.
STATUS_FVE_OVERLAPPED_UPDATE 0xC021000F	The control block for the encrypted volume was updated by another thread. Try again.
STATUS_FVE_FAILED_SECTOR_SIZE 0xC0210010	The volume encryption algorithm cannot be used on this sector size.
STATUS_FVE_FAILED_AUTHENTICATION 0xC0210011	BitLocker recovery authentication failed.
STATUS_FVE_NOT_OS_VOLUME 0xC0210012	The volume specified is not the boot operating system volume.
STATUS_FVE_KEYFILE_NOT_FOUND 0xC0210013	The BitLocker startup key or recovery password could not be read from external media.
STATUS_FVE_KEYFILE_INVALID 0xC0210014	The BitLocker startup key or recovery password file is corrupt or invalid.
STATUS_FVE_KEYFILE_NO_VMK 0xC0210015	The BitLocker encryption key could not be obtained from the startup key or the recovery password.
STATUS_FVE_TPM_DISABLED 0xC0210016	The TPM is disabled.
STATUS_FVE_TPM_SRK_AUTH_NOT_ZERO 0xC0210017	The authorization data for the SRK of the TPM is not zero.
STATUS_FVE_TPM_INVALID_PCR 0xC0210018	The system boot information changed or the TPM locked out access to BitLocker encryption keys until the computer is restarted.
STATUS_FVE_TPM_NO_VMK 0xC0210019	The BitLocker encryption key could not be obtained from the TPM.
STATUS_FVE_PIN_INVALID 0xC021001A	The BitLocker encryption key could not be obtained from the TPM and PIN.
STATUS_FVE_AUTH_INVALID_APPLICATION 0xC021001B	A boot application hash does not match the hash computed when BitLocker was turned on.
STATUS_FVE_AUTH_INVALID_CONFIG 0xC021001C	The Boot Configuration Data (BCD) settings are not supported or have

Value	Meaning
	changed because BitLocker was enabled.
STATUS_FVE_DEBUGGER_ENABLED 0xC021001D	Boot debugging is enabled. Run Windows Boot Configuration Data Store Editor (bcdedit.exe) to turn it off.
STATUS_FVE_DRY_RUN_FAILED 0xC021001E	The BitLocker encryption key could not be obtained.
STATUS_FVE_BAD_METADATA_POINTER 0xC021001F	The metadata disk region pointer is incorrect.
STATUS_FVE_OLD_METADATA_COPY 0xC0210020	The backup copy of the metadata is out of date.
STATUS_FVE_REBOOT_REQUIRED 0xC0210021	No action was taken because a system restart is required.
STATUS_FVE_RAW_ACCESS 0xC0210022	No action was taken because BitLocker Drive Encryption is in RAW access mode.
STATUS_FVE_RAW_BLOCKED 0xC0210023	BitLocker Drive Encryption cannot enter RAW access mode for this volume.
STATUS_FWP_CALLOUT_NOT_FOUND 0xC0220001	The callout does not exist.
STATUS_FWP_CONDITION_NOT_FOUND 0xC0220002	The filter condition does not exist.
STATUS_FWP_FILTER_NOT_FOUND 0xC0220003	The filter does not exist.
STATUS_FWP_LAYER_NOT_FOUND 0xC0220004	The layer does not exist.
STATUS_FWP_PROVIDER_NOT_FOUND 0xC0220005	The provider does not exist.
STATUS_FWP_PROVIDER_CONTEXT_NOT_FOUND 0xC0220006	The provider context does not exist.
STATUS_FWP_SUBLAYER_NOT_FOUND 0xC0220007	The sublayer does not exist.
STATUS_FWP_NOT_FOUND 0xC0220008	The object does not exist.
STATUS_FWP_ALREADY_EXISTS 0xC0220009	An object with that GUID or LUID already exists.
STATUS_FWP_IN_USE	The object is referenced by other

Value	Meaning
0xC022000A	objects and cannot be deleted.
STATUS_FWP_DYNAMIC_SESSION_IN_PROGRESS 0xC022000B	The call is not allowed from within a dynamic session.
STATUS_FWP_WRONG_SESSION 0xC022000C	The call was made from the wrong session and cannot be completed.
STATUS_FWP_NO_TXN_IN_PROGRESS 0xC022000D	The call must be made from within an explicit transaction.
STATUS_FWP_TXN_IN_PROGRESS 0xC022000E	The call is not allowed from within an explicit transaction.
STATUS_FWP_TXN_ABORTED 0xC022000F	The explicit transaction has been forcibly canceled.
STATUS_FWP_SESSION_ABORTED 0xC0220010	The session has been canceled.
STATUS_FWP_INCOMPATIBLE_TXN 0xC0220011	The call is not allowed from within a read-only transaction.
STATUS_FWP_TIMEOUT 0xC0220012	The call timed out while waiting to acquire the transaction lock.
STATUS_FWP_NET_EVENTS_DISABLED 0xC0220013	The collection of network diagnostic events is disabled.
STATUS_FWP_INCOMPATIBLE_LAYER 0xC0220014	The operation is not supported by the specified layer.
STATUS_FWP_KM_CLIENTS_ONLY 0xC0220015	The call is allowed for kernel-mode callers only.
STATUS_FWP_LIFETIME_MISMATCH 0xC0220016	The call tried to associate two objects with incompatible lifetimes.
STATUS_FWP_BUILTIN_OBJECT 0xC0220017	The object is built-in and cannot be deleted.
STATUS_FWP_TOO_MANY_BOOTTIME_FILTERS 0xC0220018	The maximum number of boot-time filters has been reached.
STATUS_FWP_TOO_MANY_CALLOUTS 0xC0220018	The maximum number of callouts has been reached.
STATUS_FWP_NOTIFICATION_DROPPED 0xC0220019	A notification could not be delivered because a message queue has reached maximum capacity.
STATUS_FWP_TRAFFIC_MISMATCH 0xC022001A	The traffic parameters do not match those for the security association context.



Value	Meaning
STATUS_FWP_INCOMPATIBLE_SA_STATE 0xC022001B	The call is not allowed for the current security association state.
STATUS_FWP_NULL_POINTER 0xC022001C	A required pointer is null.
STATUS_FWP_INVALID_ENUMERATOR 0xC022001D	An enumerator is not valid.
STATUS_FWP_INVALID_FLAGS 0xC022001E	The flags field contains an invalid value.
STATUS_FWP_INVALID_NET_MASK 0xC022001F	A network mask is not valid.
STATUS_FWP_INVALID_RANGE 0xC0220020	An FWP_RANGE is not valid.
STATUS_FWP_INVALID_INTERVAL 0xC0220021	The time interval is not valid.
STATUS_FWP_ZERO_LENGTH_ARRAY 0xC0220022	An array that must contain at least one element has a zero length.
STATUS_FWP_NULL_DISPLAY_NAME 0xC0220023	The displayData.name field cannot be null.
STATUS_FWP_INVALID_ACTION_TYPE 0xC0220024	The action type is not one of the allowed action types for a filter.
STATUS_FWP_INVALID_WEIGHT 0xC0220025	The filter weight is not valid.
STATUS_FWP_MATCH_TYPE_MISMATCH 0xC0220026	A filter condition contains a match type that is not compatible with the operands.
STATUS_FWP_TYPE_MISMATCH 0xC0220027	An FWP_VALUE or FWPM_CONDITION_VALUE is of the wrong type.
STATUS_FWP_OUT_OF_BOUNDS 0xC0220028	An integer value is outside the allowed range.
STATUS_FWP_RESERVED 0xC0220029	A reserved field is nonzero.
STATUS_FWP_DUPLICATE_CONDITION 0xC022002A	A filter cannot contain multiple conditions operating on a single field.
STATUS_FWP_DUPLICATE_KEYMOD 0xC022002B	A policy cannot contain the same keying module more than once.

Value	Meaning
STATUS_FWP_ACTION_INCOMPATIBLE_WITH_LAYER 0xC022002C	The action type is not compatible with the layer.
STATUS_FWP_ACTION_INCOMPATIBLE_WITH_SUBLAYER 0xC022002D	The action type is not compatible with the sublayer.
STATUS_FWP_CONTEXT_INCOMPATIBLE_WITH_LAYER 0xC022002E	The raw context or the provider context is not compatible with the layer.
STATUS_FWP_CONTEXT_INCOMPATIBLE_WITH_CALLOUT 0xC022002F	The raw context or the provider context is not compatible with the callout.
STATUS_FWP_INCOMPATIBLE_AUTH_METHOD 0xC0220030	The authentication method is not compatible with the policy type.
STATUS_FWP_INCOMPATIBLE_DH_GROUP 0xC0220031	The Diffie-Hellman group is not compatible with the policy type.
STATUS_FWP_EM_NOT_SUPPORTED 0xC0220032	An IKE policy cannot contain an Extended Mode policy.
STATUS_FWP_NEVER_MATCH 0xC0220033	The enumeration template or subscription will never match any objects.
STATUS_FWP_PROVIDER_CONTEXT_MISMATCH 0xC0220034	The provider context is of the wrong type.
STATUS_FWP_INVALID_PARAMETER 0xC0220035	The parameter is incorrect.
STATUS_FWP_TOO_MANY_SUBLAYERS 0xC0220036	The maximum number of sublayers has been reached.
STATUS_FWP_CALLOUT_NOTIFICATION_FAILED 0xC0220037	The notification function for a callout returned an error.
STATUS_FWP_INCOMPATIBLE_AUTH_CONFIG 0xC0220038	The IPsec authentication configuration is not compatible with the authentication type.
STATUS_FWP_INCOMPATIBLE_CIPHER_CONFIG 0xC0220039	The IPsec cipher configuration is not compatible with the cipher type.
STATUS_FWP_TCPIP_NOT_READY 0xC0220100	The TCP/IP stack is not ready.
STATUS_FWP_INJECT_HANDLE_CLOSING 0xC0220101	The injection handle is being closed by another thread.
STATUS_FWP_INJECT_HANDLE_STALE 0xC0220102	The injection handle is stale.

Value	Meaning
STATUS_FWP_CANNOT_PEND 0xC0220103	The classify cannot be pended.
STATUS_NDIS_CLOSING 0xC0230002	The binding to the network interface is being closed.
STATUS_NDIS_BAD_VERSION 0xC0230004	An invalid version was specified.
STATUS_NDIS_BAD_CHARACTERISTICS 0xC0230005	An invalid characteristics table was used.
STATUS_NDIS_ADAPTER_NOT_FOUND 0xC0230006	Failed to find the network interface or the network interface is not ready.
STATUS_NDIS_OPEN_FAILED 0xC0230007	Failed to open the network interface.
STATUS_NDIS_DEVICE_FAILED 0xC0230008	The network interface has encountered an internal unrecoverable failure.
STATUS_NDIS_MULTICAST_FULL 0xC0230009	The multicast list on the network interface is full.
STATUS_NDIS_MULTICAST_EXISTS 0xC023000A	An attempt was made to add a duplicate multicast address to the list.
STATUS_NDIS_MULTICAST_NOT_FOUND 0xC023000B	At attempt was made to remove a multicast address that was never added.
STATUS_NDIS_REQUEST_ABORTED 0xC023000C	The network interface aborted the request.
STATUS_NDIS_RESET_IN_PROGRESS 0xC023000D	The network interface cannot process the request because it is being reset.
STATUS_NDIS_INVALID_PACKET 0xC023000F	An attempt was made to send an invalid packet on a network interface.
STATUS_NDIS_INVALID_DEVICE_REQUEST 0xC0230010	The specified request is not a valid operation for the target device.
STATUS_NDIS_ADAPTER_NOT_READY 0xC0230011	The network interface is not ready to complete this operation.
STATUS_NDIS_INVALID_LENGTH 0xC0230014	The length of the buffer submitted for this operation is not valid.
STATUS_NDIS_INVALID_DATA 0xC0230015	The data used for this operation is not valid.
STATUS_NDIS_BUFFER_TOO_SHORT	The length of the submitted buffer for

Value	Meaning
0xC0230016	this operation is too small.
STATUS_NDIS_INVALID_OID 0xC0230017	The network interface does not support this object identifier.
STATUS_NDIS_ADAPTER_REMOVED 0xC0230018	The network interface has been removed.
STATUS_NDIS_UNSUPPORTED_MEDIA 0xC0230019	The network interface does not support this media type.
STATUS_NDIS_GROUP_ADDRESS_IN_USE 0xC023001A	An attempt was made to remove a token ring group address that is in use by other components.
STATUS_NDIS_FILE_NOT_FOUND 0xC023001B	An attempt was made to map a file that cannot be found.
STATUS_NDIS_ERROR_READING_FILE 0xC023001C	An error occurred while NDIS tried to map the file.
STATUS_NDIS_ALREADY_MAPPED 0xC023001D	An attempt was made to map a file that is already mapped.
STATUS_NDIS_RESOURCE_CONFLICT 0xC023001E	An attempt to allocate a hardware resource failed because the resource is used by another component.
STATUS_NDIS_MEDIA_DISCONNECTED 0xC023001F	The I/O operation failed because the network media is disconnected or the wireless access point is out of range.
STATUS_NDIS_INVALID_ADDRESS 0xC0230022	The network address used in the request is invalid.
STATUS_NDIS_PAUSED 0xC023002A	The offload operation on the network interface has been paused.
STATUS_NDIS_INTERFACE_NOT_FOUND 0xC023002B	The network interface was not found.
STATUS_NDIS_UNSUPPORTED_REVISION 0xC023002C	The revision number specified in the structure is not supported.
STATUS_NDIS_INVALID_PORT 0xC023002D	The specified port does not exist on this network interface.
STATUS_NDIS_INVALID_PORT_STATE 0xC023002E	The current state of the specified port on this network interface does not support the requested operation.
STATUS_NDIS_LOW_POWER_STATE 0xC023002F	The miniport adapter is in a lower power state.

Value	Meaning
STATUS_NDIS_NOT_SUPPORTED 0xC02300BB	The network interface does not support this request.
STATUS_NDIS_DOT11_AUTO_CONFIG_ENABLED 0xC0232000	The wireless LAN interface is in auto-configuration mode and does not support the requested parameter change operation.
STATUS_NDIS_DOT11_MEDIA_IN_USE 0xC0232001	The wireless LAN interface is busy and cannot perform the requested operation.
STATUS_NDIS_DOT11_POWER_STATE_INVALID 0xC0232002	The wireless LAN interface is power down and does not support the requested operation.
STATUS_IPSEC_BAD_SPI 0xC0360001	The SPI in the packet does not match a valid IPsec SA.
STATUS_IPSEC_SA_LIFETIME_EXPIRED 0xC0360002	The packet was received on an IPsec SA whose lifetime has expired.
STATUS_IPSEC_WRONG_SA 0xC0360003	The packet was received on an IPsec SA that does not match the packet characteristics.
STATUS_IPSEC_REPLAY_CHECK_FAILED 0xC0360004	The packet sequence number replay check failed.
STATUS_IPSEC_INVALID_PACKET 0xC0360005	The IPsec header and/or trailer in the packet is invalid.
STATUS_IPSEC_INTEGRITY_CHECK_FAILED 0xC0360006	The IPsec integrity check failed.
STATUS_IPSEC_CLEAR_TEXT_DROP 0xC0360007	IPsec dropped a clear text packet.

### 3 Structure Example

There are no structure examples.

## 4 Security Considerations

These structures require no security considerations beyond those of the protocols that utilize them.

## 5 Appendix A: Windows Behavior

The information in this specification is applicable to all versions of Windows, except as noted below. Unless otherwise specified, any statement of optional behavior in this specification prescribed using the terms SHOULD or SHOULD NOT implies Windows behavior in accordance with the SHOULD or SHOULD NOT prescription.

<1> [Section 2.1:](#) All HRESULT values used by Microsoft have the **C** bit clear.

<2> [Section 2.2:](#) Unless specified otherwise, Windows uses only the values in the following table.

<3> [Section 2.3:](#) All [NTSTATUS values](#) that are used by Microsoft have the C bit clear.

<4> [Section 2.3:](#) Windows defines the following NTSTATUS facility values when the C bit is clear.

Name	Value
FACILITY_DEBUGGER	0x001
FACILITY_RPC_RUNTIME	0x002
FACILITY_RPC_STUBS	0x003
FACILITY_IO_ERROR_CODE	0x004
FACILITY_NTWIN32	0x007
FACILITY_NTSSPI	0x009
FACILITY_TERMINAL_SERVER	0x00A
FACILITY_MUI_ERROR_CODE	0x00B
FACILITY_USB_ERROR_CODE	0x010
FACILITY_HID_ERROR_CODE	0x011
FACILITY_FIREWIRE_ERROR_CODE	0x012
FACILITY_CLUSTER_ERROR_CODE	0x013
FACILITY_ACPI_ERROR_CODE	0x014
FACILITY_SXS_ERROR_CODE	0x015
FACILITY_TRANSACTION	0x019
FACILITY_COMMONLOG	0x01A
FACILITY_VIDEO	0x01B
FACILITY_FILTER_MANAGER	0x01C
FACILITY_MONITOR	0x01D
FACILITY_GRAPHICS_KERNEL	0x01E
FACILITY_DRIVER_FRAMEWORK	0x020



Name	Value
FACILITY_FVE_ERROR_CODE	0x021
FACILITY_FWP_ERROR_CODE	0x022
FACILITY_NDIS_ERROR_CODE	0x023
FACILITY_HYPERVISOR	0x035
FACILITY_IPSEC	0x036
FACILITY_MAXIMUM_VALUE	0x037

## 6 Index

### A

[Applicability](#)

### F

[Fields - vendor-extensible](#)

### G

[Glossary](#)

### H

[HRESULTS packet](#)

### I

[Informative references](#)

[Introduction](#)

### L

[Localization](#)

### N

[Normative references](#)

[NTSTATUS packet](#)

### O

[Overview](#)

### R

References

[informative](#)

[normative](#)

[overview](#)

Relationships

[other protocols](#)

[other structures](#)

### S

[Security - considerations](#)

Structures

[examples](#)

[overview](#)

### V

[Vendor-extensible fields](#)

[Versioning](#)

### W

[Windows behavior](#)