

[MS-MQMQ]: Message Queuing (MSMQ): Data Structures

Intellectual Property Rights Notice for Open Specifications Documentation

- **Technical Documentation.** Microsoft publishes Open Specifications documentation for protocols, file formats, languages, standards as well as overviews of the interaction among each of these technologies.
- **Copyrights.** This documentation is covered by Microsoft copyrights. Regardless of any other terms that are contained in the terms of use for the Microsoft website that hosts this documentation, you may make copies of it in order to develop implementations of the technologies described in the Open Specifications and may distribute portions of it in your implementations using these technologies or your documentation as necessary to properly document the implementation. You may also distribute in your implementation, with or without modification, any schema, IDL's, or code samples that are included in the documentation. This permission also applies to any documents that are referenced in the Open Specifications.
- **No Trade Secrets.** Microsoft does not claim any trade secret rights in this documentation.
- **Patents.** Microsoft has patents that may cover your implementations of the technologies described in the Open Specifications. Neither this notice nor Microsoft's delivery of the documentation grants any licenses under those or any other Microsoft patents. However, a given Open Specification may be covered by Microsoft [Open Specification Promise](#) or the [Community Promise](#). If you would prefer a written license, or if the technologies described in the Open Specifications are not covered by the Open Specifications Promise or Community Promise, as applicable, patent licenses are available by contacting iplg@microsoft.com.
- **Trademarks.** The names of companies and products contained in this documentation may be covered by trademarks or similar intellectual property rights. This notice does not grant any licenses under those rights.
- **Fictitious Names.** The example companies, organizations, products, domain names, e-mail addresses, logos, people, places, and events depicted in this documentation are fictitious. No association with any real company, organization, product, domain name, email address, logo, person, place, or event is intended or should be inferred.

Reservation of Rights. All other rights are reserved, and this notice does not grant any rights other than specifically described above, whether by implication, estoppel, or otherwise.

Tools. The Open Specifications do not require the use of Microsoft programming tools or programming environments in order for you to develop an implementation. If you have access to Microsoft programming tools and environments you are free to take advantage of them. Certain Open Specifications are intended for use in conjunction with publicly available standard specifications and network programming art, and assumes that the reader either is familiar with the aforementioned material or has immediate access to it.

Revision Summary

Date	Revision History	Revision Class	Comments
05/11/2007	0.1		MCPP Milestone 4 Initial Availability
08/10/2007	1.0	Major	Updated and revised the technical content.
09/28/2007	1.0.1	Editorial	Revised and edited the technical content.
10/23/2007	1.0.2	Editorial	Revised and edited the technical content.
11/30/2007	1.0.3	Editorial	Revised and edited the technical content.
01/25/2008	1.0.4	Editorial	Revised and edited the technical content.
03/14/2008	2.0	Major	Updated and revised the technical content.
05/16/2008	2.0.1	Editorial	Revised and edited the technical content.
06/20/2008	3.0	Major	Updated and revised the technical content.
07/25/2008	3.0.1	Editorial	Revised and edited the technical content.
08/29/2008	4.0	Major	Updated and revised the technical content.
10/24/2008	5.0	Major	Updated and revised the technical content.
12/05/2008	6.0	Major	Updated and revised the technical content.
01/16/2009	6.1	Minor	Updated the technical content.
02/27/2009	7.0	Major	Updated and revised the technical content.
04/10/2009	7.1	Minor	Updated the technical content.
05/22/2009	7.2	Minor	Updated the technical content.
07/02/2009	7.3	Minor	Updated the technical content.
08/14/2009	7.4	Minor	Updated the technical content.
09/25/2009	8.0	Major	Updated and revised the technical content.
11/06/2009	9.0	Major	Updated and revised the technical content.
12/18/2009	10.0	Major	Updated and revised the technical content.
01/29/2010	11.0	Major	Updated and revised the technical content.
03/12/2010	11.1	Minor	Updated the technical content.
04/23/2010	11.1.1	Editorial	Revised and edited the technical content.
06/04/2010	11.2	Minor	Updated the technical content.
07/16/2010	12.0	Major	Significantly changed the technical content.

Date	Revision History	Revision Class	Comments
08/27/2010	13.0	Major	Significantly changed the technical content.
10/08/2010	13.1	Minor	Clarified the meaning of the technical content.
11/19/2010	14.0	Major	Significantly changed the technical content.
01/07/2011	15.0	Major	Significantly changed the technical content.
02/11/2011	16.0	Major	Significantly changed the technical content.
03/25/2011	17.0	Major	Significantly changed the technical content.
05/06/2011	17.1	Minor	Clarified the meaning of the technical content.
06/17/2011	17.2	Minor	Clarified the meaning of the technical content.

Contents

1	Introduction	10
1.1	Glossary	10
1.2	References.....	16
1.2.1	Normative References.....	16
1.2.2	Informative References	17
1.3	Relationship to Protocols and Other Structures	18
1.4	Applicability Statement.....	18
1.5	Versioning and Localization	18
1.6	Vendor-Extensible Fields.....	18
2	Definitions and Structures.....	19
2.1	MSMQ Queue Names	19
2.1.1	Path Names	19
2.1.2	Direct Format Names	20
2.1.3	Public Format Names	21
2.1.4	Private Format Names	21
2.1.5	Distribution List Format Names	22
2.1.6	Machine, Connector, and Multicast Format Names	22
2.1.7	Multiple-Element Format Names.....	23
2.2	Structures.....	24
2.2.1	MQDSPUBLICKEY	24
2.2.2	MQDSPUBLICKEYS	24
2.2.3	SECURITY_INFORMATION	25
2.2.4	TA_ADDRESS.....	25
2.2.4.1	IP Address	26
2.2.4.2	IPX Address	26
2.2.5	SEQUENCE_INFO	27
2.2.5.1	SEQUENCE_INFO (Packet)	27
2.2.6	QUEUE_FORMAT_TYPE.....	28
2.2.7	QUEUE_FORMAT	28
2.2.8	OBJECTID.....	31
2.2.9	DL_ID	31
2.2.10	MULTICAST_ID.....	31
2.2.11	QUEUE_SUFFIX_TYPE	31
2.2.12	PROPVARIANT Type Constants	32
2.2.12.1	VARTYPE.....	33
2.2.13	PROPVARIANT	33
2.2.13.1	tag_inner_PROPVARIANT	34
2.2.13.2	PROPVARIANT	35
2.2.14	VARIANT_BOOL.....	35
2.2.15	BLOB	35
2.2.16	COUNTEDARRAY.....	35
2.2.16.1	CAUB	36
2.2.16.2	CAUI	36
2.2.16.3	CAL.....	36
2.2.16.4	CAUL.....	36
2.2.16.5	CAUH	37
2.2.16.6	CACLSID.....	37
2.2.16.7	CALPWSTR.....	37
2.2.16.8	CAPROPVARIANT	37

2.2.17	ULARGE_INTEGER	38
2.2.18	Common Packet Syntax.....	38
2.2.18.1	Packet Data Types	38
2.2.18.1.1	GUID	38
2.2.18.1.2	TxSequenceID.....	38
2.2.18.1.3	MessageIdentifier	39
2.2.18.1.4	MQFFormatNameElement	39
2.2.18.1.4.1	MQFDirectQueueFormatName.....	40
2.2.18.1.4.2	MQFDistributionQueueFormatName.....	40
2.2.18.1.5	Queue Format Type	41
2.2.18.1.5.1	PrivateQueueFormatNameId	41
2.2.18.1.5.2	DirectQueueFormatName.....	41
2.2.18.1.6	Message Class Identifiers	41
2.2.18.1.7	Common Queue Formats	43
2.2.18.1.7.1	PublicQueueFormatName	43
2.2.18.1.7.2	PrivateQueueFormatName	44
2.2.18.1.8	XACTUOW	44
2.2.19	Common Headers	44
2.2.19.1	BaseHeader.....	45
2.2.19.2	UserHeader	47
2.2.19.3	MessagePropertiesHeader	51
2.2.20	UserMessage Packet	55
2.2.20.1	MultiQueueFormatHeader.....	57
2.2.20.2	MQFAddressHeader	58
2.2.20.3	MQFSignatureHeader.....	59
2.2.20.4	SessionHeader.....	60
2.2.20.5	TransactionHeader	61
2.2.20.6	SecurityHeader	63
2.2.20.7	SoapHeader	67
2.2.20.8	DebugHeader	68
2.2.21	MQUSERSIGNCERTS	70
2.2.22	MQUSERSIGNCERT	70
2.2.23	MQQMACCESSMASK	71
2.2.24	MQQUEUEACCESSMASK	73
2.2.25	MQSITEACCESSMASK	74
2.2.26	MQENTACCESSMASK	75
2.2.27	MQCNACCESSMASK	77
2.3	PROPID	78
2.3.1	Queue Property Identifiers.....	78
2.3.1.1	PROPID_Q_INSTANCE	78
2.3.1.2	PROPID_Q_TYPE.....	78
2.3.1.3	PROPID_Q_PATHNAME	78
2.3.1.4	PROPID_Q_JOURNAL.....	79
2.3.1.5	PROPID_Q_QUOTA	79
2.3.1.6	PROPID_Q_BASEPRIORITY	79
2.3.1.7	PROPID_Q_JOURNAL_QUOTA.....	79
2.3.1.8	PROPID_Q_LABEL	79
2.3.1.9	PROPID_Q_CREATE_TIME.....	80
2.3.1.10	PROPID_Q_MODIFY_TIME	80
2.3.1.11	PROPID_Q_AUTHENTICATE	80
2.3.1.12	PROPID_Q_PRIV_LEVEL.....	80
2.3.1.13	PROPID_Q_TRANSACTION	81
2.3.1.14	PROPID_Q_SCOPE	81

2.3.1.15	PROPID_Q_QMID	81
2.3.1.16	PROPID_Q_PARTITIONID	81
2.3.1.17	PROPID_Q_SEQNUM	81
2.3.1.18	PROPID_Q_HASHKEY	82
2.3.1.19	PROPID_Q_LABEL_HASHKEY	82
2.3.1.20	PROPID_Q_FULL_PATH	82
2.3.1.21	PROPID_Q_NAME_SUFFIX	82
2.3.1.22	PROPID_Q_PATHNAME_DNS	82
2.3.1.23	PROPID_Q_MULTICAST_ADDRESS	82
2.3.1.24	PROPID_Q_ADS_PATH	83
2.3.1.25	PROPID_Q_SECURITY	83
2.3.1.26	PROPID_Q_OBJ_SECURITY	83
2.3.1.27	PROPID_Q_SECURITY_INFORMATION	83
2.3.2	Machine Property Identifiers	84
2.3.2.1	PROPID_QM_SITE_ID	84
2.3.2.2	PROPID_QM_MACHINE_ID	84
2.3.2.3	PROPID_QM_PATHNAME	84
2.3.2.4	PROPID_QM_ENCRYPTION_PK	84
2.3.2.5	PROPID_QM_ADDRESS	84
2.3.2.6	PROPID_QM_CNS	84
2.3.2.7	PROPID_QM_OUTFRS	85
2.3.2.8	PROPID_QM_INFRS	85
2.3.2.9	PROPID_QM_SERVICE	85
2.3.2.10	PROPID_QM_QUOTA	85
2.3.2.11	PROPID_QM_PARTITIONID	85
2.3.2.12	PROPID_QM_HASHKEY	86
2.3.2.13	PROPID_QM_SEQNUM	86
2.3.2.14	PROPID_QM_JOURNAL_QUOTA	86
2.3.2.15	PROPID_QM_MACHINE_TYPE	86
2.3.2.16	PROPID_QM_CREATE_TIME	86
2.3.2.17	PROPID_QM_MODIFY_TIME	86
2.3.2.18	PROPID_QM_FOREIGN	86
2.3.2.19	PROPID_QM_OS	87
2.3.2.20	PROPID_QM_FULL_PATH	87
2.3.2.21	PROPID_QM_SITE_IDS	87
2.3.2.22	PROPID_QM_OUTFRS_DN	88
2.3.2.23	PROPID_QM_INFRS_DN	88
2.3.2.24	PROPID_QM_SERVICE_ROUTING	88
2.3.2.25	PROPID_QM_SERVICE_DSSERVER	88
2.3.2.26	PROPID_QM_SERVICE_DEPCLIENTS	88
2.3.2.27	PROPID_QM_ENCRYPTION_PK_BASE	89
2.3.2.28	PROPID_QM_ENCRYPTION_PK_ENHANCED	89
2.3.2.29	PROPID_QM_PATHNAME_DNS	89
2.3.2.30	PROPID_QM_OBJ_SECURITY	89
2.3.2.31	PROPID_QM_SECURITY_INFORMATION	89
2.3.2.32	PROPID_QM_ENCRYPT_PKS	89
2.3.2.33	PROPID_QM_SIGN_PKS	90
2.3.2.34	PROPID_QM_OWNER_SID	90
2.3.2.35	PROPID_QM_GROUP_IN_CLUSTER	90
2.3.2.36	PROPID_QM_SECURITY	90
2.3.2.37	PROPID_QM_SIGN_PK	91
2.3.2.38	PROPID_QM_ENCRYPT_PK	91
2.3.2.39	PROPID_QM_UPGRADE_DACL	91

2.3.3	Site Property Identifiers	91
2.3.3.1	PROPID_S_PATHNAME	91
2.3.3.2	PROPID_S_SITEID	91
2.3.3.3	PROPID_S_GATES	91
2.3.3.4	PROPID_S_PSC	92
2.3.3.5	PROPID_S_INTERVAL1	92
2.3.3.6	PROPID_S_INTERVAL2	92
2.3.3.7	PROPID_S_PARTITIONID	92
2.3.3.8	PROPID_S_SEQNUM	92
2.3.3.9	PROPID_S_FULL_NAME	92
2.3.3.10	PROPID_S_NT4_STUB	93
2.3.3.11	PROPID_S_FOREIGN	93
2.3.3.12	PROPID_S_DONOTHING	93
2.3.3.13	PROPID_S_SECURITY	93
2.3.3.14	PROPID_S_PSC_SIGNPK	94
2.3.3.15	PROPID_S_SECURITY_INFORMATION	94
2.3.4	Connected Network Property Identifiers	94
2.3.4.1	PROPID_CN_PROTOCOLID	94
2.3.4.2	PROPID_CN_NAME	94
2.3.4.3	PROPID_CN_GUID	94
2.3.4.4	PROPID_CN_PARTITIONID	95
2.3.4.5	PROPID_CN_SEQNUM	95
2.3.4.6	PROPID_CN_SECURITY	95
2.3.5	Enterprise Object Property Identifiers	95
2.3.5.1	PROPID_E_NAME	95
2.3.5.2	PROPID_E_NAMESTYLE	95
2.3.5.3	PROPID_E_CSP_NAME	96
2.3.5.4	PROPID_E_PECNAME	96
2.3.5.5	PROPID_E_S_INTERVAL1	96
2.3.5.6	PROPID_E_S_INTERVAL2	96
2.3.5.7	PROPID_E_PARTITIONID	96
2.3.5.8	PROPID_E_SEQNUM	96
2.3.5.9	PROPID_E_ID	97
2.3.5.10	PROPID_E_CRL	97
2.3.5.11	PROPID_E_CSP_TYPE	97
2.3.5.12	PROPID_E_ENCRYPT_ALG	97
2.3.5.13	PROPID_E_SIGN_ALG	97
2.3.5.14	PROPID_E_HASH_ALG	97
2.3.5.15	PROPID_E_LONG_LIVE	97
2.3.5.16	PROPID_E_VERSION	98
2.3.5.17	PROPID_E_SECURITY	98
2.3.5.18	PROPID_E_CIPHER_MODE	98
2.3.6	User Object Property Identifiers	98
2.3.6.1	PROPID_U_SID	98
2.3.6.2	PROPID_U_PARTITIONID	98
2.3.6.3	PROPID_U_SEQNUM	99
2.3.6.4	PROPID_U_SIGN_CERT	99
2.3.6.5	PROPID_U_DIGEST	99
2.3.6.6	PROPID_U_ID	99
2.3.7	Routinglink Property Identifiers	99
2.3.7.1	PROPID_L_NEIGHBOR1	99
2.3.7.2	PROPID_L_NEIGHBOR2	99
2.3.7.3	PROPID_L_COST	100

2.3.7.4	PROPID_L_PARTITIONID	100
2.3.7.5	PROPID_L_SEQNUM	100
2.3.7.6	PROPID_L_ID	100
2.3.7.7	PROPID_L_GATES_DN	100
2.3.7.8	PROPID_L_NEIGHBOR1_DN	100
2.3.7.9	PROPID_L_NEIGHBOR2_DN	101
2.3.7.10	PROPID_L_DESCRIPTION	101
2.3.7.11	PROPID_L_FULL_PATH	101
2.3.7.12	PROPID_L_ACTUAL_COST	101
2.3.7.13	PROPID_L_GATES	101
2.3.8	Settings Property Identifiers	101
2.3.8.1	PROPID_SET_NAME	102
2.3.8.2	PROPID_SET_SERVICE	102
2.3.8.3	PROPID_SET_QM_ID	102
2.3.8.4	PROPID_SET_FULL_PATH	102
2.3.8.5	PROPID_SET_NT4	102
2.3.8.6	PROPID_SET_PARTITIONID	103
2.3.8.7	PROPID_SET_SITENAME	103
2.3.8.8	PROPID_SET_SERVICE_ROUTING	103
2.3.8.9	PROPID_SET_SERVICE_DSSERVER	103
2.3.8.10	PROPID_SET_SERVICE_DEPCLIENTS	104
2.3.8.11	PROPID_SET_OLDSERVICE	104
2.3.9	MQUUser Property Identifiers	104
2.3.9.1	PROPID_MQU_SID	104
2.3.9.2	PROPID_MQU_SIGN_CERT	104
2.3.9.3	PROPID_MQU_DIGEST	105
2.3.9.4	PROPID_MQU_ID	105
2.3.9.5	PROPID_MQU_SECURITY	105
2.3.10	Computer Property Identifiers	105
2.3.10.1	PROPID_COM_FULL_PATH	105
2.3.10.2	PROPID_COM_SAM_ACCOUNT	105
2.3.10.3	PROPID_COM_ACCOUNT_CONTROL	106
2.3.10.4	PROPID_COM_DNS_HOSTNAME	106
2.3.10.5	PROPID_COM_SID	106
2.3.10.6	PROPID_COM_SIGN_CERT	106
2.3.10.7	PROPID_COM_DIGEST	106
2.3.10.8	PROPID_COM_ID	106
2.3.11	Management Machine Property Identifiers	107
2.3.11.1	PROPID_MGMT_MSMQ_ACTIVEQUEUES	107
2.3.11.2	PROPID_MGMT_MSMQ_PRIVATEQ	107
2.3.11.3	PROPID_MGMT_MSMQ_DSSERVER	107
2.3.11.4	PROPID_MGMT_MSMQ_CONNECTED	107
2.3.11.5	PROPID_MGMT_MSMQ_TYPE	108
2.3.11.6	PROPID_MGMT_MSMQ_BYTES_IN_ALL_QUEUES	108
2.3.12	Management Queue Property Identifiers	108
2.3.12.1	PROPID_MGMT_QUEUE_PATHNAME	108
2.3.12.2	PROPID_MGMT_QUEUE_FORMATNAME	108
2.3.12.3	PROPID_MGMT_QUEUE_TYPE	108
2.3.12.4	PROPID_MGMT_QUEUE_LOCATION	109
2.3.12.5	PROPID_MGMT_QUEUE_XACT	109
2.3.12.6	PROPID_MGMT_QUEUE_FOREIGN	109
2.3.12.7	PROPID_MGMT_QUEUE_MESSAGE_COUNT	110
2.3.12.8	PROPID_MGMT_QUEUE_BYTES_IN_QUEUE	110

2.3.12.9	PROPID_MGMT_QUEUE_JOURNAL_MESSAGE_COUNT	110
2.3.12.10	PROPID_MGMT_QUEUE_BYTES_IN_JOURNAL	110
2.3.12.11	PROPID_MGMT_QUEUE_STATE	110
2.3.12.12	PROPID_MGMT_QUEUE_NEXTHOPS	111
2.3.12.13	PROPID_MGMT_QUEUE_EOD_LAST_ACK	111
2.3.12.14	PROPID_MGMT_QUEUE_EOD_LAST_ACK_TIME	112
2.3.12.15	PROPID_MGMT_QUEUE_EOD_LAST_ACK_COUNT	112
2.3.12.16	PROPID_MGMT_QUEUE_EOD_FIRST_NON_ACK	112
2.3.12.17	PROPID_MGMT_QUEUE_EOD_LAST_NON_ACK	112
2.3.12.18	PROPID_MGMT_QUEUE_EOD_NEXT_SEQ	112
2.3.12.19	PROPID_MGMT_QUEUE_EOD_NO_READ_COUNT	112
2.3.12.20	PROPID_MGMT_QUEUE_EOD_NO_ACK_COUNT	113
2.3.12.21	PROPID_MGMT_QUEUE_EOD_RESEND_TIME	113
2.3.12.22	PROPID_MGMT_QUEUE_EOD_RESEND_INTERVAL	113
2.3.12.23	PROPID_MGMT_QUEUE_EOD_RESEND_COUNT	113
2.3.12.24	PROPID_MGMT_QUEUE_EOD_SOURCE_INFO	113
2.3.12.25	PROPID_MGMT_QUEUE_CONNECTION_HISTORY	114
2.3.12.26	PROPID_MGMT_QUEUE_SUBQUEUE_COUNT	116
2.3.12.27	PROPID_MGMT_QUEUE_SUBQUEUE_NAMES	116
2.3.13	Deletion Notification Property Identifiers	116
2.3.13.1	PROPID_D_SEQNUM	116
2.3.13.2	PROPID_D_PARTITIONID	116
2.3.13.3	PROPID_D_SCOPE	116
2.3.13.4	PROPID_D_OBJTYPE	116
2.3.13.5	PROPID_D_IDENTIFIER	117
2.4	Error Codes	117
2.5	Message Properties for Digital Signatures	127
2.5.1	MSMQ 1.0 Digital Signature Properties	127
2.5.2	MSMQ 2.0 Digital Signature Properties	127
2.5.3	MSMQ 3.0 Digital Signature Properties	128
3	Appendix A: PROPVARIANT IDL	129
4	Appendix B: Product Behavior	132
5	Change Tracking	136
6	Index	138

1 Introduction

Message Queuing (MSMQ): Data Structures contains common definitions and data structures that are used in various protocols in the set of **Microsoft Message Queuing** protocols. The documentation for individual protocols contains references to this document, as needed.

1.1 Glossary

The following terms are defined in [\[MS-GLOS\]](#):

Active Directory
distinguished name (DN)
Domain Name System (DNS)
fully qualified domain name (FQDN) (1)
globally unique identifier (GUID)
Interface Definition Language (IDL)
Lightweight Directory Access Protocol (LDAP)
little-endian
Microsoft Interface Definition Language (MIDL)
NULL GUID
Remote Access Service (RAS) server
remote procedure call (RPC)
RPC protocol sequence
RPC transfer syntax
security descriptor
security identifier (SID)
Unicode
universally unique identifier (UUID)

The following terms are specific to this document:

active queue: A **queue** that contains **messages** or is currently opened by an **application**.
Active queues may be **public queues**, **private queues**, or **outgoing queues**.

administration queue: A messaging **queue** that receives **Message Queuing (MSMQ)** system-generated acknowledgment **messages**. An administration queue is available to MSMQ applications for checking **message** status.

application: See Message Queuing application.

application protocol: A protocol that is used by **applications** to communicate with **queue managers**. **Application protocols** include the Message Queuing (MSMQ): Queue Manager Client Protocol [\[MS-MQMP\]](#), the Message Queuing (MSMQ): Queue Manager Management Protocol [\[MS-MQMR\]](#) and the Message Queuing (MSMQ): ActiveX Client Protocol [\[MC-MQAC\]](#).

Backup Site Controller (BSC): An **MSMQ Directory Service** role played by an **MSMQ queue manager**. A BSC contains a read-only copy of the directory for a **site**. A BSC may satisfy directory lookup requests but cannot satisfy directory change requests. There may be zero or more BSCs in a **site**.

connected network: A network of computers in which any two computers can communicate directly through a common transport protocol (for example, TCP/IP or SPX/IPX). A computer can belong to multiple connected networks.

ConnectedNetworkID: A **GUID** that has been assigned to a particular **MSMQ Connected Network** and that is unique to that **Connected Network**.

connector application: An application that runs on a **connector server** and translates both outgoing and incoming **messages** sent between a **Message Queuing** computer and a foreign messaging system.

connector queue: A **queue** used by a **connector server**. **Messages** sent to **foreign queues** are temporarily stored in a **connector queue** before they are retrieved by the **connector application**.

connector server: A **Message Queuing routing server** that is configured to send **messages** between a **Message Queuing site** and one or more foreign sites. A **connector server** has a **connector application** running on it and two **connector queues** for each foreign site: one used for **transactional messages** and one used for **nontransactional messages**.

cursor: A data structure providing sequential access over a **message queue**. A cursor has a current pointer that lies between the head and tail pointer of the **queue**. The pointer can be moved forward or backward through an operation on the cursor (Next). A **message** at the current pointer can be accessed through a nondestructive read (Peek) operation or a destructive read (Receive) operation.

dead-letter queue: A **queue** that contains **messages** that were sent from a host with a request for negative source journaling and that could not be delivered. **Message Queuing** provides a transactional dead-letter queue and a non-transactional dead-letter queue.

direct format name: A name that is used to reference a **public queue** or a **private queue** without accessing the **MSMQ Directory Service**. Message Queuing can use the physical, explicit location information provided by direct format names to send **messages** directly to their destinations. For more information, see section [2.1](#).

directory service: An entity that maintains a collection of objects. These objects can be remotely manipulated either by the Message Queuing (MSMQ): Directory Service Protocol, as specified in [\[MS-MQDS\]](#), or by the Lightweight Directory Access Protocol (v3), as specified in [\[RFC2251\]](#).

distribution list: An **Active Directory** object that can contain explicit references only to destinations published in **Active Directory**; that is, to **public queues**, **queue aliases**, and other distribution lists, but not to private and URL-named queues.

enterprise: A unit of administration of a network of **MSMQ queue managers**. An enterprise consists of an **MSMQ Directory Service**, one or more **connected networks** and one or more **MSMQ sites**.

EnterpriseID: A **GUID** that has been assigned to a particular **MSMQ enterprise** and is unique to that **enterprise**.

enterprise site: An **MSMQ site** that has a **Primary Enterprise Controller** as its **Primary Site Controller**.

exactly once: A **message** delivery assurance that requires that the **Message Queuing** system will deliver the **message** to the destination once and only once, such that each sent **message** is either delivered once to the destination or an error is raised.

external transaction: An atomic transaction context dispensed by a transaction coordinator other than an **MSMQ queue manager**, such as by a distributed transaction coordinator

(DTC), and used by an **MSMQ queue manager** to coordinate its state changes with state changes in other resource managers. For more information, see [\[MS-DTCO\]](#).

foreign queue: A messaging queue that resides on a computer that does not run an **MSMQ** messaging application.

foreign site: A site that contains messaging applications that are not based on MSMQ.

format name: A name used to reference a **queue** when making calls to API functions.

GUID_NULL: The **GUID** {00000000-0000-0000-0000-000000000000}.

internal transaction: An atomic transaction context dispensed by an **MSMQ Queue Manager** instance that can be used to atomically commit or rollback state changes within that **MSMQ Queue Manager**. The dispensing **MSMQ Queue Manager** instance is the transaction coordinator and is also the only resource manager participant supported by the transaction context. An internal transaction cannot, therefore, be used to coordinate state changes with other resource managers, including other **MSMQ Queue Manager** instances.

local queue: For a **queue manager**, a **queue** hosted by the **queue manager** itself. For an **application**, a **queue** hosted by the **queue manager** with which the **application** communicates.

management application: An **MSMQ application** that performs management operations, as specified in [MS-MQMR].

message: A data structure representing a unit of data transfer between distributed applications. A message has **message properties**, which may include message header properties, a **message body** property, and message trailer properties.

message body: A distinguished **message property** that represents the application payload.

message header: See **message packet header**.

message packet: A byte buffer that is the physical representation of the **message** in the **queue manager** and on the wire.

message packet header: The set of **message properties** in a **message packet** that precedes the **message body** property. Also called a **message header**.

message packet trailer: The set of **message properties** in a **message packet** that follows the **message body** property. Also called a **message trailer**.

message property: A data structure that contains a **property identifier** and a value, and that is associated with a **message**.

message queue: A data structure containing an ordered list of zero or more **messages**. A **queue** has a head and a tail and supports a first in, first out (FIFO) access pattern. **Messages** are appended to the tail through a write operation (Send) that appends the **message** and increments the tail pointer. **Messages** are consumed from the head through a destructive read operation (Receive) that deletes the **message** and increments the head pointer. A **message** at the head may also be read through a nondestructive read operation (Peek).

message queuing: See **Microsoft Message Queuing (MSMQ)**.

Message Queuing application: An application that communicates with the **queue manager** over one of the **application protocols**.

Message Queuing Information Store (MQIS): The directory service store used by **MSMQ Directory Service**.

message trailer: See **message packet trailer**.

Message Transfer Protocol: A Message Transfer Protocol defines a mechanism for reliably transferring **messages** between two **message queues** located on two different hosts.

Microsoft Message Queuing (MSMQ): A communications service that provides asynchronous and reliable **message** passing between distributed **applications**. In **Message Queuing**, **applications** send **messages** to **queues** and consume **messages** from **queues**. The **queues** provide persistence of the **messages**, enabling the sending and receiving **applications** to operate asynchronously from one another.

MSMQ: See **Microsoft Message Queuing (MSMQ)**.

MSMQ 1.0 digital signature: A digital signature based on a hash of the [MSMQ 1.0 Digital Signature Properties \(section 2.5.1\)](#). This signature type is supported by all versions of **Message Queuing**.

MSMQ 2.0 digital signature: A digital signature that is more robust than the **MSMQ 1.0 digital signature** and is based on a hash of the [MSMQ 2.0 Digital Signature Properties \(section 2.5.2\)](#). This signature type is not supported by **MSMQ** version 1.

MSMQ 3.0 digital signature: A digital signature that is used only for **messages** sent to distribution lists or [multiple-element format names](#) and is based on a hash of the [MSMQ 3.0 Digital Signature Properties \(section 2.5.3\)](#). This signature type is not supported by **MSMQ** version 1 nor **MSMQ** version 2.

MSMQ connector server: See **connector server**.

MSMQ Directory Service: A network directory service that provides directory information, including key distribution, to **MSMQ**. It initially shipped in the Windows NT 4.0 Option Pack as part of **MSMQ**. This directory service predates and is superseded by **Active Directory (AD)**.

MSMQ Directory Service server: An **MSMQ queue manager** that provides **MSMQ Directory Service**. The server can act in either of the **MSMQ Directory Service** roles: **Primary Site Controller (PSC)** or **Backup Site Controller (BSC)**.

MSMQ management server: A role played by an **MSMQ queue manager**. An **MSMQ management server** enables management applications to perform management and administrative operations on the Message Queuing System. The Management Server operations are specified in [MS-MQMR] and [\[MS-MQCN\]](#).

MSMQ mixed-mode: When upgrading from **MSMQ 1.0** in Windows NT 4.0 to **MSMQ 2.0** in Windows 2000, a transitional mode known as mixed-mode environment is supported. Although not intended as a final deployment strategy, there is full support for this mixed-mode, which allows **MSMQ 1.0** controller servers to coexist in the same **enterprise** with **MSMQ 2.0 directory service servers**, supporting both **MSMQ 1.0** and **MSMQ 2.0** directory service clients. In mixed-mode, the **MSMQ** replication service is used to synchronize **MQIS** with **Active Directory (AD)**.

MSMQ object: Any one of the objects stored by **MSMQ** in its directory service. An object has a class name and a set of properties.

MSMQ queue manager: An **MSMQ** service hosted on a machine that provides **queued** messaging services. **Queue managers** manage **queues** deployed on the local computer and

provide asynchronous transfer of **messages** to **queues** located on other computers. A **queue manager** is identified by a **globally unique identifier (GUID)**.

MSMQ queue server: A role played by an **MSMQ queue manager**. An **MSMQ queue server** hosts **queues**, accepts **messages** from **applications**, delivers **messages** to **applications**, and transfers **messages** to other **queue managers**.

MSMQ routing link: A communication link between two sites. A routing link is represented by a routing link object in the directory service. Routing links may have associated **link costs**. Routing links with their associated costs can be used to compute lowest-cost routing paths for store-and-forward messaging.

MSMQ routing server: A role played by an **MSMQ queue manager**. An MSMQ routing server implements store and forward messaging. A routing server may provide connectivity between different **connected networks** within a **site** or may provide session concentration between **sites**.

MSMQ site: A network of computers, typically physically collocated, that have high connectivity as measured in terms of latency (low) and throughput (high). A site is represented by a site object in the directory service. An MSMQ site maps one-to-one with an **Active Directory** site when **Active Directory** provides directory services to **MSMQ**.

MSMQ site gate: An **MSMQ routing server** through which all intersite messaging traffic flows.

MSMQ supporting server: A role played by an **MSMQ queue manager**. An **MSMQ supporting server** supports **applications** to send and receive **messages** through the Message Queuing (MSMQ): Queue Manager Client Protocol [MS-MQMP].

nontransactional message: A **message** that is sent outside of a transaction.

order acknowledgment: A special acknowledgment **message** that is generated by a receiving **queue manager** to acknowledge receipt of a **message** in a **transactional queue**.

order queue: A messaging queue that is used to monitor the arrival order of **messages** that are sent as part of a transaction.

outgoing queue: A temporary internal **queue** that holds **messages** for a remote destination **queue**. The **path name** of an outgoing **queue** is identical to the **path name** of the corresponding destination **queue**. An outgoing **queue** is distinguished from its corresponding destination **queue** by the fact that the outgoing **queue** is located on the sending computer. The **format name** of an outgoing **queue** is identical to the **format name** used by the **messages** to reference the destination **queue**. Messages that reference the destination **queue** using a different **format name** are placed in a different outgoing **queue**.

path name: The path name of a **queue** includes the name of the receiving computer where the **messages** for the **queue** are stored, and an optional PRIVATE\$ key word indicating whether the **queue** is private, followed by the name of the **queue**. Path names can also refer to subqueues; for more information, see section [2.1](#).

Primary Enterprise Controller (PEC): An **MSMQ Directory Service** role played by an **MSMQ queue manager**. The PEC acts as the authority for the **enterprise** configuration information stored in the directory. There is only one PEC in an **enterprise**. The PEC also acts in the role of **Primary Site Controller (PSC)** for the **site** to which it belongs.

Primary Site Controller (PSC): An **MSMQ Directory Service** role played by an **MSMQ queue manager**. The PSC acts as the authority for the directory information for the **site** to which it

belongs. The PSC may satisfy directory lookup requests and directory change requests. There is only one PSC per **site**.

private queue: An application-defined **message queue** that is not registered in the **MSMQ Directory Service**. A private queue is deployed on a particular **queue manager**.

property identifier: A DWORD value associated with an **MSMQ object** property that defines the property type and its semantic meaning.

public queue: An application-defined **message queue** that is registered in the **MSMQ Directory Service**. A public queue may be deployed at any **queue manager**.

queue: An object that holds **messages** passed between applications or **messages** passed between **Message Queuing** and applications. In general, applications can send **messages** to queues and read **messages** from queues.

queue alias: An **Active Directory** object used to reference queues that might not be listed in **Active Directory**. Queue aliases are published in **Active Directory**.

queue journal: A **queue** that contains copies of the **messages** sent from a host when positive source journaling is requested.

queue manager: A message queuing service that manages **queues** deployed on a computer. A queue manager may also provide asynchronous transfer of **messages** to **queues** deployed on other queue managers.

queue property: A data structure that contains a **property identifier** and a value, and is associated with a **message queue**.

quota: The physical disk quota for **messages** in the **queue**.

remote queue: For a **queue manager**, a **queue** hosted by a remote **queue manager**. For an **application**, a **queue** hosted by a **queue manager** other than the one with which the **application** communicates.

remote read: The act of reading (receiving) **messages** from a **remote queue**.

routing link: See **MSMQ routing link**.

routing link cost: A value that models the relative cost of direct communication between two **MSMQ sites**.

Secure Hash Algorithm (SHA): An algorithm that computes a fixed-length digital representation of message properties of any length. Five algorithms are published by the National Institute of Standards and Technology as Federal Information Processing Standards.

SiteID: A **GUID** that has been assigned to a particular **MSMQ site** and is unique to that **site**.

SOAP Reliable Messaging Protocol (SRMP): A published specification defining an open general-purpose extension of WS-Routing that adds reliability to the Web Services Routing Protocol (WS-Routing) and to SOAP. **Message Queuing** uses this protocol to format the packets in **messages** sent over HTTP/HTTPS or to a multicast address.

subqueue: A **message queue** that is logically associated, through a naming hierarchy, with a parent **message queue**. Subqueues may be used to partition **messages** within the **queue**. For example, a **queue journal** may be a subqueue that holds a copy of each **message** consumed from its parent **queue**.

system queue: An internal **queue** that is used by the queue manager for a purpose other than holding messages destined for a remote destination **queue**.

transactional message: A **message** sent as part of a transaction. Transaction **messages** must be sent to **transactional queues**.

transactional queue: A **queue** that contains only **transactional messages**.

unit of work: A set of individual operations that **MSMQ** must successfully complete before any of the individual **MSMQ** operations can be considered complete.

workgroup mode: The operation of **message queuing** without **MSMQ Directory Service (MQDS)** integration.

XML digital signature: When authentication is requested for an HTTP **message** or a multicast **message**, which is also sent in **SRMP**, it is automatically signed using an XML digital signature. The signature value is calculated by using the SHA-1, SHA-256, or SHA-512 algorithms, encrypting the hash with the public key in the certificate attached to the **message**, and converting the result to base64 encoding. <1>

MAY, SHOULD, MUST, SHOULD NOT, MUST NOT: These terms (in all caps) are used as described in [RFC2119]. All statements of optional behavior use either MAY, SHOULD, or SHOULD NOT.

1.2 References

References to Microsoft Open Specification documents do not include a publishing year because links are to the latest version of the documents, which are updated frequently. References to other documents include a publishing year when one is available.

1.2.1 Normative References

We conduct frequent surveys of the normative references to assure their continued availability. If you have any issue with finding a normative reference, please contact dochelp@microsoft.com. We will assist you in finding the relevant information. Please check the archive site, <http://msdn2.microsoft.com/en-us/library/E4BD6494-06AD-4aed-9823-445E921C9624>, as an additional source.

[FIPS180-2] Federal Information Processing Standards Publication, "Secure Hash Standard", FIPS PUB 180-2, August 2002, <http://csrc.nist.gov/publications/fips/fips180-2/fips180-2.pdf>

[FIPS197] National Institute of Standards and Technology, "Federal Information Processing Standards Publication 197: Advanced Encryption Standard (AES)", November 2001, <http://csrc.nist.gov/publications/fips/fips197/fips-197.pdf>

[IANAIMA] Internet Assigned Numbers Authority, "Internet Multicast Addresses", March 2007, <http://www.iana.org/assignments/multicast-addresses>

[MS-ADTS] Microsoft Corporation, "[Active Directory Technical Specification](#)".

[MS-DTYP] Microsoft Corporation, "[Windows Data Types](#)".

[MS-ERREF] Microsoft Corporation, "[Windows Error Codes](#)".

[MS-MQMR] Microsoft Corporation, "[Message Queuing \(MSMQ\): Queue Manager Management Protocol Specification](#)".

[MS-MQRR] Microsoft Corporation, "[Message Queuing \(MSMQ\): Queue Manager Remote Read Protocol Specification](#)".

[MS-RDPBCGR] Microsoft Corporation, "[Remote Desktop Protocol: Basic Connectivity and Graphics Remoting Specification](#)".

[MS-SAMR] Microsoft Corporation, "[Security Account Manager \(SAM\) Remote Protocol Specification \(Client-to-Server\)](#)".

[PKCS5] RSA Laboratories, "PKCS #5: Password-Based Cryptography Standard", PKCS #5, Version 2.0, March 1999, <http://www.rsa.com/rsalabs/node.asp?id=2127>

[RFC1319] Kaliski, B., "The MD2 Message-Digest Algorithm", RFC 1319, April 1992, <http://www.ietf.org/rfc/rfc1319.txt>

[RFC1320] Rivest, R., "The MD4 Message-Digest Algorithm", RFC 1320, April 1992, <http://www.ietf.org/rfc/rfc1320.txt>

[RFC1321] Rivest, R., "The MD5 Message-Digest Algorithm", RFC 1321, April 1992, <http://www.ietf.org/rfc/rfc1321.txt>

[RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997, <http://www.rfc-editor.org/rfc/rfc2119.txt>

[RFC2268] Rivest, R., "A Description of the RC2(r) Encryption Algorithm", RFC 2268, March 1998, <http://www.ietf.org/rfc/rfc2268.txt>

[RFC3110] Eastlake III, D., "RSA/SHA-1 SIGs and RSA KEYS in the Domain Name System (DNS)", RFC 3110, May 2001, <http://www.ietf.org/rfc/rfc3110.txt>

[RFC3280] Housley, R., Polk, W., Ford, W., and Solo, D., "Internet X.509 Public Key Infrastructure Certificate and Certificate Revocation List (CRL) Profile", RFC 3280, April 2002, <http://www.ietf.org/rfc/rfc3280.txt>

[RFC3447] Jonsson, J., and Kaliski, B., "Public-Key Cryptography Standards (PKCS) #1: RSA Cryptography Specifications Version 2.1", RFC 3447, February 2003, <http://www.ietf.org/rfc/rfc3447.txt>

[RFC3986] Berners-Lee, T., Fielding, R., and Masinter, L., "Uniform Resource Identifier (URI): Generic Syntax", STD 66, RFC 3986, January 2005, <http://www.ietf.org/rfc/rfc3986.txt>

[RFC4514] Network Working Group, Zeilenga, K., Ed, "Lightweight Directory Access Protocol (LDAP): String Representation of Distinguished Names", RFC 4514, June 2006, <http://www.ietf.org/rfc/rfc4514.txt>

[RFC4516] Network Working Group, Smith, M., Ed, and Howes, T., "Lightweight Directory Access Protocol (LDAP): Uniform Resource Locator", RFC 4516, June 2006, <http://www.ietf.org/rfc/rfc4516.txt>

[RFC4757] Jaganathan, K., Zhu, L., and Brezak, J., "The RC4-HMAC Kerberos Encryption Types Used by Microsoft Windows", RFC 4757, December 2006, <http://www.ietf.org/rfc/rfc4757.txt>

1.2.2 Informative References

[MC-MQDSRP] Microsoft Corporation, "[Message Queuing \(MSMQ\): Directory Service Replication Protocol Specification](#)".

[MS-DTCO] Microsoft Corporation, "[MSDTC Connection Manager: OleTx Transaction Protocol Specification](#)".

[MS-GLOS] Microsoft Corporation, "[Windows Protocols Master Glossary](#)".

[MS-MQDS] Microsoft Corporation, "[Message Queuing \(MSMQ\): Directory Service Protocol Specification](#)".

[MS-MQQB] Microsoft Corporation, "[Message Queuing \(MSMQ\): Message Queuing Binary Protocol Specification](#)".

[MSDN-ACP] Microsoft Corporation, "Microsoft AES Cryptographic Provider", [http://msdn.microsoft.com/en-us/library/aa386979\(VS.85\).aspx](http://msdn.microsoft.com/en-us/library/aa386979(VS.85).aspx)

[MSDN-BCP] Microsoft Corporation, "Microsoft Base Cryptographic Provider", [http://msdn.microsoft.com/en-us/library/aa386980\(VS.85\).aspx](http://msdn.microsoft.com/en-us/library/aa386980(VS.85).aspx)

[MSDN-CSP] Microsoft Corporation, "Cryptographic Provider Names", <http://msdn.microsoft.com/en-us/library/aa380243.aspx>

[MSDN-MQEIC] Microsoft Corporation, "Message Queuing Error and Information Codes", <http://msdn.microsoft.com/en-us/library/ms700106.aspx>

[RFC2251] Wahl, M., Howes, T., and Kille, S., "Lightweight Directory Access Protocol (v3)", RFC 2251, December 1997, <http://www.ietf.org/rfc/rfc2251.txt>

1.3 Relationship to Protocols and Other Structures

The data types in this document are used by protocols in the set of Microsoft Message Queuing protocols.

1.4 Applicability Statement

None.

1.5 Versioning and Localization

None.

1.6 Vendor-Extensible Fields

None.

2 Definitions and Structures

This section discusses data structures that are used by various protocols in the set of Microsoft Message Queuing protocols.

2.1 MSMQ Queue Names

The following sections describe the various ways to designate Message Queuing **queues**.

2.1.1 Path Names

The path of a **public queue** consists of the name of the computer hosting the queue and the name of the queue separated by a backward slash in the form "ComputerName\QueueName". The names of **private queues** are prefixed by the string "private\$" separated by a backward slash. Thus, the path of a private queues has the form "ComputerName\private\$\QueueName". The names of system queues are prefixed by the string "system\$" separated by a semicolon. Thus, the path of a **system queue** has the form "ComputerName\system\$;QueueName".

A queue **path name** MUST conform to the following format in Augmented Backus-Naur Form (ABNF) notation.

```
QueuePathName = (Computer "\" QueueName /  
                  Computer "\"private$" QueueName /  
                  Computer "\"system$;" QueueName)  
Computer      = 1*256(VCHAR)  
VCHAR         = %x21-7E
```

For MSMQ 1.0, the format is as follows.

```
QueueName = 1*124(%x21-3A / %x3C-5B / %x5D-7f)  
           ; Exclude backslash and semicolon
```

For MSMQ 2.0–MSMQ 3.0, the format is as follows.

```
QueueName = 1*124(%x21 / %x23-2A / %x2D-3A / %x3C-5B / %x5D-7f)  
           ; Exclude backslash, semicolon, plus, comma, double quote
```

For MSMQ 4.0–MSMQ 5.0, the format is as follows.

```
QueueName = 1*124(%x21 / %x23-2A / %x2D-3A / %x3C-5B / %x5D-7f)  
           [";" Subqueue]  
  
Subqueue  = 1*32(%x21 / %x23-2A / %x2D-3A / %x3C-5B / %x5D-7f)
```

2.1.2 Direct Format Names

Direct format names are used to reference public or private queues without accessing the directory service. Message Queuing can use the information provided by direct format names to send **messages** directly to their destinations. Thus, direct format names can be used to send and receive messages in **workgroup mode**, send messages to computers on the Internet, and send messages directly to a computer.

A direct format name **MUST** conform to the following format in ABNF notation.

```
DirectName = PrivateQueuePath / PublicQueuePath / MachineQueuePath

PrivateQueuePath = "DIRECT=" Protocol ":"
                  ProtocolAddressSpecification "\PRIVATE$"
                  QueueName [";JOURNAL"]

PublicQueuePath = "DIRECT=" Protocol ":"
                 ProtocolAddressSpecification "\" QueueName
                 [";JOURNAL"]

MachineQueuePath = "DIRECT=" Protocol ":"
                  ProtocolAddressSpecification "\SYSTEM$;"
                  ("JOURNAL" / "DEADLETTER" / "DEADXACT")

Subqueue=1*32(%x21 / %x23-2A / %x2D-3A / %x3C-5B / %x5D-7f)

Protocol = "TCP" / "OS" / "HTTP" / "HTTPS" / "IPX"
```

Where:

- <QueueName> is a queue path name from [Path names \(section 2.1.1\)](#).
- <ProtocolAddressSpecification> is the protocol-specific address format as defined in the following table.

Protocol	Description	Protocol address specification
TCP	Connection-oriented TCP over IP	Internet address notation (IP address)
IPX	Connection-oriented SPX over IPX	Network number and host number (separated by a colon ":" character)
OS	Connection using the native computer-naming convention	Any computer name supported by the underlying operating system
HTTP	Connection over HTTP	ProtocolAddressSpecification = "://" Host [":" Port] "/MSMQ" Port = *(%x30-39) Where: <ul style="list-style-type: none">▪ <Host> is either a computer name supported by the

Protocol	Description	Protocol address specification
		underlying operating system or an IP address. <ul style="list-style-type: none"> If <Port> is unspecified, a default of 80 is assumed.
HTTPS	Connection over HTTPS	ProtocolAddressSpecification = "/" Host [":" Port] "/MSMQ" Port = *(%x30-39) Where <ul style="list-style-type: none"> <Host> is either a computer name supported by the underlying operating system or an IP address. If <Port> is unspecified, a default of 443 is assumed.

2.1.3 Public Format Names

Public format names and [direct format names \(section 2.1.2\)](#) are used to reference public queues. When a public format name is used, Message Queuing uses its internal routing algorithm to define the route to the destination queue.

Public format names contain the string "PUBLIC=" followed by the identifier assigned to the queue when it was created. This identifier is the **GUID** listed for the queue object in Active Directory.

A public format name MUST conform to the following format in ABNF notation.

```

PublicName = "PUBLIC=" QueueGuid

QueueGuid  = Guid

Guid       = 8HexDig %x2D 3(4HexDig %x2D) 12HexDig

HexDig     = Digit / "A" / "B" / "C" / "D" / "E" / "F"

Digit      = %x30-39

```

2.1.4 Private Format Names

Private format names are used to reference private queues. When a private format name is used, Message Queuing uses its internal routing algorithm to define the route to the destination queue.

When Message Queuing detects a private format name, it does not refer to the directory service for information about the queue. However, it does use the directory service to look up information about the computer for routing purposes.

Private format names contain the string "PRIVATE=" followed by the identifier of the computer where the queue is registered and a hexadecimal number that identifies the queue.

A private format name MUST conform to the following format in ABNF notation.

```

PrivateName = "PRIVATE=" ComputerGuid "\" 1*8HEXDIG [";JOURNAL"]

ComputerGuid = Guid

```

Where:

<Guid> is a **GUID**, as specified in section [2.1.3](#).

2.1.5 Distribution List Format Names

Distribution list format names are used to reference **distribution lists** (group objects) stored in Active Directory (as specified in [\[MS-ADTS\]](#)). Distribution list format names contain the string "DL=" followed by the distribution list identifier. This identifier is the GUID listed for the distribution list (group) object in Active Directory. The following is the general format used to reference a distribution list with optional inclusion of the Active Directory domain name.

The name **MUST** conform to the following format in ABNF notation.

```
DistributionListName = "DL=" DistributionListGuid ["@" DomainName]

DistributionListGuid = Guid

DomainName           = 1*255 (VCHAR)

VCHAR                 = %x21-7E
```

Where:

<Guid> is a **GUID**, as specified in section [2.1.3](#).

2.1.6 Machine, Connector, and Multicast Format Names

Machine format names are used to reference computer journals and **dead-letter queues** for a specific computer (for MSMQ 2.0 and MSMQ 3.0, [Direct Format Names \(section 2.1.2\)](#) also can be used for this purpose). Connector format names are used to reference the **connector queues** on a **connector server**. Multicast address format names (introduced in MSMQ 3.0) reference multiple destination queues that are addressed by an IPv4 Multicast address [\[IANA:IMA\]](#).

These names **MUST** conform to the following format in ABNF notation.

```
Machine      = "MACHINE=" Guid

Connector    = "CONNECTOR=" Guid

Multicast    = "MULTICAST=" Address

Address      = dec-octet1 "." dec-octet "." dec-octet "." dec-octet ":" Port

dec-octet    = Digit                ; 0-9
              / %x31-39 Digit        ; 10-99
              / "1" 2Digit           ; 100-199
              / "2" %x30-34 Digit     ; 200-249
              / "25" %x30-35         ; 250-255

dec-octet1    = "22" %x34-39         ; 224-229
              / "23" Digit           ; 230-239
```

```

Port      = Digit                ; 0-9
           / "1" Digit           ; 10-99
           / "1" 2Digit          ; 100-999
           / "1" 3Digit          ; 1000-9999
           / %x31-35 4Digit       ; 10000-59999
           / "6" %x30-34 3Digit   ; 60000-64999
           / "65" %x30-34 2Digit  ; 65000-65499
           / "655" %x30-32 Digit  ; 65500-65529
           / "6553" %x30-35      ; 65530-65535

Digit     = %x30-39

```

Where:

<Guid> is a [GUID](#), as specified in section [2.1.3](#).

2.1.7 Multiple-Element Format Names

A multiple-element format name is formed as a concatenation of one or more public (section [2.1.3](#)), private (section [2.1.4](#)), direct (section [2.1.2](#)), distribution list (section [2.1.5](#)), connector (section [2.1.6](#)), or multicast (section [2.1.6](#)) **format names**, separated by commas. Thus, different kinds of format names used in Message Queuing can be used together as elements of a multiple-element format name.

The following example shows a multiple-element format name that contains a direct format name, a public format name, and a distribution list format name.

```
DIRECT=ComputerAddress\QueueName,PUBLIC=QueueGUID,DL=DL_GUID
```

Note A multiple-element format name containing an element that is a public, private, or distribution list format name cannot be used when there is no access to Active Directory.

Multiple-element format names cannot contain the format names of read-only queues, such as **queue journals**, computer journals, or dead-letter queues. An error is returned if the format name of a read-only queue is included in the multiple-element format name.

The name **MUST** conform to the following format in ABNF notation.

```

MultipleElementName = FormatName *("," FormatName)

FormatName = DirectName / PublicName / PrivateName /
             DistributionListName / Connector /
             Multicast

```

2.2 Structures

2.2.1 MQDSPUBLICKEY

The MQDSPUBLICKEY structure defines a public key certificate.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
ulKeyLen																															
ulProviderLen																															
ulProviderType																															
sProviderName (variable)																															
...																															
aBuf (variable)																															
...																															

ulKeyLen (4 bytes): An unsigned 32-bit integer that MUST contain the size, in bytes, of the MQDSPUBLICKEY structure.

ulProviderLen (4 bytes): An unsigned 32-bit integer that MUST contain the size, in bytes, of the provider name, including the terminating null character.

ulProviderType (4 bytes): An unsigned 32-bit integer that MUST contain an enumerated constant for the provider-type code. The value MUST be PROV_RSA_FULL (0x00000001).

sProviderName (variable): A null-terminated **Unicode** string that contains the provider name.

aBuf (variable): A buffer that MUST contain the public key certificate formatted as specified in [\[MS-MQDS\]](#) section 2.2.18.

2.2.2 MQDSPUBLICKEYS

The MQDSPUBLICKEYS structure defines a set of [MQDSPUBLICKEY \(section 2.2.1\)](#) structures.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
ulLen																															
cNumofKeys																															
aPublicKeys (variable)																															

...

ulLen (4 bytes): An unsigned 32-bit integer that MUST contain the size, in bytes, of the MQDSPUBLICKEYS structure.

cNumofKeys (4 bytes): An unsigned 32-bit integer that MUST contain the count of MQDSPUBLICKEY (section 2.2.1) structures in the array aPublicKeys.

aPublicKeys (variable): An array of MQDSPUBLICKEY (section 2.2.1) structures.

2.2.3 SECURITY_INFORMATION

A SECURITY_INFORMATION value applies to a [SECURITY_DESCRIPTOR](#) (as specified in [\[MS-DTYP\]](#) section 2.4.6). The value is constructed from zero or more bit flags from the following table.

Value	Meaning
OWNER_SECURITY_INFORMATION 0x00000001	Owner identifier of the object
GROUP_SECURITY_INFORMATION 0x00000002	Primary group identifier
DACL_SECURITY_INFORMATION 0x00000004	Discretionary access control list (DACL) of the object
SACL_SECURITY_INFORMATION 0x00000008	System ACL of the object

This type is declared as follows:

```
typedef DWORD SECURITY_INFORMATION;
```

2.2.4 TA_ADDRESS

The **TA_ADDRESS** structure defines a single transport address of a specific type.

```
typedef struct _TA_ADDRESS {
    USHORT AddressLength;
    USHORT AddressType;
    UCHAR Address[1];
} TA_ADDRESS,
*PTA_ADDRESS;
```

AddressLength: An unsigned 16-bit integer that MUST contain the size, in bytes, of the **Address** field. The value MUST be one of the following (by address type).

Address type prefix	Value
IP_	4
IPX_	10
FOREIGN_	16

AddressType: An unsigned 16-bit integer that MUST contain one of the values in the following table.

Value	Meaning
IP_ADDRESS_TYPE 0x0001	The Address field contains a 32-bit IP address.
IP_RAS_ADDRESS_TYPE 0x0002	The Address field contains a 32-bit IP address associated with a connection that is established through a Remote Access Service (RAS) server .
IPX_ADDRESS_TYPE 0x0003	The Address field contains a 4-byte netnum followed by a 6-byte nodenum. The netnum identifies the IPX network. The nodenum represents the IPX node address.
FOREIGN_ADDRESS_TYPE 0x0005	The Address field contains the GUID of a connected network object.

Address: The array of bytes that contains the address value.

This MUST be one of the following:

- An IP address (as specified in section [2.2.4.1](#)).
- An IPX address (as specified in section [2.2.4.2](#)).
- A FOREIGN address is a **GUID** object (as specified in [\[MS-DTYP\]](#) section 2.3.2).

2.2.4.1 IP Address


The IP Address packet is a numerical representation of an IPv4 address.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
IP_Address																															

IP_Address (4 bytes): A 32-bit unsigned integer.

2.2.4.2 IPX Address

The IPX Address packet identifies a remote destination on a Novell Netware network.



2.2.5 SEQUENCE_INFO

The **SEQUENCE_INFO** structure stores the sequence information about the applicable message in a message stream sent from a given sending computer to a given destination queue.

```
typedef struct tagSEQUENCE_INFO {
    LONGLONG SeqID;
    ULONG SeqNo;
    ULONG PrevNo;
} SEQUENCE_INFO;
```


SeqID: Specifies a sequence identifier.

SeqNo: Specifies the sequence number of a message within the sequence identified by the **SeqID** member.

PrevNo: Specifies the sequence number of the message previous to the message indicated by the **SeqNo** member within the sequence identified by the **SeqID** member.

2.2.5.1 SEQUENCE_INFO (Packet)

The SEQUENCE_INFO (Packet) stores the sequence information about the applicable message in a message stream sent from a given sending computer to a given destination queue.



SeqID (8 bytes): A 64-bit signed integer that specifies a sequence identifier.

SeqNo (4 bytes): A 32-bit unsigned integer that specifies the sequence number of a message within the sequence identified by the **SeqID** field.

PrevNo (4 bytes): A 32-bit unsigned integer that specifies the sequence number of the message previous to the message indicated by the **SeqNo** field within the sequence identified by the **SeqID** field.

2.2.6 QUEUE_FORMAT_TYPE

The **QUEUE_FORMAT_TYPE** enumeration identifies the type of name format being used.

```
typedef enum __QUEUE_FORMAT_TYPE
{
    QUEUE_FORMAT_TYPE_UNKNOWN = 0,
    QUEUE_FORMAT_TYPE_PUBLIC = 1,
    QUEUE_FORMAT_TYPE_PRIVATE = 2,
    QUEUE_FORMAT_TYPE_DIRECT = 3,
    QUEUE_FORMAT_TYPE_MACHINE = 4,
    QUEUE_FORMAT_TYPE_CONNECTOR = 5,
    QUEUE_FORMAT_TYPE_DL = 6,
    QUEUE_FORMAT_TYPE_MULTICAST = 7,
    QUEUE_FORMAT_TYPE_SUBQUEUE = 8
} QUEUE_FORMAT_TYPE;
```

QUEUE_FORMAT_TYPE_UNKNOWN: The format type is unknown.

QUEUE_FORMAT_TYPE_PUBLIC: The [QUEUE_FORMAT \(section 2.2.7\)](#) structure contains a **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) that identifies a queue.

QUEUE_FORMAT_TYPE_PRIVATE: The **QUEUE_FORMAT** (section 2.2.7) structure contains an [OBJECTID](#) structure that identifies a queue.

QUEUE_FORMAT_TYPE_DIRECT: The **QUEUE_FORMAT** structure contains a direct format name string that identifies a queue.

QUEUE_FORMAT_TYPE_MACHINE: The **QUEUE_FORMAT** structure contains a **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) that identifies a queue.

QUEUE_FORMAT_TYPE_CONNECTOR: The **QUEUE_FORMAT** structure contains a **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) that identifies a connector queue. This is not supported by all protocols.

QUEUE_FORMAT_TYPE_DL: The **QUEUE_FORMAT** structure contains a **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) that identifies a distribution list (DL). This is not supported by all protocols.

QUEUE_FORMAT_TYPE_MULTICAST: The **QUEUE_FORMAT** structure contains a **MULTICAST_ID** (section [2.2.10](#)) that identifies a multicast address. This is not supported by all protocols.

QUEUE_FORMAT_TYPE_SUBQUEUE: The **QUEUE_FORMAT** structure contains a direct name string that identifies a **subqueue**.

Note **QUEUE_FORMAT_TYPE_SUBQUEUE** was introduced in MSMQ version 4.

2.2.7 QUEUE_FORMAT

The **QUEUE_FORMAT** structure describes the type of queue being managed and an identifier for that queue.

```

typedef struct __QUEUE_FORMAT {
    unsigned char m_qft;
    unsigned char m_SuffixAndFlags;
    unsigned short m_reserved;
    [switch_is(m_qft)] union {
        [case (QUEUE_FORMAT_TYPE_UNKNOWN)]
            ;
        [case (QUEUE_FORMAT_TYPE_PUBLIC)]
            GUID m_gPublicID;
        [case (QUEUE_FORMAT_TYPE_PRIVATE)]
            OBJECTID m_oPrivateID;
        [case (QUEUE_FORMAT_TYPE_DIRECT)]
            LPWSTR m_pDirectID;
        [case (QUEUE_FORMAT_TYPE_MACHINE)]
            GUID m_gMachineID;
        [case (QUEUE_FORMAT_TYPE_CONNECTOR)]
            GUID m_GConnectorID;
        [case (QUEUE_FORMAT_TYPE_DL)]
            DL_ID m_DlID;
        [case (QUEUE_FORMAT_TYPE_MULTICAST)]
            MULTICAST_ID m_MulticastID;
        [case (QUEUE_FORMAT_TYPE_SUBQUEUE)]
            wchar_t* m_pDirectSubqueueID;
    };
} QUEUE_FORMAT;

```

m_qft: The type of queue format name. It MUST be set to one of the values of [QUEUE_FORMAT_TYPE](#). It is used as a union discriminant in the **QUEUE_FORMAT** structure.

m_SuffixAndFlags: This member is broken into two subfields: **Suffix Type** is located in the 4 least-significant bits, and **Flags** is located in the 4 most-significant bits.

0	1	2	3	4	5	6	7
Flags				Suffix type			

Flags	Meaning
QUEUE_FORMAT_FLAG_NOT_SYSTEM 0x00	The specified queue is not a system queue.
QUEUE_FORMAT_FLAG_SYSTEM 0x80	The specified queue is a system queue.

Suffix type	Meaning
QUEUE_SUFFIX_TYPE_NONE 0x00	No suffix is specified. The Flags subfield MUST be set to 0x00. The m_qft member MUST NOT be set to 0x04.

Suffix type	Meaning
QUEUE_SUFFIX_TYPE_JOURNAL 0x01	A journal suffix. The Flags subfield MUST be set to 0x80. The m_qft member MUST NOT be set to 0x05, 0x06, or 0x07.
QUEUE_SUFFIX_TYPE_DEADLETTER 0x02	A dead-letter suffix. The Flags subfield MUST be set to 0x80. The m_qft member MUST NOT be set to 0x01, 0x02, 0x05, 0x06, or 0x07.
QUEUE_SUFFIX_TYPE_DEADXACT 0x03	A transacted dead-letter suffix. The Flags subfield MUST be set to 0x80. The m_qft member MUST be set to 0x03 or 0x04.
QUEUE_SUFFIX_TYPE_XACTONLY 0x04	A transaction-only suffix. The m_qft member MUST be set to 0x05.
QUEUE_SUFFIX_TYPE_SUBQUEUE 0x05	A subqueue suffix. The Flags subfield MUST be 0x00. The m_qft member MUST be set to 0x08.

m_reserved: The integer value used for padding. The client SHOULD set this value to 0. The server MUST not use it.

(unnamed union): Based on the value of **m_qft**.

m_gPublicID: A **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) of a public queue. Selected when **m_qft** is set to 0x01.

m_oPrivateID: An **OBJECTID** of a private queue; members MUST be used as specified in **OBJECTID**. Selected when **m_qft** is set to 0x02.

m_pDirectID: A direct format name (as specified in section [2.1.2](#)) with the "DIRECT=" prefix removed. It is selected when **m_qft** is set to 0x03.

m_gMachineID: The **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) of a machine. It is selected when **m_qft** is set to 0x04.

m_GConnectorID: The **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) of a connector queue. It is selected when **m_qft** is set to 0x05.

m_DIID: The identifier of a distribution list. It is selected when **m_qft** is set to 0x06.

m_MulticastID: A **MULTICAST_ID** (section [2.2.10](#)) which specifies a multicast address and port. It is selected when **m_qft** is set to 0x07.

m_pDirectSubqueueID: The identifier of a subqueue. Selected when **m_qft** is set to 0x08.

The value MUST conform to the ABNF for DirectName and contain the optional <Subqueue> element, as specified in section [2.1](#).

The full QUEUE_FORMAT IDL is specified in [\[MS-MQMR\] Appendix A \(section 6\)](#).

2.2.8 OBJECTID

The **OBJECTID** structure is used to uniquely distinguish objects of the same type within the message queuing system. The structure has two identifiers: a group identifier and an object identifier.

```
typedef struct _OBJECTID {
    GUID Lineage;
    DWORD Uniquifier;
} OBJECTID;
```

Lineage: A [GUID](#) (as specified in [\[MS-DTYP\]](#) section 2.3.2) value that identifies the group to which an object belongs. A group is a protocol-specific concept. For instance, it can be the identifier of the object owner, or it can be the identifier of the source where the objects originate.

Uniquifier: A [DWORD](#) value that identifies the object within the group.

2.2.9 DL_ID

The **DL_ID** structure defines a distribution list queue identifier.

```
typedef struct _DL_ID {
    GUID m_DlGuid;
    LPWSTR m_pwzDomain;
} DL_ID;
```

m_DlGuid: The [GUID](#) (as specified in [\[MS-DTYP\]](#) section 2.3.2) of the distribution list queue.

m_pwzDomain: The Active Directory domain of the distribution list queue. This field **MUST** be a null-terminated Unicode string.

2.2.10 MULTICAST_ID

The **MULTICAST_ID** structure defines a multicast queue identifier.

```
typedef struct _MULTICAST_ID {
    ULONG m_address;
    ULONG m_port;
} MULTICAST_ID;
```

m_address: The IP address of the queue.

m_port: The port to which the queue is attached.

2.2.11 QUEUE_SUFFIX_TYPE

The **QUEUE_SUFFIX_TYPE** enumeration defines which type of queue object is represented by the [QUEUE_FORMAT \(section 2.2.7\)](#) structure. This suffix refers to the portion of the queue path separated from the queue name by a semicolon, as specified in [Path Names \(section 2.1.1\)](#).

```
typedef enum
{
    QUEUE_SUFFIX_TYPE_NONE = 0,
    QUEUE_SUFFIX_TYPE_JOURNAL = 1,
    QUEUE_SUFFIX_TYPE_DEADLETTER = 2,
    QUEUE_SUFFIX_TYPE_DEADXACT = 3,
    QUEUE_SUFFIX_TYPE_XACTONLY = 4,
    QUEUE_SUFFIX_TYPE_SUBQUEUE = 5
} QUEUE_SUFFIX_TYPE;
```

QUEUE_SUFFIX_TYPE_NONE: There is no suffix.

QUEUE_SUFFIX_TYPE_JOURNAL: Refers to the queue journal of the queue identified by the unnamed union in the **QUEUE_FORMAT** (section 2.2.7) structure.

QUEUE_SUFFIX_TYPE_DEADLETTER: Refers to the nontransacted dead-letter queue of the computer identified by the union in the **QUEUE_FORMAT** (section 2.2.7) structure.

QUEUE_SUFFIX_TYPE_DEADXACT: Refers to the transacted dead-letter queue of the computer identified by the union in the **QUEUE_FORMAT** (section 2.2.7) structure.

QUEUE_SUFFIX_TYPE_XACTONLY: Refers to the transacted connector queue of the connector identified by the union in the **QUEUE_FORMAT** (section 2.2.7) structure.

QUEUE_SUFFIX_TYPE_SUBQUEUE: Refers to the subqueue that is the direct name identified by the union in the **QUEUE_FORMAT** (section 2.2.7) structure.

2.2.12 PROPVARIANT Type Constants

The following values are used in the discriminant field, **vt**, of the [PROPVARIANT \(section 2.2.13\)](#) type.

The PROPVARIANT (section 2.2.13) type constants are defined in the **VARENUM** enumeration, as follows:

```
typedef enum
{
    VT_EMPTY = 0,
    VT_NULL = 1,
    VT_I2 = 2,
    VT_I4 = 3,
    VT_BOOL = 11,
    VT_VARIANT = 12,
    VT_I1 = 16,
    VT_UI1 = 17,
    VT_UI2 = 18,
    VT_UI4 = 19,
    VT_I8 = 20,
    VT_UI8 = 21,
    VT_LPWSTR = 31,
    VT_BLOB = 65,
    VT_CLSID = 72,
    VT_VECTOR = 0x1000
} VARENUM;
```


VT_EMPTY: (0x0000): The type of the contained field is undefined. When this flag is specified, the PROPVARIANT (section 2.2.13) MUST NOT contain a data field.

VT_NULL: (0x0001): The type of the contained field is NULL. When this flag is specified, the PROPVARIANT (section 2.2.13) MUST NOT contain a data field.

VT_I2: (0x0002): The type of the contained field MUST be a 2-byte signed integer.

VT_I4: (0x0003): The type of the contained field MUST be a 4-byte signed integer.

VT_BOOL: (0x000B): The type of the contained field MUST be [VARIANT_BOOL \(section 2.2.14\)](#).

VT_VARIANT: (0x000C): The type of the contained field MUST be [CAPROPVARIANT \(section 2.2.16.8\)](#). It MUST appear with the bit flag VT_VECTOR.

VT_I1: (0x0010): The type of the contained field MUST be a 1-byte integer.

VT_UI1: (0x0011): The type of the contained field MUST be a 1-byte unsigned integer.

VT_UI2: (0x0012): The type of the contained field MUST be a 2-byte unsigned integer.

VT_UI4: (0x0013): The type of the contained field MUST be a 4-byte unsigned integer.

VT_I8: (0x0014): The type of the contained field MUST be an 8-byte signed integer.

VT_UI8: (0x0015): The type of the contained field MUST be an 8-byte unsigned integer.

VT_LPWSTR: (0x001F): The type of the contained field MUST be an **LPWSTR** (as specified in [\[MS-DTYP\]](#) section 2.2.35), a null-terminated Unicode string.

VT_BLOB: (0x0041): The type of the contained field MUST be a [binary large object \(BLOB\) \(section 2.2.15\)](#).

VT_CLSID: (0x0048): The type of the contained field MUST be a pointer to a **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) value.

VT_VECTOR: (0x1000): The type of the contained field MUST be combined with other values by using the bitwise OR operation to indicate a counted field. The type of the contained field MUST be a [COUNTEDARRAY \(section 2.2.16\)](#).

2.2.12.1 VARTYPE

The **VARTYPE** holds [VARENUM \(section 2.2.12\)](#) enumerated values.

This type is declared as follows:

```
typedef unsigned short VARTYPE;
```

2.2.13 PROPVARIANT

The [PROPVARIANT \(section 2.2.13.2\)](#) is a container for a union that can hold many types of data.

2.2.13.1 tag_inner_PROPVARIANT

```
typedef struct _tag_inner_PROPVARIANT {
    VARTYPE vt;
    UCHAR wReserved1;
    UCHAR wReserved2;
    ULONG wReserved3;
    [switch_is(vt)] union {
        [case(VT_EMPTY, VT_NULL)]
            ;
        [case(VT_I1)]
            CHAR cVal;
        [case(VT_UI1)]
            UCHAR bVal;
        [case(VT_I2)]
            SHORT iVal;
        [case(VT_UI2)]
            USHORT uiVal;
        [case(VT_I4)]
            LONG lVal;
        [case(VT_UI4)]
            ULONG ulVal;
        [case(VT_I8)]
            LARGE_INTEGER hVal;
        [case(VT_UI8)]
            ULARGE_INTEGER uhVal;
        [case(VT_BOOL)]
            VARIANT_BOOL boolVal;
        [case(VT_CLSID)]
            GUID* puuid;
        [case(VT_BLOB)]
            BLOB blob;
        [case(VT_LPWSTR)]
            LPWSTR pwszVal;
        [case(VT_VECTOR|VT_UI1)]
            CAUB caub;
        [case(VT_VECTOR|VT_UI2)]
            CAUI caui;
        [case(VT_VECTOR|VT_I4)]
            CAL cal;
        [case(VT_VECTOR|VT_UI4)]
            CAUL caul;
        [case(VT_VECTOR|VT_UI8)]
            CAUH cauh;
        [case(VT_VECTOR|VT_CLSID)]
            CACLSID cauuid;
        [case(VT_VECTOR|VT_LPWSTR)]
            CALPWSTR calpwstr;
        [case(VT_VECTOR|VT_VARIANT)]
            CAPROPVARIANT capropvar;
    } _varUnion;
} tag_inner_PROPVARIANT;
```

vt: MUST be set to one of the values as specified in section [2.2.12](#).

wReserved1: MAY be set to 0 and MUST be ignored by the recipient.

wReserved2: MAY be set to 0 and MUST be ignored by the recipient.

wReserved3: MAY be set to 0 and MUST be ignored by the recipient.

_varUnion: MUST contain an instance of the type according to the value in the **vt** field.

2.2.13.2 PROPVARIANT

The following is the type definition for **PROPVARIANT**.

This type is declared as follows:

```
typedef tag_inner_PROPVARIANT PROPVARIANT;
```

2.2.14 VARIANT_BOOL

The **VARIANT_BOOL** type specifies Boolean values.

The values MUST be defined as follows.

Name/value	Value	Description
VARIANT_TRUE	0xFFFF	MUST indicate a Boolean value of TRUE.
VARIANT_FALSE	0x0	MUST indicate a Boolean value of FALSE.

This type is declared as follows:

```
typedef short VARIANT_BOOL;
```

2.2.15 BLOB

The **BLOB** structure defines a counted array of unsigned characters.

```
typedef struct tagBLOB {  
    unsigned long cbSize;  
    [size_is(cbSize)] unsigned char* pBlobData;  
} BLOB;
```

cbSize: A 32-bit unsigned integer that specifies the size of the array of unsigned characters pointed to by **pBlobData**.

pBlobData: An array of 8-bit unsigned characters.

2.2.16 COUNTEDARRAY

A COUNTEDARRAY specifies a counted array of types.

2.2.16.1 CAUB

The **CAUB** structure defines a counted array of unsigned characters.

```
typedef struct tagCAUB {
    unsigned long cElems;
    [size_is(cElems)] unsigned char* pElems;
} CAUB;
```

cElems: MUST be set to the total number of elements of the array.

pElems: An array of unsigned characters.

2.2.16.2 CAUI

The **CAUI** structure defines a counted array of unsigned short integers.

```
typedef struct tagCAUI {
    unsigned long cElems;
    [size_is(cElems)] unsigned short* pElems;
} CAUI;
```

cElems: MUST be set to the total number of elements of the array.

pElems: An array of unsigned short integers.

2.2.16.3 CAL

The **CAL** structure defines a counted array of 32-bit unsigned integers.

```
typedef struct tagCAL {
    unsigned long cElems;
    [size_is(cElems)] long* pElems;
} CAL;
```

cElems: MUST be set to the total number of elements of the array.

pElems: An array of 32-bit unsigned integers.

2.2.16.4 CAUL

The **CAUL** structure defines a counted array of 32-bit unsigned integers.

```
typedef struct tagCAUL {
    unsigned long cElems;
    [size_is(cElems)] unsigned long* pElems;
} CAUL;
```

cElems: MUST be set to the total number of elements of the array.

pElems: An array of 32-bit unsigned integers.

2.2.16.5 CAUH

The **CAUH** structure defines a counted array of [ULARGE_INTEGER \(section 2.2.17\)](#) values.

```
typedef struct tagCAUH {  
    unsigned long cElems;  
    [size_is(cElems)] ULARGE_INTEGER* pElems;  
} CAUH;
```

cElems: MUST be set to the total number of elements of the array.

pElems: An array of **ULARGE_INTEGER** (section 2.2.17) values.

2.2.16.6 CACLSID

The **CACLSID** structure defines a counted array of **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) values.

```
typedef struct tagCACLSID {  
    unsigned long cElems;  
    [size_is(cElems)] GUID* pElems;  
} CACLSID;
```

cElems: MUST be set to the total number of elements of the array.

pElems: An array of **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) values.

2.2.16.7 CALPWSTR

The **CALPWSTR** structure defines a counted array of **LPWSTR** (as specified in [\[MS-DTYP\]](#) section 2.2.35) values.

```
typedef struct tagCALPWSTR {  
    unsigned long cElems;  
    [size_is(cElems)] LPWSTR* pElems;  
} CALPWSTR;
```

cElems: MUST be set to the total number of elements of the array.

pElems: An array of **LPWSTR** (as specified in [\[MS-DTYP\]](#) section 2.2.35) values.

2.2.16.8 CAPROPVARIANT

The **CAPROPVARIANT** structure defines a counted array of [PROPVARIANT \(section 2.2.13.2\)](#) values.

```
typedef struct tagCAPROPVARIANT {  
    unsigned long cElems;
```

```

    [size_is(cElems )] PROPVARIANT* pElems;
} CAPROPVARIANT;

```

cElems: MUST be set to the total number of elements of the array.

pElems: An array of **PROPVARIANT** (section 2.2.13.2) values.

2.2.17 ULARGE_INTEGER

The **ULARGE_INTEGER** structure defines a large integer.

```

typedef struct _ULARGE_INTEGER {
    ULONGLONG QuadPart;
} ULARGE_INTEGER;

```

QuadPart: A **ULONGLONG** (as specified in [\[MS-DTYP\]](#) section 2.2.54) value.

2.2.18 Common Packet Syntax

Multiple MSMQ protocols share the packet syntax that is defined in the following sections.

The protocols that consume this packet syntax use **little-endian** byte order.

2.2.18.1 Packet Data Types

The following data types are used for describing the common packet syntax.


2.2.18.1.1 GUID

This specification uses the globally unique identifier data type (the **GUID** data type), as specified in [\[MS-DTYP\]](#) section 2.3.2.

2.2.18.1.2 TxSequenceID

A TxSequenceID is a 64-bit value that identifies a sequence of **transactional messages** originated from a **queue manager**. This structure contains two monotonically increasing numeric values.

When comparing ADM elements of type TxSequenceID, the structure is treated as a 64-bit unsigned integer with **Ordinal** being the low-order bytes and **TimeStamp** being the high-order bytes.



Ordinal (4 bytes): A 32-bit unsigned integer field. This field has a valid range from 0x00000000 to 0xFFFFFFFF.

TimeStamp (4 bytes): A 32-bit unsigned integer field. This field has a valid range from 0x00000000 to 0xFFFFFFFF.

2.2.18.1.3 MessageIdentifier

A MessageIdentifier is a 20-byte identifier that uniquely identifies a message from a queue manager.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
QueueManagerGuid																															
...																															
...																															
...																															
Ordinal																															

QueueManagerGuid (16 bytes): A **GUID**, as specified in [\[MS-DTYP\]](#) section 2.3.2, that contains the identifier of the sender queue manager. This value **MUST** be the same for messages originating from the same queue manager.

Ordinal (4 bytes): A 32-bit unsigned integer ordinal value that identifies the message. This value **MUST** be unique within messages originating from the same queue manager. This field has a valid range from 0x00000000 to 0xFFFFFFFF.

2.2.18.1.4 MQFFormatNameElement

The MQFFormatNameElement specifies a queue format name.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
FormatType																FormatName (variable)															
...																															

FormatType (2 bytes): A 16-bit unsigned short integer field specifying the queue format name type. The field **MUST** be set to one of the following values.

Value	Meaning
0x0001	Public Format Name
0x0002	Private Format Name
0x0003	Direct Format Name

Value	Meaning
0x0006	Distribution List Format Name

FormatName (variable): A variable-length byte array that contains a queue format name. The layout of this field depends on the value of the **FormatType** field. There are no restrictions on the value of the padding bytes. <2> The following table lists the data structures that MUST be used as the **FormatName** field for specific **FormatType** values.

FormatType Value	Data Structure
0x0001	FormatName contains a PublicQueueFormatName structure.
0x0002	FormatName contains a PrivateQueueFormatName structure.
0x0003	FormatName contains an MQFDirectQueueFormatName structure.
0x0006	FormatName contains an MQFDistributionQueueFormatName structure.

2.2.18.1.4.1 MQFDirectQueueFormatName

If the **FormatType** field is set to 0x0003, the layout of the **FormatName** field MUST be as follows.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
DirectFormatName (variable)																															
...																															

DirectFormatName (variable): A null-terminated **WCHAR** ([\[MS-DTYP\]](#) section 2.2.59) buffer that MUST specify a queue using a **direct format name**. The size of the field is the **WCHAR** string's length in bytes. The start of this field is rounded up to the next 2-byte boundary.

2.2.18.1.4.2 MQFDistributionQueueFormatName

If the **FormatType** field is set to 0x0006, then the layout of the **FormatName** field MUST be as follows.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
DistributionListIdentifier																															
...																															
...																															
...																															


DistributionListIdentifier (16 bytes): A **GUID**, as specified in [\[MS-DTYP\]](#) section 2.3.2, that MUST identify a distribution list. The start of this field is rounded up to the next 4-byte boundary.

2.2.18.1.5 Queue Format Type

The Queue Format Type specifies the layout of the queue name as indicated by the **UserHeader.Flags.DQ**, **UserHeader.Flags.AQ**, and **UserHeader.Flags.RQ** fields (section [2.2.19.2](#)) and is one of the types specified in sections [2.2.18.1.5.1](#) and [2.2.18.1.5.2](#).

2.2.18.1.5.1 PrivateQueueFormatNameId


The layout of the PrivateQueueFormatNameId queue format type MUST be as follows.



PrivateQueueIdentifier (4 bytes): A 32-bit unsigned integer that identifies the private queue on the host queue manager. This value MUST be unique for private queues hosted on the same queue manager.

2.2.18.1.5.2 DirectQueueFormatName

The layout of the DirectQueueFormatName queue format type MUST be as follows.



Count (2 bytes): A 16-bit unsigned integer that specifies the length, in bytes, of the following null-terminated **WCHAR** buffer, **DirectFormatName**, up to and including the terminating null character.

DirectFormatName (variable): A null-terminated **WCHAR**, as specified in [\[MS-DTYP\]](#) section 2.2.59, buffer that contains a direct format name. The end of this field is padded up to the next 4-byte boundary relative to the start of the header that contains the queue format name.

The **Count** value does not include the padding bytes. There are no restrictions on the value of the padding bytes. [<3>](#)

2.2.18.1.6 Message Class Identifiers

A message class identifier is used to indicate the type of a message. In some cases the class identifier can also indicate that the message is generated as a response to an action on another message such as its receipt by a higher-layer messaging application or a delivery failure. This other message is referred to as the original message in the text that follows. The sender of the original message is referred to as the original sender in the text that follows.

The **MESSAGE_CLASS_VALUES** enumeration identifies the predefined message types.

Alternatively, the sending application can set the type of a message to a custom value by setting one or more bits of the mask 0xE1FF and by leaving the remaining bits as zero.

```
typedef enum
{
    MQMSG_CLASS_NORMAL = 0x0000,
    MQMSG_CLASS_REPORT = 0x0001,
    MQMSG_CLASS_ACK_REACH_QUEUE = 0x0002,
    MQMSG_CLASS_ORDER_ACK = 0x00ff,
    MQMSG_CLASS_ACK_RECEIVE = 0x4000,
    MQMSG_CLASS_NACK_BAD_DST_Q = 0x8000,
    MQMSG_CLASS_NACK_DELETED = 0x8001,
    MQMSG_CLASS_NACK_REACH_QUEUE_TIMEOUT = 0x8002,
    MQMSG_CLASS_NACK_Q_EXCEED_QUOTA = 0x8003,
    MQMSG_CLASS_NACK_ACCESS_DENIED = 0x8004,
    MQMSG_CLASS_NACK_HOP_COUNT_EXCEEDED = 0x8005,
    MQMSG_CLASS_NACK_BAD_SIGNATURE = 0x8006,
    MQMSG_CLASS_NACK_BAD_ENCRYPTION = 0x8007,
    MQMSG_CLASS_NACK_NOT_TRANSACTIONAL_Q = 0x8009,
    MQMSG_CLASS_NACK_NOT_TRANSACTIONAL_MSG = 0x800A,
    MQMSG_CLASS_NACK_UNSUPPORTED_CRYPTO_PROVIDER = 0x800B,
    MQMSG_CLASS_NACK_Q_DELETED = 0xC000,
    MQMSG_CLASS_NACK_Q_PURGED = 0xC001,
    MQMSG_CLASS_NACK_RECEIVE_TIMEOUT = 0xC002,
    MQMSG_CLASS_NACK_RECEIVE_REJECTED = 0xC004
} MESSAGE_CLASS_VALUES;
```

MQMSG_CLASS_NORMAL: Indicates the original message sent on behalf of a higher-layer messaging application.

MQMSG_CLASS_REPORT: Indicates a report message used to track delivery of sent messages. For more information, see [\[MS-MQOB\]](#) section 3.1.5.8.9.

MQMSG_CLASS_ACK_REACH_QUEUE: The class is used by administration acknowledgment messages.

Indicates that the original message was delivered to its destination queue.

MQMSG_CLASS_ORDER_ACK: The class is used to acknowledge in-order receipt of an original transactional message. This acknowledgment **MUST** be sent from the final destination queue manager to the original sender.

MQMSG_CLASS_ACK_RECEIVE: The class is used by administration acknowledgment messages.

Indicates that the original message was retrieved by a receiving application from the destination queue.

MQMSG_CLASS_NACK_BAD_DST_Q: Indicates that the destination queue is not available to the original sender.

MQMSG_CLASS_NACK_DELETED: Indicates that the original message was deleted by an administrative action before reaching the destination queue.

MQMSG_CLASS_NACK_REACH_QUEUE_TIMEOUT: Indicates that the original message did not reach the destination queue. This message can be generated by expiration of either the `UserMessage.UserHeader.TimeToBeReceived` time or `UserMessage.BaseHeader.TimeToReachQueue` time before the original message reaches the destination queue.

MQMSG_CLASS_NACK_Q_EXCEED_QUOTA: Indicates that the original message was rejected by the destination queue manager because the destination queue exceeded **Quota**.

MQMSG_CLASS_NACK_ACCESS_DENIED: Indicates that the access rights for placing the original message in the destination queue were not allowed for the sender.

MQMSG_CLASS_NACK_HOP_COUNT_EXCEEDED: Indicates that the original message was rejected because it exceeded the maximum routing hop count.

MQMSG_CLASS_NACK_BAD_SIGNATURE: Indicates that the digital signature attached to the original message is not valid.

MQMSG_CLASS_NACK_BAD_ENCRYPTION: Indicates that the destination queue manager could not decrypt the original message.

MQMSG_CLASS_NACK_NOT_TRANSACTIONAL_Q: Indicates that the original transactional message was sent to a nontransactional queue.

MQMSG_CLASS_NACK_NOT_TRANSACTIONAL_MSG: Indicates that the original **nontransactional message** was sent to a **transactional queue**.

MQMSG_CLASS_NACK_UNSUPPORTED_CRYPTO_PROVIDER: Indicates that the encryption provider requested in the original message is not supported by the destination.

MQMSG_CLASS_NACK_Q_DELETED: Indicates that the queue was deleted before the original message could be read from the queue.

MQMSG_CLASS_NACK_Q_PURGED: Indicates that the queue was purged and the original message no longer exists.

MQMSG_CLASS_NACK_RECEIVE_TIMEOUT: Indicates that the original message was placed in the destination queue but was not retrieved from the queue before its time-to-be-received timer expired.

MQMSG_CLASS_NACK_RECEIVE_REJECTED: Indicates that the message was rejected by a receiving application.

2.2.18.1.7 Common Queue Formats

2.2.18.1.7.1 PublicQueueFormatName

The layout of a public queue format name MUST be as follows.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
PublicQueueIdentifier																															
...																															

...
...

PublicQueueIdentifier (16 bytes): A **GUID**, as specified in [\[MS-DTYP\]](#) section 2.3.2, that MUST be set to the identifier of the public queue.

2.2.18.1.7.2 PrivateQueueFormatName

The layout of a private queue format name MUST be as follows.

0	1	2	3	4	5	6	7	8	9	10	1	2	3	4	5	6	7	8	9	20	1	2	3	4	5	6	7	8	9	30	1
SourceQueueManager																															
...																															
...																															
...																															
PrivateQueueIdentifier																															

SourceQueueManager (16 bytes): A **GUID**, as specified in [\[MS-DTYP\]](#) section 2.3.2, that MUST specify the queue manager that hosts the private queue. The start of this field is rounded up to the next 4-byte boundary.

PrivateQueueIdentifier (4 bytes): A 32-bit unsigned integer that MUST identify the private queue on the source queue manager. This value MUST be unique for private queues hosted on the same queue manager.

2.2.18.1.8 XACTUOW

An **XACTUOW** is a structure that serves as a unique identifier for a transactional **unit of work**. An **XACTUOW** contains 16 unsigned single-byte characters representing a **GUID** ([\[MS-DTYP\]](#) section 2.3.2) and is defined as follows:

```
typedef struct {
    unsigned char rgb[16];
} XACTUOW;
```

rgb: An array of unsigned single-byte characters that contains a globally unique identifier (GUID).

2.2.19 Common Headers

This section contains headers that are common to multiple packets.

2.2.19.1 BaseHeader

The BaseHeader is the first field of each packet described in this section. The BaseHeader contains information to identify and manage protocol packets.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
VersionNumber								Reserved								Flags															
Signature																															
PacketSize																															
TimeToReachQueue																															

VersionNumber (1 byte): An 8-bit unsigned integer that is the version of the packet format. This field **MUST** be set to the value 0x10.

Reserved (1 byte): Reserved for future use. This field can be set to any arbitrary value when sent and **MUST** be ignored on receipt.

Flags (2 bytes): A 16-bit unsigned short integer containing a set of options that provides additional information about the packet. Any combination of these values is acceptable unless otherwise noted in the following table.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
PR			IN		SH	DH	X9	X8	TR	X6	X5	X4	X3	X2	X1	X0															

PR (3 bits): Specifies the priority of the message in the packet. This field has a valid range from 0x0 to 0x7, with 0x7 being the highest priority. The default is 0x3. A message with a higher priority **MUST** be placed closer to the front of the queue. This field **MUST** be set to a value of 0x0 if the packet contains a transactional message. For more details, see **UserHeader.Flags.TH** in section [2.2.19.2](#).

IN (1 bit): Indicates that the message within the packet is internal and used by [message transfer protocols](#) for connection establishment and session acknowledgements. This field **MUST** be set if the packet is an EstablishConnection Packet as defined in [\[MS-MQQB\] section 2.2.3](#), a ConnectionParameters Packet as defined in [\[MS-MQQB\] section 2.2.2](#), or a SessionAck Packet as defined in [\[MS-MQQB\] section 2.2.6](#). This field **MUST NOT** be set if the packet is a OrderAck Packet as defined in [\[MS-MQQB\] sections 2.2.4](#) or a FinalAck Packet as defined in [\[MS-MQQB\] section 2.2.5](#).

SH (1 bit): Specifies if a [SessionHeader \(section 2.2.20.4\)](#) is present in the packet. If set, the packet **MUST** contain a SessionHeader.

DH (1 bit): Specifies if a [DebugHeader \(section 2.2.20.8\)](#) is present in the packet. This field **MUST NOT** be set if the BaseHeader is part of a packet other than a [UserMessage Packet \(section 2.2.20\)](#). If and only if set, **MUST** the packet include a DebugHeader.

X9 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X8 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

TR (1 bit): Specifies whether message tracing is enabled for this packet. This field MUST be set if message tracing is required for this message. If this field is set, the **DH** field MUST also be set.

X6 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X5 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X4 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X3 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X2 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X1 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X0 (1 bit): Reserved. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

Signature (4 bytes): A 32-bit unsigned integer that is the packet signature value. This field MUST be set to 0x524F494C.

PacketSize (4 bytes): A 32-bit unsigned integer that indicates the packet size. This field MUST be set to the size, in bytes, of the entire packet including the base header and any padding bytes used to align the various **message headers** on 4-byte boundaries, but MUST NOT include the SessionHeader size when the SessionHeader is present. This field has a maximum value of 0x00400000.

TimeToReachQueue (4 bytes): A 32-bit unsigned integer that indicates the length of time, in seconds, that a UserMessage Packet has to reach its destination **queue manager**. This field has a valid range from 0x00000000 to 0xFFFFFFFF. The value 0xFFFFFFFF indicates an infinite time.

When a UserMessage Packet is sent or received, this value MUST be evaluated against the current system time and the **UserMessage.UserHeader.SentTime** field. If **CURRENT_TIME - UserMessage.UserHeader.SentTime** is greater than the value of this field, then the UserMessage Packet has expired and MUST be deleted by a sender and ignored by a receiver.

When the BaseHeader is not part of a UserMessage Packet, this value MUST be set to 0xFFFFFFFF.

For the purpose of this section, **CURRENT_TIME** is defined as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 Coordinated Universal Time (UTC).

2.2.19.2 UserHeader

The `UserHeader` contains source and destination information for the message in a [UserMessage Packet](#).

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
SourceQueueManager																															
...																															
...																															
...																															
QueueManagerAddress																															
...																															
...																															
...																															
TimeToBeReceived																															
SentTime																															
MessageID																															
Flags																															
DestinationQueue (variable)																															
...																															
AdminQueue (variable)																															
...																															
ResponseQueue (variable)																															
...																															
ConnectorType (optional)																															
...																															

Value	Meaning
0x1	Recoverable messaging (including transactional). Recoverable messages MUST be recovered after queue manager restarts.

Note a transactional message is a recoverable message that has **UserHeader.Flags.TH** set to 0x1.

- X1 (1 bit):** Reserved bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.
- JN (1 bit):** Specifies if negative source journaling is enabled. [<4>](#) If set, the protocol SHOULD log a record locally in the event of message delivery failure. [<5>](#)
- JP (1 bit):** Specifies if positive source journaling is enabled. If set, the protocol SHOULD log a record locally if the message is successfully delivered. [<6>](#)
- DQ (3 bits):** Type of destination queue in **UserHeader.DestinationQueue**. The field MUST be set to 0x0, 0x3, 0x5, or 0x7. The value in this field determines the layout of the destination queue name in the **UserHeader.DestinationQueue** field.
- AQ (3 bits):** Type of **administration queue** in **UserHeader.AdminQueue**. The field MUST be set to 0x0, 0x2, 0x3, 0x5, 0x6 or 0x7. The value in this field determines the layout of the administration queue name in the **UserHeader.AdminQueue** field.
- RQ (3 bits):** Type of response queue in **UserHeader.ResponseQueue**. The field MUST be set to 0x0, 0x1, 0x2, 0x3, 0x4, 0x5, 0x6, or 0x7. The value in this field determines the layout of the response queue name in the **UserHeader.ResponseQueue** field.
- SH (1 bit):** Specifies if a [SecurityHeader](#) is present in the UserMessage Packet. If set, the packet MUST contain a SecurityHeader; otherwise, it MUST NOT.
- TH (1 bit):** Specifies if a [TransactionHeader](#) is present in the UserMessage Packet. If set, the packet MUST contain a TransactionHeader; otherwise, it MUST NOT. If this flag is set the DM flag MUST NOT be 0x0.
- MP (1 bit):** Specifies if a [MessagePropertiesHeader](#) is present in the UserMessage Packet. This flag MUST always be set.
- CQ (1 bit):** Specifies if the **ConnectorType** field is present in the packet. If set, the packet MUST contain a **ConnectorType** field; otherwise, it MUST NOT.
- MQ (1 bit):** Specifies if a [MultiQueueFormatHeader](#) is present in the UserMessage Packet. If set, the packet MUST contain a MultiQueueFormatHeader; otherwise, it MUST NOT.
- X2 (1 bit):** Reserved bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.
- AH (1 bit):** Indicates if the packet being received was originally sent over HTTP, as specified in [\[MS-MQRR\]](#) section 2.2.5.1. This field MUST NOT be set when sent.
- X3 (2 bits):** Reserved bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.
- HH (1 bit):** Specifies if a [SoapHeader](#) is present in the packet. If set, the UserMessage Packet MUST contain a SoapHeader; otherwise, it MUST NOT.

X4 (3 bits): Reserved bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

DestinationQueue (variable): The destination queue specifies the final destination of the message that is contained inside the UserMessage Packet. The queue type and data type of the destination queue name vary depending on the value specified in the **Flags.DQ** field, as described in the following table.

Flags.DQ	Queue type	Data type
0x0	None	None
0x3	Private queue on destination host	PrivateQueueFormatNameId
0x5	Public queue	PublicQueueFormatName
0x7	Direct	DirectQueueFormatName

When the **Flags.DQ** field is set to 0x03 or 0x5, the **QueueManagerAddress** field MUST be set to the **GUID** of the destination queue manager.

Any value for **Flags.DQ** other than those specified in the preceding table MUST be treated as an error by closing the session.

AdminQueue (variable): The name of the administration queue. This field specifies the response queue where administration acknowledgment messages are sent. An administration response queue MUST be specified if a MessagePropertiesHeader is included and any bits are set in the **MessagePropertiesHeader.Flags** field; otherwise, this field MUST NOT be specified. Details about administration acknowledgments are as specified in [MS-MQTB] sections [1.3.5.2](#) and [3.1.5.8.10](#). The queue type and data type of the administration queue name vary depending on the value specified in the **Flags.AQ** field, as described in the following table. This field MUST be present when the **Flags.AQ** field is set to 0x2, 0x3, 0x5, 0x6, or 0x7. This field MUST NOT be present when the **Flags.AQ** field is set to 0x0.

Flags.AQ	Queue type	Data type
0x0	None	None
0x2	Private queue on source host	PrivateQueueFormatNameId
0x3	Private queue on destination host	PrivateQueueFormatNameId
0x5	Public queue	PublicQueueFormatName
0x6	Private queue on host other than the source or destination host	PrivateQueueFormatName
0x7	Direct	DirectQueueFormatName

Any value for the **Flags.AQ** field other than those specified in the preceding table MUST be treated as an error by closing the session.

ResponseQueue (variable): A variable-length array of bytes containing the name of the response queue. The response queue is an application-defined value that specifies a queue that a receiving application could use to send a reply message. The queue type and data type of the response queue name vary depending on the queue format type specified in the **Flags.RQ** field, as described in the following table. This field MUST be present when the

Flags.RQ field is set to 0x1, 0x2, 0x3, 0x5, 0x6, or 0x7. This field MUST NOT be present when the **Flags.RQ** field is set to 0x0 or 0x1. When the **Flags.RQ** flag is set to 0x1, the response queue is the same as the administration queue. When the **Flags.RQ** field is set to 0x4, the **PrivateQueueIdentifier** in the queue format type MUST identify the private queue on the queue manager that hosts the administration queue.

Flags.RQ	Queue type	Data type
0x0	None	None
0x1	Same as the administration queue	None
0x2	Private queue on source host	PrivateQueueFormatNameId
0x3	Private queue on destination host	PrivateQueueFormatNameId
0x4	Private queue on the same host as the administration queue	PrivateQueueFormatNameId
0x5	Public queue	PublicQueueFormatName
0x6	Private queue on a host other than the source queue , destination queue , or administration queue host	PrivateQueueFormatName
0x7	Direct	DirectQueueFormatName

ConnectorType (16 bytes): An optional field that represents an application-defined **GUID**, as specified in [\[MS-DTYP\]](#) section 2.3.2. This field MUST be present if and only if the **Flags.CQ** field is set. This field is used by higher-layer messaging applications. The server MUST NOT process or interpret this field.

2.2.19.3 MessagePropertiesHeader

The MessagePropertiesHeader contains property information about a [UserMessage Packet](#) and the application-defined message payload.

0	1	2	3	4	5	6	7	8	9	10	1	2	3	4	5	6	7	8	9	20	1	2	3	4	5	6	7	8	9	30	1	
Flags									LabelLength								MessageClass															
CorrelationID																																
...																																
...																																
...																																
...																																
BodyType																																

ApplicationTag
MessageSize
AllocationBodySize
PrivacyLevel
HashAlgorithm
EncryptionAlgorithm
ExtensionSize
Label (variable)
...
ExtensionData (variable)
...
MessageBody (variable)
...

Flags (1 byte): An 8-bit unsigned integer field that specifies administration acknowledgments. Any combination of these values is acceptable unless otherwise noted in the following table.

For more details on administration acknowledgments, see [\[MS-MQOB\]](#) sections [3.1.7.2.1](#) and [3.1.5.8.10](#).

0	1	2	3	4	5	6	7
P A	P R	N A	N R	X	X	X	X

Where the bits are defined as:

Value	Description
PA	If the message is delivered to the destination queue, the server MUST send a positive acknowledgment.
PR	If the message is retrieved from the destination queue by the application, the server MUST send a positive acknowledgment.
NA	If the message is not delivered to the destination queue, the server MUST send a negative

Value	Description
	acknowledgment.
NR	If the message is not retrieved from the destination queue by the application, the server MUST send a negative acknowledgment.
X	Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.
X	Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.
X	Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.
X	Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

LabelLength (1 byte): An 8-bit unsigned integer field that MUST be set to the number of elements of **WCHAR** in the **Label** field. This field has a valid range from 0x00 to 0xFA. When the value of this field is 0x00, the **Label** field MUST NOT be present after the **ExtensionSize** field. When greater than 0x00, this value MUST include the terminating null character.

MessageClass (2 bytes): A 16-bit unsigned integer that specifies the class of the message in the packet. The value MUST be set to a value of the **MESSAGE_CLASS_VALUES** enumeration specified in section [2.2.18.1.6](#).

CorrelationID (20 bytes): If this header appears outside an administration acknowledgement message, as specified in [\[MS-MQOB\]](#) section 3.1.5.8.10, then this field MUST be treated as an application-defined buffer and the server MUST not process or interpret this field.

If this header appears inside an administration acknowledgment message, as specified in [\[MS-MQOB\]](#) section 3.1.5.8.10, then this field MUST be set to a [MessageIdentifier](#) consisting of **UserMessage.UserHeader.MessageID** and **UserMessage.UserHeader.SourceQueueManager** of the message being acknowledged. See section [2.2.18.1.3](#) for details of the MessageIdentifier type.

BodyType (4 bytes): A 32-bit unsigned integer that specifies the type of data that is contained in the **message body**. This value MUST be set to a **PROPVARIANT** type constant as specified in section [2.2.12](#).

ApplicationTag (4 bytes): A 32-bit unsigned integer that specifies an application-defined value that can be used to organize messages and the server MUST not process or interpret this field.

MessageSize (4 bytes): A 32-bit unsigned integer that MUST be set to the size, in bytes, of the **MessageBody** field. The field MUST be set to a value between 0x00000000 and the size limit imposed by the value of **BaseHeader.PacketSize**.

AllocationBodySize (4 bytes): A 32-bit unsigned integer field that MUST be set to the size, in bytes, of the data allocated for the **MessageBody** field. This size can be larger than the actual message body size; for example, an encrypted message body might be larger than the original unencrypted message body, up to the size limit imposed by the value of **BaseHeader.PacketSize**.

PrivacyLevel (4 bytes): A 32-bit unsigned integer field that specifies the privacy level of the message in the UserMessage Packet. The privacy level determines what part of the message is encrypted. The field **MUST** be set to one of the following values. <7>

Value	Meaning
0x00000000	No encryption. The MessageBody field is sent as clear text.
0x00000001	The MessageBody field is encrypted using 40-bit end-to-end encryption.
0x00000003	The MessageBody field is encrypted using 128-bit end-to-end encryption.
0x00000005	The MessageBody field is encrypted using Advanced Encryption Standard (AES).

Any value not specified in the preceding table **MUST** be treated as an authentication failure.

HashAlgorithm (4 bytes): A 32-bit unsigned integer that specifies the hashing algorithm that is used when authenticating the message. The following table lists the allowed values for this field.

Value	Meaning
0x00008001	Specifies the MD2 hash algorithm, as specified in [RFC1319] .
0x00008002	Specifies the MD4 hash algorithm, as specified in [RFC1320] .
0x00008003	Specifies the MD5 hash algorithm, as specified in [RFC1321] .
0x00008004	Specifies the SHA-1 hash algorithm, as specified in [RFC3110] .
0x0000800C	Specifies the SHA-256 hash algorithm [FIPS180-2] .
0x0000800E	Specifies the SHA-512 hash algorithm [FIPS180-2] .

Any value not specified in the preceding table **MUST** be treated as an authentication failure when the **SecurityHeader** is present in the UserMessage and the **SecurityHeader.SecurityData.Signature** field is present. The SHA-512 hash algorithm (0x0000800E) **SHOULD** be used to generate the message signature. <8>

EncryptionAlgorithm (4 bytes): A 32-bit unsigned integer that specifies the encryption algorithm used to encrypt the **MessageBody** field. This field **MUST** be set to a value in the following table.

Value	Meaning
0x00006602	Specifies the RC2 algorithm, as specified in [RFC2268] .
0x00006610	Specifies the AES 256 algorithm, as specified in [FIPS197] .
0x0000660E	Specifies the AES 128 algorithm, as specified in [FIPS197] .
0x0000660F	Specifies the AES 192 algorithm, as specified in [FIPS197] .
0x00006801	Specifies the RC4 algorithm, as specified in [RFC4757] .

Any value not specified in the preceding table MUST be treated as a failed decryption error when the **SecurityHeader** is present in the UserMessage and the **SecurityHeader.EB** flag is set.

This field MUST be set according to **PrivacyLevel** as specified in the following table.

PrivacyLevel	Allowed encryption algorithms
0x00000001	RC2, RC4
0x00000003	RC2, RC4
0x00000005	AES 128, AES 192, AES 256

When specifying AES or RC2, the initialization vector must be set to zero. The Padding used with AES or RC2 is [\[PKCS5\]](#) padding.

ExtensionSize (4 bytes): A 32-bit unsigned integer field that MUST be set to the length, in bytes, of the application-defined **ExtensionData** field. The field MUST be set to a value between 0x00000000 and the size limit imposed by the value of **BaseHeader.PacketSize**.

Label (variable): The **Label** field is an application-defined Unicode string. This field can be used by an application to assign a short descriptive string to the message. This field is of length **LabelLength** * 2 bytes and MUST NOT be more than 500 bytes. If **LabelLength** is nonzero, this field MUST be in the format specified by the following ABNF rule.

```
label = 0*249(%x0001-FFFF) 0x0000
```

If **LabelLength** is zero then this field MUST NOT be present.

Unlike the fields preceding and including the **Label** field, the **ExtensionData** and **MessageBody** fields are not guaranteed to be on 4-byte boundaries.

ExtensionData (variable): This field is a buffer containing additional application-defined information that is associated with the message. This field is of length **ExtensionSize** bytes. If **ExtensionSize** is zero then this field MUST NOT be present.

MessageBody (variable): The **MessageBody** field is a buffer containing the application-defined message payload. This field is of length **MessageSize** bytes. If **MessageSize** is zero then this field MUST NOT be present.

The MessagePropertiesHeader packet MUST be a multiple of 4 bytes in length and MUST append padding bytes needed to ensure this requirement. There are no restrictions on the value of the padding bytes. [<9>](#)

2.2.20 UserMessage Packet

A UserMessage Packet always contains an entire message. The UserMessage Packet is used to communicate application-defined and administration acknowledgment messages between a sender and receiver.

A UserMessage Packet contains a number of required headers and can contain additional optional headers. The required headers that MUST appear in all UserMessage Packets are: [BaseHeader](#), [UserHeader](#), and [MessagePropertiesHeader](#). Optional headers include: [TransactionHeader](#), [SecurityHeader](#), [DebugHeader](#), [SoapHeader](#), [MultiQueueFormatHeader](#), and [SessionHeader](#).

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
BaseHeader																															
...																															
...																															
...																															
UserHeader (variable)																															
...																															
TransactionHeader (variable)																															
...																															
SecurityHeader (variable)																															
...																															
MessagePropertiesHeader (variable)																															
...																															
DebugHeader (variable)																															
...																															
SoapHeader (variable)																															
...																															
MultiQueueFormatHeader (variable)																															
...																															
SessionHeader (optional)																															
...																															
...																															
...																															

BaseHeader (16 bytes): A [BaseHeader \(section 2.2.19.1\)](#) packet that contains information to identify and manage protocol packets. The **BaseHeader.Flags.IN** field MUST NOT be set.

UserHeader (variable): A [UserHeader \(section 2.2.19.2\)](#) packet that contains source and destination queue information.

TransactionHeader (variable): A [TransactionHeader \(section 2.2.20.5\)](#) packet that contains flags and sequence information for the packet. This header MUST be present when **UserHeader.Flags.TH** is set and MUST NOT be present if it is clear.

SecurityHeader (variable): A [SecurityHeader \(section 2.2.20.6\)](#) packet that contains security information. This header MUST be present when **UserHeader.Flags.SH** is set and MUST NOT be present if it is clear.

MessagePropertiesHeader (variable): A [MessagePropertiesHeader \(section 2.2.19.3\)](#) packet that contains property information about a UserMessage Packet and the application-defined message payload. This header MUST be present.

DebugHeader (variable): A [DebugHeader \(section 2.2.20.8\)](#) packet that specifies the queue to receive trace messages for this UserMessage Packet. This header specifies the queue where trace messages are sent. This header MUST be present if and only if **BaseHeader.Flags.DH** is set.

SoapHeader (variable): A [SoapHeader \(section 2.2.20.7\)](#) packet that contains application-defined information. This header MUST be present if and only if **UserHeader.Flags.HH** is set.

MultiQueueFormatHeader (variable): A [MultiQueueFormatHeader \(section 2.2.20.1\)](#) packet that is included when a message is destined for multiple queues. This header MUST be present if and only if **UserHeader.Flags.MQ** is set.

SessionHeader (16 bytes): A [SessionHeader \(section 2.2.20.4\)](#) packet that is used to acknowledge express and recoverable UserMessage Packets received by the **message transfer protocols**. This header MUST be present if and only if **BaseHeader.Flags.SH** is set.

2.2.20.1 MultiQueueFormatHeader

The optional MultiQueueFormatHeader is used when a message is destined for multiple queues. [<10>](#) When an application-layer message is sent using a multiple-element format name, this header is added to the packet to list the destinations. The sending queue manager creates a separate [UserMessage Packet](#) for each destination and specifies the packet address in the [UserHeader](#). The information in this header provides a list of all destinations that were sent the message in addition to associated administration and response queues.

0	1	2	3	4	5	6	7	8	9	10	1	2	3	4	5	6	7	8	9	20	1	2	3	4	5	6	7	8	9	30	1
Destination (variable)																															
...																															
Administration (variable)																															
...																															

Response (variable)
...
Signature (variable)
...

Destination (variable): An [MQFAddressHeader](#) that specifies the name of one or more destination queues. This field **MUST** contain the list of all queues that were sent a copy of this UserMessage Packet. The end of this field is rounded up to the next 4-byte boundary. There are no restrictions on the value of the padding bytes. [<11>](#)

Administration (variable): An [MQFAddressHeader](#) that specifies the name of one or more administration queues that can receive positive and negative acknowledgement messages. The end of this field is rounded up to the next 4-byte boundary. There are no restrictions on the value of the padding bytes. [<12>](#)

Response (variable): An [MQFAddressHeader](#) that specifies the name of one or more response queues that can receive response messages from the receivers at the destinations. The end of this field is rounded up to the next 4-byte boundary. There are no restrictions on the value of the padding bytes. [<13>](#)

Signature (variable): An [MQFSignatureHeader](#) that specifies a signature for the packet.

2.2.20.2 MQFAddressHeader

The MQFAddressHeader is used to specify multiple destination queue format names.

0	1	2	3	4	5	6	7	8	9	10	1	2	3	4	5	6	7	8	9	20	1	2	3	4	5	6	7	8	9	30	1
HeaderSize																															
HeaderID																Reserved															
ElementCount																															
FormatNameList (variable)																															
...																															

HeaderSize (4 bytes): A 32-bit unsigned integer that specifies the size of the header. This value **MUST** contain the size, in bytes, of this header including the variable data. This field has a valid range between 0x0000000C and the size limit imposed by the value of **BaseHeader.PacketSize**.

HeaderID (2 bytes): A 16-bit unsigned integer that specifies an identifier for this header. This field **MUST** be set to one of the following values based on the header designation:

Value	Meaning
0x0064	Destination
0x00C8	Admin
0x012C	Response
0x015E	Signature

Reserved (2 bytes): A 16-bit unsigned integer field that is reserved for alignment. The sender SHOULD set this field to 0x0000, and the receiver MUST ignore it on receipt.

ElementCount (4 bytes): A 32-bit unsigned integer field that MUST be set to the number of elements in the **FormatNameList** field. This field has a valid range between 0x00000000 and the size limit imposed by the value of **BaseHeader.PacketSize**.

FormatNameList (variable): An [MQFFormatNameElement](#) that contains a list of queue format names. This field MUST contain a list of MQFFormatNameElement data structures. The array MUST contain the number of elements specified by the **ElementCount** field. The end of this field is rounded up to the next 4-byte boundary. Padding bytes in this field MAY be any value. [<14>](#)

2.2.20.3 MQFSignatureHeader

The MQFSignatureHeader is a signature used in the [MultiQueueFormatHeader](#).

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
ID																Reserved															
Size																															
Signature (variable)																															
...																															

ID (2 bytes): A 16-bit unsigned short integer value that MUST be set to 0x015E.

Reserved (2 bytes): A 16-bit unsigned short integer field that is reserved for alignment. The sender SHOULD set this field to 0x0000, and the receiver MUST ignore it on receipt.

Size (4 bytes): A 32-bit unsigned integer field that MUST be set to the size, in **bytes**, of the **byte** array to hold the **Signature**. This field has a valid range between 0x00000000 and the size limit imposed by the value of **BaseHeader.PacketSize**.

Signature (variable): A **byte** array that contains the signature. The array MUST contain the number of elements that are specified by the **Size** field. The **Signature** MUST be calculated in the same way as the **SecurityData.Signature** as specified in section [2.2.20.6](#).

2.2.20.4 SessionHeader

The SessionHeader is used to acknowledge express and recoverable [UserMessage Packets](#) received by the message transfer protocols. This header is present in stand-alone SessionAck Packet as defined in [\[MS-MQQB\]](#) (section [2.2.6](#)) and is optional in a UserMessage Packet.

This header contains a session acknowledgment. For more details, see [\[MS-MQQB\]](#) sections [3.1.1.7](#), and [3.1.1.6.1](#).

The set of UserMessage Packets sent on a session represent a message sequence. There is a local-to-remote and remote-to-local sequence. These message sequences exist for the lifetime of the session. The local and remote protocols MUST maintain counts of the UserMessage Packets sent and received. A message MUST be associated with a sequence number that corresponds to its position within the sequence. Sequence numbers MUST begin with 1 and MUST increment by 1 with each subsequent message. For example, the third message sent on a session has a sequence number of 3.

The protocols MUST also maintain a count of recoverable UserMessage Packets sent and associates recoverable sequence numbers with those messages. For example, the fifth recoverable message sent on a session has a sequence number of 5.

0	1	2	3	4	5	6	7	8	9	10	1	2	3	4	5	6	7	8	9	20	1	2	3	4	5	6	7	8	9	30	1
AckSequenceNumber																RecoverableMsgAckSeqNumber															
RecoverableMsgAckFlags																															
UserMsgSequenceNumber																RecoverableMsgSeqNumber															
WindowSize																Reserved															

AckSequenceNumber (2 bytes): A 16-bit unsigned integer that specifies a count of messages received. This field MUST be set to the count of UserMessage Packets received on this session. This field acknowledges all messages up to and including the specified sequence number. This field has a valid range from 0x0000 to 0xFFFF, inclusive.

RecoverableMsgAckSeqNumber (2 bytes): A 16-bit unsigned integer that specifies a recoverable message sequence number. This field MUST be set to the lowest unacknowledged recoverable message sequence number that has been persisted for reliable recovery. If no recoverable messages have been received by the receiver since the last SessionHeader was sent, this field MUST be set to 0. This field has a valid range from 0x0000 to 0xFFFF, inclusive.

RecoverableMsgAckFlags (4 bytes): A 32-bit unsigned integer bit field representing messages. This bit field represents up to 32 recoverable UserMessage Packets that are being acknowledged as written to disk. Bit 0 of this field represents the UserMessage Packet whose sequence number is specified in the **RecoverableMsgAckSeqNumber** field. A given bit k of this field represents a recoverable UserMessage Packet with a sequence number of **RecoverableMsgAckSeqNumber** + k. The corresponding bit for a UserMessage Packet that has been persisted for reliable recovery MUST be set in the bit field.

UserMsgSequenceNumber (2 bytes): A 16-bit unsigned integer that is the count of messages sent. This field SHOULD [<15>](#) be set to the count of UserMessage Packets sent on this session. When the **UserMsgSequenceNumber** is not set to the count of UserMessage Packets sent on

a session, the user message is sent to the destination queue, and the session is closed by the receiver. This field has a valid range from 0x0000 to 0xFFFF, inclusive.

RecoverableMsgSeqNumber (2 bytes): A 16-bit unsigned integer that is the count of recoverable messages sent. This field **MUST** be set to the count of recoverable UserMessage Packets sent on this session. This value **MUST** be 0 if no recoverable UserMessage Packets have been sent. This field has a valid range from 0x0000 to 0xFFFF, inclusive.

WindowSize (2 bytes): A 16-bit unsigned integer field that specifies the acknowledgment window size. The window size controls the frequency at which the message transfer protocols send acknowledgment packets. [<16>](#) The value of this field **SHOULD** be set to 0x0040. [<17>](#) This field has a valid range from 0x0001 to 0xFFFF, inclusive. [<18>](#)

Reserved (2 bytes): Reserved. Can be set to any arbitrary value when sent and **MUST** be ignored on receipt.

2.2.20.5 TransactionHeader

The TransactionHeader packet contains sequence information for a transactional message. The presence of this packet in a [UserMessage Packet](#) indicates that the message contained in the packet is transactional.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
Flags																															
TxSequenceID																															
...																															
TxSequenceNumber																															
PreviousTxSequenceNumber																															
ConnectorQMGuid (optional)																															
...																															
...																															
...																															

Flags (4 bytes): A 32-bit unsigned integer that contains a set of options that provide additional information about the packet. Any combination of these values is acceptable unless otherwise noted in the following table.

Any value not specified in the table **MUST** be treated as an error by closing the session.

The value **SHOULD** be set to a combination of the following values. [<19>](#)

TxSequenceNumber (4 bytes): A 32-bit unsigned integer that is the message sequence number within the **TxSequenceID** sequence. This field MUST be set to the value that represents the message position within the transactional sequence. The first message within a sequence MUST be set to the value 1. This field has a valid range from 0x00000001 to 0xFFFFFFFF.

PreviousTxSequenceNumber (4 bytes): A 32-bit unsigned integer that is the sequence number of the previous message in the **TxSequenceID** sequence. This field MUST be set to the sequence number of the message that precedes this message in the transactional sequence. This value MUST be set to 0x00000000 if there is no previous message. This field has a valid range from 0x00000000 to 0xFFFFFFFFE.

ConnectorQMGuid (16 bytes): An optional field containing an application-defined **GUID**, as specified in [\[MS-DTYP\]](#) section 2.3.2. If **Flags.CG** is set, this field MUST be present; otherwise, it MUST NOT. This field can be used by higher-layer messaging applications. The server MUST NOT process or interpret this field.

2.2.20.6 SecurityHeader

The optional SecurityHeader contains security information.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	1	2	3	4	5	6	7	8	9	30	1
Flags																SenderIdSize															
EncryptionKeySize																SignatureSize															
SenderCertSize																															
ProviderInfoSize																															
SecurityData (variable)																															
...																															

Flags (2 bytes): A 16-bit unsigned short integer that contains a set of options that provides additional information about the packet. Any combination of these values is acceptable unless otherwise noted in the following table.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
ST				A	E	D	A	AS				X1	X1	X1	X1																
				U	B	E	I					2	3	4	5																

ST (4 bits): Specifies the type of sender ID in the **SecurityData** field. This field MUST be set to one of the following values.

Value	Meaning
0x0	The SecurityData.SecurityID field is not present and the SenderIdSize field MUST be set to 0x0000.
0x1	The SecurityData.SecurityID field MUST contain the sender application security identifier (SID). The SID layout is specified in [MS-DTYP] section 2.4.2.2. The SubAuthority field of the SID packet is a variable-length array of unsigned 32-bit little-endian integers.
0x2	The SecurityData.SecurityID field MUST contain the queue manager GUID .

AU (1 bit): Indicates whether the message is authenticated. This field MUST be set to 0.

EB (1 bit): Indicates whether the body of the message is encrypted. If set, the **MessagePropertiesHeader.MessageBody** field MUST be encrypted by the sender and decrypted by the receiver.

For details about encryption on the sender side, see [\[MS-MQOB\]](#) section 3.1.7.1.5.

For details about decryption on the receiver side, see [\[MS-MQOB\]](#) section 3.1.5.8.3.

DE (1 bit): Indicates whether the default cryptographic provider is used. [<20>](#) When clear and **SignatureSize** is nonzero, the **SecurityData.ProviderName** MUST specify the name of the alternate provider.

AI (1 bit): Indicates whether the **SecurityData** field is present. If set, the header MUST include a **SecurityData** field.

AS (4 bits): Indicates the authentication signature type. This field MUST be set to 0.

X12 (1 bit): Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X13 (1 bit): Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X14 (1 bit): Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

X15 (1 bit): Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

SenderIdSize (2 bytes): A 16-bit unsigned integer that specifies the size of the **SecurityData.SecurityID** field. This value MUST be set to the size, in bytes, of the security identifier in the **SecurityData.SecurityID** field. This field has a valid range from 0x0000 to 0xFFFF, inclusive.

EncryptionKeySize (2 bytes): A 16-bit unsigned integer that specifies the size of the **SecurityData.EncryptionKey** field. This value MUST be set to the size, in bytes, of the encryption key in the **SecurityData.EncryptionKey** field. This field has a valid range from 0x0000 to 0xFFFF, inclusive.

SignatureSize (2 bytes): A 16-bit unsigned integer that specifies the size of the **SecurityData.Signature** field. This value MUST be set to the size, in bytes, of the sender signature in the **SecurityData.Signature** field. This field has a valid range from 0x0000 to 0xFFFF, inclusive.

SenderCertSize (4 bytes): A 32-bit unsigned integer that specifies the size of the **SecurityData.SenderCert** field. This value MUST be set to the size, in bytes, of the sender signature in the **SecurityData.SenderCert** field. This field has a valid range from 0x00000000 to a value 0x0000FFFF, inclusive.

ProviderInfoSize (4 bytes): A 32-bit unsigned integer that specifies the size of the **SecurityData.ProviderInfo** field. This value MUST be set to the size, in bytes, of the security provider information in the **SecurityData.ProviderInfo** field. This field has a valid range between 0x00000000 and the size limit imposed by the value of **BaseHeader.PacketSize**.

At least one of the fields **SenderIdSize**, **EncryptionKeySize**, **SignatureSize**, **SenderCertSize**, and **ProviderInfoSize** MUST be nonzero.

SecurityData (variable): An optional variable-length array of bytes containing additional security information. This field MUST contain the security information specified in the **Flags** field.

The data appears in the order specified below. Each field MUST be aligned up to the next 4-byte boundary. The size of each field is specified by the corresponding **SenderIdSize**, **EncryptionKeySize**, **SignatureSize**, **SenderCertSize**, and **ProviderInfoSize** fields. An item with a size of zero occupies no space in the **SecurityData** array.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
SecurityID (variable)																															
...																															
EncryptionKey (variable)																															
...																															
Signature (variable)																															
...																															
SenderCert (variable)																															
...																															
ProviderInfo (variable)																															
...																															

SecurityID (variable): Contains the sender [SID](#) or the sending queue manager [GUID](#). This field MUST be set to the queue manager **GUID** when the packet is sent and signed by the queue manager.

EncryptionKey (variable): Sender symmetrical encryption key.

Signature (variable): The packet digital signature. The type of signature is specified by the MSMQ version as described in the following table and the hash algorithm is specified by the **MessagePropertiesHeader.HashAlgorithm** field.

MSMQ Version	Signature Type
MSMQ 1.0	The SecurityData.Signature field is an MSMQ 1.0 digital signature . If the SecurityData.Flags.ST field is set to 1, the SecurityData.SecurityID field MUST contain the sender application security identifier. If the SecurityData.Flags.ST field is set to 2, it specifies that the message is signed with Sender ID as the Signature . If set, the SecurityData.SecurityID field MUST contain the queue manager GUID. The signature MUST be a hash of the MSMQ 1.0 Digital Signature Properties (section 2.5.1) .
MSMQ 2.0	The SecurityData.Signature field is an MSMQ 2.0 digital signature . The signature MUST be a hash of the MSMQ 2.0 Digital Signature Properties (section 2.5.2) .
MSMQ 3.0, MSMQ 4.0, or MSMQ 5.0	The SecurityData.Signature field is an MSMQ 3.0 digital signature . The signature MUST be a hash of the MSMQ 3.0 Digital Signature Properties (section 2.5.3) .

The hash algorithm that is used to compute the **SecurityData.Signature** field is specified by the **MessagePropertiesHeader.HashAlgorithm** field.

For details about signature and hash computations on the sender side, see [\[MS-MQOB\]](#) section 3.1.7.1.4.

For details about authentication on the receiver side, see [\[MS-MQOB\]](#) section 3.1.5.8.3.

SenderCert (variable): Sender X.509 digital certificate. Details are as specified in [\[RFC3280\]](#). The public key that is contained in the certificate has the following structure.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
0x06								0x02								0x00								Key Type							
...																								0x52							
0x53								0x41								0x31								Length in bits							
...																								Public Exponent							
...																								Modulus (variable)							
...																															

Key Type (4 bytes): This MUST be set to 0x00002400 for RSA signing keys and 0x0000A400 for RSA encryption keys.

Length in bits (4 bytes): This 32-bit unsigned number MUST be the length of the RSA modulus. It MUST contain the length, in bits, of the Modulus field.

Public Exponent (4 bytes): This MUST be a 32-bit unsigned integer. It MUST be the public exponent of the RSA key pair, referred to as e in [\[RFC3447\]](#) section 2.

Modulus (variable): This MUST be the RSA modulus, referred to as defined in [\[RFC3447\]](#) section 2. This field MUST be a multiple of 8 bits in length and MUST append padding bits needed to ensure this requirement. Padding bits MUST be set to zero. The public key SHOULD [<21>](#) be stored in the directory.

ProviderInfo (variable): Contains the information of the alternative provider used to produce the signature. [<22>](#) If the Flags.DE bit is clear and the **ProviderInfoSize** is nonzero, this field MUST be set; otherwise it MUST NOT be included in the **SecurityData** field. The layout of this field is as follows. [<23>](#)

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
ProviderType																															
ProviderName (variable)																															
...																															

ProviderType (4 bytes): A 32-bit unsigned integer that indicates the type of the alternative provider used to produce the signature.

ProviderName (variable): A null-terminated Unicode string that contains the name of the alternative provider used to produce the signature.

2.2.20.7 SoapHeader

The optional SoapHeader packet contains application-defined information.

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	1	2	3	4	5	6	7	8	9	30	1
HeaderSectionID																Reserved															
HeaderDataLength																															
Header (variable)																															
...																															
BodySectionID																Reserved1															
BodyDataLength																															

Body (variable)
...

HeaderSectionID (2 bytes): A 16-bit unsigned short integer field that MUST be set to 0x0320.

Reserved (2 bytes): A 16-bit unsigned integer field that is reserved for future use. The sender SHOULD set this field to 0x0000, and the receiver MUST ignore it on receipt.

HeaderDataLength (4 bytes): A 32-bit unsigned integer that specifies the length of the **Header** field. This field MUST be set to the number of elements in the Unicode **Header** field, including the terminating null character. This field has a valid range between 0x00000000 and the size limit imposed by the value of BaseHeader.PacketSize.

Header (variable): A null-terminated Unicode string. This field contains an application-defined string.

BodySectionID (2 bytes): A 16-bit unsigned short integer that MUST be set to 0x0384.

Reserved1 (2 bytes): A 16-bit unsigned short integer field reserved for future use. The sender SHOULD set this field to 0x0000, and the receiver MUST ignore it on receipt.

BodyDataLength (4 bytes): A 32-bit unsigned integer that specifies the length of the **Body** field. This field MUST be set to the number of elements in the Unicode **Body** field, including the terminating null character. This field has a valid range between 0x00000000 and the size limit imposed by the value of BaseHeader.PacketSize.

Body (variable): A null-terminated Unicode string. This field contains an application-defined string.

2.2.20.8 DebugHeader

The DebugHeader specifies the queue to receive trace messages for this [UserMessage Packet](#). For details about how this header is used when tracing is enabled [<24>](#) see [\[MS-MQQB\]](#) section 3.1.5.8.9.

0	1	2	3	4	5	6	7	8	9	10	1	2	3	4	5	6	7	8	9	20	1	2	3	4	5	6	7	8	9	30	1
Flags																Reserved															
QueueIdentifier (optional)																															
...																															
...																															
...																															

Flags (2 bytes): A 16-bit unsigned short integer field that provides bit flags containing additional information about the packet.

--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--

QT (2 bits): Specifies the queue type. This field **MUST** be set to one of the following values.

Value	Meaning
0x0	No queue. The QueueIdentifier field is not present.
0x1	Public queue. The QueueIdentifier field contains a 16-byte queue GUID , as specified in [MS-DTYP] section 2.3.2.

X2 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X3 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X4 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X5 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X6 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X7 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X8 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X9 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X10 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X11 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X12 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X13 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X14 (1 bit): Unused bit field. This field **SHOULD NOT** be set when sent and **MUST** be ignored on receipt.

X15 (1 bit): Unused bit field. This field SHOULD NOT be set when sent and MUST be ignored on receipt.

Reserved (2 bytes): A 16-bit unsigned integer field that is reserved for future use. The sender SHOULD set this field to 0x0000, and the receiver MUST ignore it on receipt.

QueueIdentifier (16 bytes): An optional field that contains a **GUID**, as specified in [\[MS-DTYP\]](#) section 2.3.2, which is the identifier of the queue that is used to store trace messages. This field MUST be present when **DebugHeader.Flags.QT** is set to 0x1; otherwise, it MUST NOT be present.

2.2.21 MQUSERSIGNCERTS

The MQUSERSIGNCERTS structure defines a format for packing multiple [MQUSERSIGNCERT](#) structures into a single [BLOB \(section 2.2.15\)](#).

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
CertificateCount																															
Certificates (variable)																															
...																															

CertificateCount (4 bytes): A 32-bit unsigned integer that contains the count of MQUSERSIGNCERT structures in the **Certificates** field.

Certificates (variable): A variable-length array of bytes that contains MQUSERSIGNCERT structures.

2.2.22 MQUSERSIGNCERT

The MQUSERSIGNCERT structure defines one public key certificate stored in the user's signing certificate list ([MQUSERSIGNCERTS \(section 2.2.21\)](#)).

0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
Digest																															
...																															
...																															
...																															
Identifier																															
...																															

...
...
CertificateLength
Certificate (variable)
...

Digest (16 bytes): A 16-byte value that is computed as the MD5 hash of the user's X.509 certificate contained in the **Certificate** field, as defined in [\[RFC1321\]](#).

Identifier (16 bytes): A **GUID**, as specified in [\[MS-DTYP\]](#) section 2.3.2, that identifies the certificate contained in the **Certificate** field. It is generated by the entity that registers the certificate.

CertificateLength (4 bytes): A 32-bit unsigned integer that contains the size, in bytes, of the **Certificate** field.

Certificate (variable): A variable length array of bytes that contains an X.509-encoded certificate as defined in [\[RFC3280\]](#).

2.2.23 MQQMACCESSMASK

The **MQQMACCESSMASK** bitfield enumeration values can be used to set the value of an **ACCESS_MASK** structure ([\[MS-DTYP\]](#) section 2.4.3), which is used to constrain the permissions for a Queue Manager.

```
typedef enum
{
    MQSEC_DELETE_DEADLETTER_MESSAGE = 0x00000001,
    MQSEC_PEEK_DEADLETTER_MESSAGE = 0x00000002,
    MQSEC_CREATE_QUEUE = 0x00000004,
    MQSEC_SET_MACHINE_PROPERTIES = 0x00000010,
    MQSEC_GET_MACHINE_PROPERTIES = 0x00000020,
    MQSEC_DELETE_JOURNAL_QUEUE_MESSAGE = 0x00000040,
    MQSEC_PEEK_JOURNAL_QUEUE_MESSAGE = 0x00000080,
    MQSEC_DELETE_MACHINE = 0x00010000,
    MQSEC_GET_MACHINE_PERMISSIONS = 0x00020000,
    MQSEC_CHANGE_MACHINE_PERMISSIONS = 0x00040000,
    MQSEC_TAKE_MACHINE_OWNERSHIP = 0x00080000,
    MQSEC_RECEIVE_DEADLETTER_MESSAGE = (MQSEC_DELETE_DEADLETTER_MESSAGE
    + MQSEC_PEEK_DEADLETTER_MESSAGE),
    MQSEC_RECEIVE_JOURNAL_QUEUE_MESSAGE = (MQSEC_DELETE_JOURNAL_QUEUE_MESSAGE
    + MQSEC_PEEK_JOURNAL_QUEUE_MESSAGE),
    MQSEC_MACHINE_GENERIC_READ = (MQSEC_GET_MACHINE_PROPERTIES
    + MQSEC_GET_MACHINE_PERMISSIONS
    + MQSEC_RECEIVE_DEADLETTER_MESSAGE
    + MQSEC_RECEIVE_JOURNAL_QUEUE_MESSAGE),
    MQSEC_MACHINE_GENERIC_WRITE = (MQSEC_GET_MACHINE_PROPERTIES
    + MQSEC_GET_MACHINE_PERMISSIONS
    + MQSEC_CREATE_QUEUE),
    MQSEC_MACHINE_GENERIC_ALL = (MQSEC_RECEIVE_DEADLETTER_MESSAGE
```

```

+ MQSEC_RECEIVE_JOURNAL_QUEUE_MESSAGE
+ MQSEC_CREATE_QUEUE
+ MQSEC_SET_MACHINE_PROPERTIES
+ MQSEC_GET_MACHINE_PROPERTIES
+ MQSEC_DELETE_MACHINE
+ MQSEC_GET_MACHINE_PERMISSIONS
+ MQSEC_CHANGE_MACHINE_PERMISSIONS
+ MQSEC_TAKE_MACHINE_OWNERSHIP),
MQSEC_MACHINE_WORLD_RIGHTS = (MQSEC_GET_MACHINE_PROPERTIES
+ MQSEC_GET_MACHINE_PERMISSIONS)
} MQQACCESSMASK;

```

MQSEC_DELETE_DEADLETTER_MESSAGE: Specifies the permission required by a security principal to delete messages from the system dead-letter queue.

MQSEC_PEEK_DEADLETTER_MESSAGE: Specifies the permission required by a security principal to peek messages from the system dead-letter queue.

MQSEC_CREATE_QUEUE: Specifies the permission required by a security principal to create a new queue.

MQSEC_SET_MACHINE_PROPERTIES: Specifies the permission required by a security principal to change the properties of the queue manager.

MQSEC_GET_MACHINE_PROPERTIES: Specifies the permission required by a security principal to read the properties of the queue manager.

MQSEC_DELETE_JOURNAL_QUEUE_MESSAGE: Specifies the permission required by a security principal to delete a message from the system queue journal.

MQSEC_PEEK_JOURNAL_QUEUE_MESSAGE: Specifies the permission required by a security principal to peek a message from the system queue journal.

MQSEC_DELETE_MACHINE: Specifies the permission required by a security principal to delete the queue manager.

MQSEC_GET_MACHINE_PERMISSIONS: Specifies the permission required by a security principal to get the security descriptor of the queue manager.

MQSEC_CHANGE_MACHINE_PERMISSIONS: Specifies the permission required by a security principal to set or modify the security descriptor of the queue manager.

MQSEC_TAKE_MACHINE_OWNERSHIP: Specifies the permission required by a security principal to change the owner of the queue manager.

MQSEC_RECEIVE_DEADLETTER_MESSAGE: Specifies the permission required by a security principal to destructively read a message from the system dead-letter queue.

MQSEC_RECEIVE_JOURNAL_QUEUE_MESSAGE: Specifies the permission required by a security principal to destructively read a message from the system queue journal.

MQSEC_MACHINE_GENERIC_READ: Specifies the permission required by a security principal to read the queue manager properties, read the queue manager permissions, and destructively read a message from the system dead-letter or system queue journal.

MQSEC_MACHINE_GENERIC_WRITE: Specifies the permission required by a security principal to read the queue manager properties, read the queue manager permissions, and create new queues.

MQSEC_MACHINE_GENERIC_ALL: Specifies the permission required by a security principal to perform all of the operations listed previously.

MQSEC_MACHINE_WORLD_RIGHTS: Specifies the permission required by a security principal to get queue manager properties or permissions.

2.2.24 MQQUEUEACCESSMASK

The **MQQUEUEACCESSMASK** bitfield enumeration values can be used to set the value of an **ACCESS_MASK** structure ([\[MS-DTYP\]](#) section 2.4.3), which is used to constrain the permissions for a Queue.

```
typedef enum
{
    MQSEC_DELETE_MESSAGE = 0x00000001,
    MQSEC_PEEK_MESSAGE = 0x00000002,
    MQSEC_WRITE_MESSAGE = 0x00000004,
    MQSEC_DELETE_JOURNAL_MESSAGE = 0x00000008,
    MQSEC_SET_QUEUE_PROPERTIES = 0x00000010,
    MQSEC_GET_QUEUE_PROPERTIES = 0x00000020,
    MQSEC_DELETE_QUEUE = 0x00010000,
    MQSEC_GET_QUEUE_PERMISSIONS = 0x00020000,
    MQSEC_CHANGE_QUEUE_PERMISSIONS = 0x00040000,
    MQSEC_TAKE_QUEUE_OWNERSHIP = 0x00080000,
    MQSEC_RECEIVE_MESSAGE = (MQSEC_DELETE_MESSAGE
    + MQSEC_PEEK_MESSAGE),
    MQSEC_RECEIVE_JOURNAL_MESSAGE = (MQSEC_DELETE_JOURNAL_MESSAGE
    + MQSEC_PEEK_MESSAGE),
    MQSEC_QUEUE_GENERIC_READ = (MQSEC_GET_QUEUE_PROPERTIES
    + MQSEC_GET_QUEUE_PERMISSIONS
    + MQSEC_RECEIVE_MESSAGE
    + MQSEC_RECEIVE_JOURNAL_MESSAGE),
    MQSEC_QUEUE_GENERIC_WRITE = (MQSEC_GET_QUEUE_PROPERTIES
    + MQSEC_GET_QUEUE_PERMISSIONS
    + MQSEC_WRITE_MESSAGE),
    MQSEC_QUEUE_GENERIC_ALL = (MQSEC_RECEIVE_MESSAGE
    + MQSEC_RECEIVE_JOURNAL_MESSAGE
    + MQSEC_WRITE_MESSAGE + MQSEC_SET_QUEUE_PROPERTIES
    + MQSEC_GET_QUEUE_PROPERTIES
    + MQSEC_DELETE_QUEUE
    + MQSEC_GET_QUEUE_PERMISSIONS
    + MQSEC_CHANGE_QUEUE_PERMISSIONS
    + MQSEC_TAKE_QUEUE_OWNERSHIP)
} MQQUEUEACCESSMASK;
```

MQSEC_DELETE_MESSAGE: Specifies the permission required by a security principal to delete messages from the queue.

MQSEC_PEEK_MESSAGE: Specifies the permission required by a security principal to peek messages from the queue.

MQSEC_WRITE_MESSAGE: Specifies the permission required by a security principal to insert messages into the queue.

MQSEC_DELETE_JOURNAL_MESSAGE: Specifies the permission required by a security principal to delete messages from the queue journal associated with the queue.

MQSEC_SET_QUEUE_PROPERTIES: Specifies the permission required by a security principal to modify the properties of the queue.

MQSEC_GET_QUEUE_PROPERTIES: Specifies the permission required by a security principal to read the properties of the queue.

MQSEC_DELETE_QUEUE: Specifies the permission required by a security principal to delete a queue.

MQSEC_GET_QUEUE_PERMISSIONS: Specifies the permission required by a security principal to read the permissions for the queue.

MQSEC_CHANGE_QUEUE_PERMISSIONS: Specifies the permission required by a security principal to modify the permissions for the queue.

MQSEC_TAKE_QUEUE_OWNERSHIP: Specifies the permission required by a security principal to change the owner for the queue.

MQSEC_RECEIVE_MESSAGE: Specifies the permission required by a security principal to destructively read a message from the queue.

MQSEC_RECEIVE_JOURNAL_MESSAGE: Specifies the permission required by a security principal to destructively read a message from the queue journal associated with the queue.

MQSEC_QUEUE_GENERIC_READ: Specifies the permission required by a security principal to read the queue properties, read the queue permissions, and destructively receive messages from the queue or the associated queue journal.

MQSEC_QUEUE_GENERIC_WRITE: Specifies the permission required by a security principal to read the queue properties, read the queue permissions, and insert messages into the queue.

MQSEC_QUEUE_GENERIC_ALL: Specifies the permission required by a security principal to perform all of the operations listed previously.

2.2.25 MQSITEACCESSMASK

The **MQSITEACCESSMASK** bitfield enumeration values can be used to set the value of an **ACCESS_MASK** structure ([\[MS-DTYP\]](#) section 2.4.3), which is used to constrain the permissions for a Site.

```
typedef enum
{
    MQSEC_CREATE_FRS = 0x00000001,
    MQSEC_CREATE_BSC = 0x00000002,
    MQSEC_CREATE_MACHINE = 0x00000004,
    MQSEC_SET_SITE_PROPERTIES = 0x00000010,
    MQSEC_GET_SITE_PROPERTIES = 0x00000020,
    MQSEC_DELETE_SITE = 0x00010000,
    MQSEC_GET_SITE_PERMISSIONS = 0x00020000,
    MQSEC_CHANGE_SITE_PERMISSIONS = 0x00040000,
    MQSEC_TAKE_SITE_OWNERSHIP = 0x00080000,
    MQSEC_SITE_GENERIC_READ = (MQSEC_GET_SITE_PROPERTIES
    + MQSEC_GET_SITE_PERMISSIONS),
    MQSEC_SITE_GENERIC_WRITE = (MQSEC_GET_SITE_PROPERTIES
```

```

+ MQSEC_GET_SITE_PERMISSIONS
+ MQSEC_CREATE_MACHINE),
MQSEC_SITE_GENERIC_ALL = (MQSEC_CREATE_FRS
+ MQSEC_CREATE_BSC
+ MQSEC_CREATE_MACHINE
+ MQSEC_SET_SITE_PROPERTIES
+ MQSEC_GET_SITE_PROPERTIES
+ MQSEC_DELETE_SITE
+ MQSEC_GET_SITE_PERMISSIONS
+ MQSEC_CHANGE_SITE_PERMISSIONS
+ MQSEC_TAKE_SITE_OWNERSHIP)
} MQSITEACCESSMASK;

```

MQSEC_CREATE_FRS: Specifies the permission required by a security principal to add a routing server to the site.

MQSEC_CREATE_BSC: Specifies the permission required by a security principal to create a **Backup Site Controller (BSC)** for the site.

MQSEC_CREATE_MACHINE: Specifies the permission required by a security principal to add a queue manager to the site.

MQSEC_SET_SITE_PROPERTIES: Specifies the permission required by a security principal to modify properties of the site.

MQSEC_GET_SITE_PROPERTIES: Specifies the permission required by a security principal to read properties of the site.

MQSEC_DELETE_SITE: Specifies the permission required by a security principal to delete the site.

MQSEC_GET_SITE_PERMISSIONS: Specifies the permission required by a security principal to read permissions for the site.

MQSEC_CHANGE_SITE_PERMISSIONS: Specifies the permission required by a security principal to modify permissions for the site.

MQSEC_TAKE_SITE_OWNERSHIP: Specifies the permission required by a security principal to modify the owner of the site.

MQSEC_SITE_GENERIC_READ: Specifies the permission required by a security principal to read the properties and permissions for the site.

MQSEC_SITE_GENERIC_WRITE: Specifies the permission required by a security principal to read properties, read permissions, and add queue managers to the site.

MQSEC_SITE_GENERIC_ALL: Specifies the permission required by a security principal to perform all of the operations listed previously.

2.2.26 MQENTACCESSMASK

The **MQENTACCESSMASK** bitfield enumeration values can be used to set the value of an **ACCESS_MASK** structure ([\[MS-DTYP\]](#) section 2.4.3), which is used to constrain the permissions for an Enterprise.

```
typedef enum
```

```

{
    MQSEC_CREATE_USER = 0x00000001,
    MQSEC_CREATE_SITE = 0x00000002,
    MQSEC_CREATE_CN = 0x00000004,
    MQSEC_SET_ENTERPRISE_PROPERTIES = 0x00000010,
    MQSEC_GET_ENTERPRISE_PROPERTIES = 0x00000020,
    MQSEC_DELETE_ENTERPRISE = 0x00010000,
    MQSEC_GET_ENTERPRISE_PERMISSIONS = 0x00020000,
    MQSEC_CHANGE_ENTERPRISE_PERMISSIONS = 0x00040000,
    MQSEC_TAKE_ENTERPRISE_OWNERSHIP = 0x00080000,
    MQSEC_ENTERPRISE_GENERIC_READ = (MQSEC_CREATE_USER
    + MQSEC_GET_ENTERPRISE_PROPERTIES
    + MQSEC_GET_ENTERPRISE_PERMISSIONS),
    MQSEC_ENTERPRISE_GENERIC_WRITE = (MQSEC_CREATE_USER
    + MQSEC_GET_ENTERPRISE_PROPERTIES
    + MQSEC_GET_ENTERPRISE_PERMISSIONS
    + MQSEC_CREATE_SITE
    + MQSEC_CREATE_CN),
    MQSEC_ENTERPRISE_GENERIC_ALL = (MQSEC_CREATE_USER
    + MQSEC_CREATE_CN
    + MQSEC_CREATE_SITE
    + MQSEC_SET_ENTERPRISE_PROPERTIES
    + MQSEC_GET_ENTERPRISE_PROPERTIES
    + MQSEC_DELETE_ENTERPRISE
    + MQSEC_GET_ENTERPRISE_PERMISSIONS
    + MQSEC_CHANGE_ENTERPRISE_PERMISSIONS
    + MQSEC_TAKE_ENTERPRISE_OWNERSHIP)
} MQENTACCESSMASK;

```

MQSEC_CREATE_USER: Specifies the permission required by a security principal to add a user to the enterprise.

MQSEC_CREATE_SITE: Specifies the permission required by a security principal to create a site in the enterprise.

MQSEC_CREATE_CN: Specifies the permission required by a security principal to create a connected network in the enterprise.

MQSEC_SET_ENTERPRISE_PROPERTIES: Specifies the permission required by a security principal to modify properties of the enterprise.

MQSEC_GET_ENTERPRISE_PROPERTIES: Specifies the permission required by a security principal to read properties of the enterprise.

MQSEC_DELETE_ENTERPRISE: Specifies the permission required by a security principal to delete the enterprise.

MQSEC_GET_ENTERPRISE_PERMISSIONS: Specifies the permission required by a security principal to read permissions for the enterprise.

MQSEC_CHANGE_ENTERPRISE_PERMISSIONS: Specifies the permission required by a security principal to modify permissions for the enterprise.

MQSEC_TAKE_ENTERPRISE_OWNERSHIP: Specifies the permission required by a security principal to modify the owner of the enterprise.

MQSEC_ENTERPRISE_GENERIC_READ: Specifies the permission required by a security principal to read the properties and permissions for the enterprise, and create users.

MQSEC_ENTERPRISE_GENERIC_WRITE: Specifies the permission required by a security principal to read properties and permissions, and to add users, connected networks, and sites to the enterprise.

MQSEC_ENTERPRISE_GENERIC_ALL: Specifies the permission required by a security principal to perform all of the operations listed previously.

2.2.27 MQCNACCESSMASK

The **MQCNACCESSMASK** bitfield enumeration values can be used to set the value of an **ACCESS_MASK** structure ([\[MS-DTYP\]](#) section 2.4.3), which is used to constrain the permissions for a Connected Network.

```
typedef enum
{
    MQSEC_CN_OPEN_CONNECTOR = 0x00000001,
    MQSEC_SET_CN_PROPERTIES = 0x00000010,
    MQSEC_GET_CN_PROPERTIES = 0x00000020,
    MQSEC_DELETE_CN = 0x00010000,
    MQSEC_GET_CN_PERMISSIONS = 0x00020000,
    MQSEC_CHANGE_CN_PERMISSIONS = 0x00040000,
    MQSEC_TAKE_CN_OWNERSHIP = 0x00080000,
    MQSEC_CN_GENERIC_READ = (MQSEC_GET_CN_PROPERTIES
    + MQSEC_GET_CN_PERMISSIONS),
    SEC_CN_GENERIC_ALL = (MQSEC_CN_OPEN_CONNECTOR
    + MQSEC_SET_CN_PROPERTIES
    + MQSEC_GET_CN_PROPERTIES
    + MQSEC_DELETE_CN
    + MQSEC_GET_CN_PERMISSIONS
    + MQSEC_CHANGE_CN_PERMISSIONS
    + MQSEC_TAKE_CN_OWNERSHIP)
} MQCNACCESSMASK;
```

MQSEC_CN_OPEN_CONNECTOR: Specifies the permission required by a security principal to open a connector queue in the connected network.

MQSEC_SET_CN_PROPERTIES: Specifies the permission required by a security principal to modify properties of the connected network.

MQSEC_GET_CN_PROPERTIES: Specifies the permission required by a security principal to read properties of the connected network.

MQSEC_DELETE_CN: Specifies the permission required by a security principal to delete the connected network.

MQSEC_GET_CN_PERMISSIONS: Specifies the permission required by a security principal to read permissions for the connected network.

MQSEC_CHANGE_CN_PERMISSIONS: Specifies the permission required by a security principal to modify permissions for the site.

MQSEC_TAKE_CN_OWNERSHIP: Specifies the permission required by a security principal to modify the owner of the connected network.

MQSEC_CN_GENERIC_READ: Specifies the permission required by a security principal to read properties and permissions of the connected network.

SEC_CN_GENERIC_ALL: Specifies the permission required by a security principal to perform all of the operations listed previously.

2.3 PROPID

When making MSMQ-related API function calls, object properties are specified by providing an array of **property identifiers** (a unique **PROPID** value). The associated property values are specified (or returned) in a related array of [PROPVARIANT](#) structures. The values (in decimal), their PROPVARIANT types (as specified in section [2.2.12](#)), and their associated symbolic names are listed in the **PROPID** subsections. Related properties are grouped together within each **PROPID** subsection.

A **PROPID** is an unsigned 32-bit value.

This type is declared as follows:

```
typedef unsigned long PROPID;
```

Each directory object type and management type has a set of properties associated with it. The following sections define the property identifier ranges and the properties associated within each range.

Unless otherwise specified, properties are valid for all MSMQ versions.

2.3.1 Queue Property Identifiers

Queue properties specify attributes of individual queue objects.

2.3.1.1 PROPID_Q_INSTANCE

Value: 101

Variant type: [VT_CLSID](#)

Description: GUID for the queue.

2.3.1.2 PROPID_Q_TYPE

Value: 102

Variant type: [VT_CLSID](#)

Description: A user-defined value that indicates the type of service that the queue provides. The value is optionally specified at queue creation and can be changed after the queue has been created.

2.3.1.3 PROPID_Q_PATHNAME

Value: 103

Variant type: [VT_LPWSTR](#)

Description: The path of the queue. The value is specified at queue creation and is immutable thereafter. The value MUST conform to the ABNF rule QueuePathName, as specified in section [2.1.1](#).

2.3.1.4 PROPID_Q_JOURNAL

Value: 104

Variant type: [VT_UI1](#)

Description: A value that specifies how MSMQ tracks messages removed from the queue. This field MUST be one of the following.

Value	Constant	Description
0	MQ_JOURNAL_NONE	The default. Target journaling is not requested. Messages removed from the destination queue are no longer available.
1	MQ_JOURNAL	Target journaling is requested. Copies of messages are stored in the journal of the queue whenever a receiving application removes a message.

2.3.1.5 PROPID_Q_QUOTA

Value: 105

Variant type: [VT_UI4](#)

Description: Maximum size (in kilobytes) of a queue. [<25>](#)

2.3.1.6 PROPID_Q_BASEPRIORITY

Value: 106

Variant type: [VT_I2](#)

Description: Priority level of the queue. PROPID_Q_BASEPRIORITY applies only to public queues that can be located through the directory service (using a public format name). The base priority of private queues, as well as public queues accessed directly, is always 0x0000. Any attempt to create this property and set its value or to set the value of an existing property for a private queue when the queue is being created or after the queue is created will be ignored and will cause no change. The value MUST be set to a valid priority level. Priority levels are integer values between -32768 (0x8000) and +32767 (0x7fff). The default priority level is 0x0000.

2.3.1.7 PROPID_Q_JOURNAL_QUOTA

Value: 107

Variant type: [VT_UI4](#)

Description: Maximum size (in kilobytes) of the queue journal. Value may be in the range 0 to 0xffffffff. [<26>](#)

2.3.1.8 PROPID_Q_LABEL

Value: 108

Variant type: [VT_LPWSTR](#)

Description: A descriptive label (maximum 124 characters) for the queue.

2.3.1.9 PROPID_Q_CREATE_TIME

Value: 109

Variant type: [VT_I4](#)

Description: The time when the queue was created. Time is represented as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 UTC.

2.3.1.10 PROPID_Q_MODIFY_TIME

Value: 110

Variant type: [VT_I4](#)

Description: The time when the queue properties were last modified. The time is represented as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 UTC.

2.3.1.11 PROPID_Q_AUTHENTICATE

Value: 111

Variant type: [VT_UI1](#)

Description: Authentication level of the queue. MUST be one of the following values.

Value	Constant
0x0	MQ_AUTHENTICATE_NONE
0x01	MQ_AUTHENTICATE

2.3.1.12 PROPID_Q_PRIV_LEVEL

Value: 112

Variant type: [VT_UI4](#)

Description: Privacy level of the queue. MUST be one of the following values.

Value	Constant
0x00000000	MQ_PRIV_LEVEL_NONE
0x00000001	MQ_PRIV_LEVEL_OPTIONAL
0x00000002	MQ_PRIV_LEVEL_BODY

MQ_PRIV_LEVEL_NONE: The queue accepts only nonprivate (clear) messages.

MQ_PRIV_LEVEL_BODY: The queue accepts only private (encrypted) messages.

MQ_PRIV_LEVEL_OPTIONAL: The default. The queue does not enforce privacy. It accepts private (encrypted) messages and nonprivate (clear) messages.

2.3.1.13 PROPID_Q_TRANSACTION

Value: 113

Variant type: [VT_UI1](#)

Description: Transaction level of the queue. MUST be one of the following values.

Value	Constant
0x00	MQ_TRANSACTIONAL_NONE
0x01	MQ_TRANSACTIONAL

2.3.1.14 PROPID_Q_SCOPE

Value: 114

Variant type: [VT_UI1](#)

Description: A value that specifies the scope of a queue object. The value MUST be one of the following.

Value	Constant	Description
0x00	MQDS_SITESCOPE	Indicates a site scope.
0x01	MQDS_ENTERPRISESCOPE	Indicates an enterprise scope.

2.3.1.15 PROPID_Q_QMID

Value: 115

Variant type: [VT_CLSID](#)

Description: Contains the GUID of the queue manager that hosts the queue.

2.3.1.16 PROPID_Q_PARTITIONID

Value: 116

Variant type: [VT_CLSID](#)

Description: This property MAY [<27>](#) be used to group **MSMQ** directory objects.

2.3.1.17 PROPID_Q_SEQNUM

Value: 117

Variant type: [VT_BLOB](#)

Description: Contains the sequence number of the queue object.

2.3.1.18 PROPID_Q_HASHKEY

Value: 118

Variant type: [VT_UI4](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.1.19 PROPID_Q_LABEL_HASHKEY

Value: 119

Variant type: [VT_UI4](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.1.20 PROPID_Q_FULL_PATH

Value: 121

Variant type: [VT_LPWSTR](#)

Description: Contains the distinguished name (DN) of the queue object in Active Directory (as specified in [\[MS-ADTS\]](#)).

Note This property identifier was introduced in MSMQ 2.0.

2.3.1.21 PROPID_Q_NAME_SUFFIX

Value: 123

Variant type: [VT_LPWSTR](#)

Description: Contains the suffix of the queue name if the name exceeds 64 characters (the length of the **Common-Name** attribute in Active Directory).

Note This property identifier was introduced in MSMQ 2.0.

2.3.1.22 PROPID_Q_PATHNAME_DNS

Value: 124

Variant type: [VT_LPWSTR](#)

Description: Contains the **fully qualified domain name (FQDN)** prefixed path of the queue. The value MUST conform to the ABNF for QueuePathName (as specified in section [2.1.1](#)), where the computer name is the FQDN of the hosting computer.

Note This property identifier was introduced in MSMQ 2.0.

2.3.1.23 PROPID_Q_MULTICAST_ADDRESS

Value: 125

Variant type: [VT_LPWSTR](#)

Description: IP multicast address associated with the queue. The property value MUST contain a string that contains a valid multicast address conforming to the ABNF.

```
MulticastAddress = Address ":" Port
```

The ABNF rules for Address and Port are defined in section [2.1.6](#). The address MUST be in the class D range from 224.0.0.0 to 239.255.255.255. However, only certain ranges of addresses in this range are unreserved and available for sending multicast messages. For more information and the current list of reserved multicast addresses, see [\[IANAIMA\]](#). There are no restrictions on the port number.

Note This property identifier was introduced in MSMQ 3.0.

2.3.1.24 PROPID_Q_ADS_PATH

Value: 126

Variant type: [VT_LPWSTR](#)

Description: Contains the Active Directory path to the public queue object stored in Active Directory. The value MUST conform to the ABNF for ldapurl (as specified in [\[RFC4516\]](#)).

The following example shows a possible Active Directory path of the queue "MyComp\MyQueue".

LDAP://MyLDAPServer/CN=MyQueue,CN=msmq,CN=MyComp,CN=Computers,DC=MyDomain,DC=MyCompany,DC=COM

Note This property identifier was introduced in MSMQ 3.0.

2.3.1.25 PROPID_Q_SECURITY

Value: 1101

Variant type: [VT_BLOB](#)

Description: Contains the **security descriptor** of the queue object. The BLOB layout is that of **SECURITY_DESCRIPTOR**, as specified in [\[MS-DTYP\]](#) section 2.4.6. [<28>](#)

2.3.1.26 PROPID_Q_OBJ_SECURITY

Value: 1102

Variant type: [VT_BLOB](#)

Description: Contains the security descriptor of the queue object. The BLOB layout is that of **SECURITY_DESCRIPTOR** (as specified in [\[MS-DTYP\]](#) section 2.4.6).

Note This property identifier was introduced in MSMQ 2.0.

2.3.1.27 PROPID_Q_SECURITY_INFORMATION

Value: 1103

Variant type: [VT_UI4](#)

Description: Contains options related to setting or retrieving a security descriptor. It contains [SECURITY INFORMATION \(section 2.2.3\)](#).

2.3.2 Machine Property Identifiers

Machine object property identifiers describe a queue manager.

2.3.2.1 PROPID_QM_SITE_ID

Value: 201

Variant type: [VT_CLSID](#)

Description: Contains the site identifier GUID of the site in which the queue manager is located.

2.3.2.2 PROPID_QM_MACHINE_ID

Value: 202

Variant type: [VT_CLSID](#)

Description: A GUID that uniquely identifies the queue manager for the computer.

2.3.2.3 PROPID_QM_PATHNAME

Value: 203

Variant type: [VT_LPWSTR](#)

Description: The name of the computer where the queue manager is located.

2.3.2.4 PROPID_QM_ENCRYPTION_PK

Value: 205

Variant type: [VT_UI1](#) | [VT_VECTOR](#)

Description: The public encryption key of the computer. This property is superseded by [PROPID_QM_ENCRYPTION_PK_BASE](#) if present.

2.3.2.5 PROPID_QM_ADDRESS

Value: 206

Variant type: [VT_BLOB](#)

Description: The network address or addresses of the computer. The blob layout is a packed array of [TA_ADDRESS \(section 2.2.4\)](#) structures.

2.3.2.6 PROPID_QM_CNS

Value: 207

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: Contains an array of Connected Network identifiers for the connected networks that the queue manager supports.

2.3.2.7 PROPID_QM_OUTFRS

Value: 208

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: An array of GUIDs of routing servers that act as outgoing interfaces for all MSMQ messages that a given machine sends.

2.3.2.8 PROPID_QM_INFRS

Value: 209

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: An array of GUIDs of routing servers that act as incoming interfaces for all MSMQ messages that a given machine receives.

2.3.2.9 PROPID_QM_SERVICE

Value: 210

Variant type: [VT_UI4](#)

Description: Indicates the type of service that a given machine supports. The possible values are as follows.

Value	Meaning
0x00000000	The machine does not support any service.
0x00000001	The machine is an MSMQ Routing Server .
0x00000002	The machine is a Backup Site Controller (BSC).
0x00000004	The machine is a Primary Site Controller (PSC) .
0x00000008	The machine is a Primary Enterprise Controller (PEC) .
0x00000010	The machine is a RAS server.

2.3.2.10 PROPID_QM_QUOTA

Value: 214

Variant type: [VT_UI4](#)

Description: The disk quota for all queues located at the queue manager. Valid range: 0 to max unsigned 32-bit (0xffffffff).

2.3.2.11 PROPID_QM_PARTITIONID

Value: 211

Variant type: [VT_CLSID](#)

Description: This property MAY<29> be used to group MSMQ directory objects.

2.3.2.12 PROPID_QM_HASHKEY

Value: 212

Variant type: [VT_UI4](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.2.13 PROPID_QM_SEQNUM

Value: 213

Variant type: [VT_BLOB](#)

Description: Contains the sequence number of the queue manager object.

2.3.2.14 PROPID_QM_JOURNAL_QUOTA

Value: 215

Variant type: [VT_UI4](#)

Description: Contains the systemwide journal storage quota, in kilobytes. Range restrictions are identical to [PROPID_QM_QUOTA \(section 2.3.2.10\)](#).

2.3.2.15 PROPID_QM_MACHINE_TYPE

Value: 216

Variant type: [VT_LPWSTR](#)

Description: A description of the operating system version and the MSMQ version. MAY be an empty string<[30](#)> or a version string<[31](#)>.

2.3.2.16 PROPID_QM_CREATE_TIME

Value: 217

Variant type: [VT_I4](#)

Description: The time when the directory object was created. Time is represented as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 UTC.

2.3.2.17 PROPID_QM_MODIFY_TIME

Value: 218

Variant type: [VT_I4](#)

Description: The time when the directory object was last modified. The time is represented as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 UTC.

2.3.2.18 PROPID_QM_FOREIGN

Value: 219

Variant type: [VT_UI1](#)

Description: Indicates whether the queue manager is a foreign system that services **foreign queues**. The value MUST be one of the following.

Constant	Value
FOREIGN_MACHINE	0x01
MSMQ_MACHINE	0x00

2.3.2.19 PROPID_QM_OS

Value: 220

Variant type: [VT_UI4](#)

Description: A value indicating the operating system type of the queue manager. The value MUST be one of the following.

String	Value	Description
MSMQ_OS_NONE	0x00000000	Unknown operating system type
MSMQ_OS_FOREIGN	0x00000100	Not a Microsoft Windows® operating system type
MSMQ_OS_95	0x00000200	Microsoft Windows® 95 operating system
MSMQ_OS_NTW	0x00000300	Windows Client
MSMQ_OS_NTS	0x00000400	Windows Server
MSMQ_OS_NTE	0x00000500	Windows Server® 2003 Enterprise Edition operating system

2.3.2.20 PROPID_QM_FULL_PATH

Value: 221

Variant type: [VT_LPWSTR](#)

Description: The distinguishedName for the MSMQ Configuration object. The name MUST conform to ABNF: distinguishedName, as specified in [\[RFC4514\]](#).

Note Not valid for MSMQ 1.0.

2.3.2.21 PROPID_QM_SITE_IDS

Value: 222

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: Contains an array of site identifiers for sites to which the computer belongs.

Note Not valid for MSMQ 1.0.

2.3.2.22 PROPID_QM_OUTFRS_DN

Value: 223

Variant type: [VT_LPWSTR](#) | [VT_VECTOR](#)

Description: An array of distinguished names for MSMQ routing servers through which all outgoing traffic for this computer should be routed. Each name MUST conform to ABNF: distinguishedName, as specified in [\[RFC4514\]](#).

Note Not valid for MSMQ 1.0.

2.3.2.23 PROPID_QM_INFRS_DN

Value: 224

Variant type: [VT_LPWSTR](#) | [VT_VECTOR](#)

Description: An array of distinguished names for MSMQ routing servers through which all incoming traffic to this computer should be routed. Each name MUST conform to ABNF: distinguishedName, as specified in [\[RFC4514\]](#).

Note Not valid for MSMQ 1.0.

2.3.2.24 PROPID_QM_SERVICE_ROUTING

Value: 227

Variant type: [VT_UI1](#)

Description: Indicates whether the queue manager is configured as a routing server. This value SHOULD be settable only by the MSMQ installer. The value MUST be one of the following.

Value	Meaning
0x00	The queue manager is NOT configured as a routing server.
0x01	The queue manager is configured as a routing server.

Note Not valid for MSMQ 1.0.

2.3.2.25 PROPID_QM_SERVICE_DSSERVER

Value: 228

Variant type: [VT_UI1](#)

Description: Indicates whether the installed version of Microsoft Message Queuing (MSMQ) provides **MSMQ Directory Service (MQDS)** services. This property value is stored in **Active Directory (AD)** as a Boolean.

2.3.2.26 PROPID_QM_SERVICE_DEPCLIENTS

Value: 229

Variant type: [VT_UI1](#)

Description: Indicates whether the installed version of Microsoft Message Queuing (MSMQ) acts as an **MSMQ supporting server**. This property value is stored in Active Directory as a Boolean.

2.3.2.27 PROPID_QM_ENCRYPTION_PK_BASE

Value: 231

Variant type: [VT_UI1](#) | [VT_VECTOR](#)

Description: Contains the public encryption key of the computer.

Note Not valid for MSMQ 1.0.

2.3.2.28 PROPID_QM_ENCRYPTION_PK_ENHANCED

Value: 232

Variant type: [VT_UI1](#) | [VT_VECTOR](#)

Description: Contains the enhanced (128-bit) public encryption key of the computer.

Note Not valid for MSMQ 1.0.

2.3.2.29 PROPID_QM_PATHNAME_DNS

Value: 233

Variant type: [VT_LPWSTR](#)

Description: Contains the FQDN of the computer.

Note Not valid for MSMQ 1.0.

2.3.2.30 PROPID_QM_OBJ_SECURITY

Value: 234

Variant type: [VT_BLOB](#)

Description: Contains the security descriptor of the MSMQ Configuration object. The BLOB layout is that of **SECURITY_DESCRIPTOR**, as specified in [\[MS-DTYP\]](#) section 2.4.6.

Note Not valid for MSMQ 1.0.

2.3.2.31 PROPID_QM_SECURITY_INFORMATION

Value: 237

Variant type: [VT_UI4](#)

Description: Contains options related to setting or retrieving a security descriptor. The value MUST conform to [SECURITY_INFORMATION \(section 2.2.3\)](#).

2.3.2.32 PROPID_QM_ENCRYPT_PKS

Value: 238

Variant type: [VT_BLOB](#)

Description: The computer's public key certificates used for signing formatted as an [MQDSPUBLICKEYS \(section 2.2.2\)](#) structure.

2.3.2.33 PROPID_QM_SIGN_PKS

Value: 239

Variant type: [VT_BLOB](#)

Description: The computer's public key certificates used for signing, formatted as an [MQDSPUBLICKEYS \(section 2.2.2\)](#) structure.

2.3.2.34 PROPID_QM_OWNER_SID

Value: 241

Variant type: [VT_BLOB](#)

Description: Contains the **SID** of the user who ran the setup program. It is passed from the MSMQ service that created the MSMQ Configuration object so that the server can add it with full control to the DACL of the newly created object. The **SID** layout is specified in [\[MS-DTYP\]](#) section 2.4.2.2. The **SubAuthority** field of the **SID** packet is a variable-length array of unsigned 32-bit little-endian integers.

Note This property identifier was introduced in MSMQ 2.0.

2.3.2.35 PROPID_QM_GROUP_IN_CLUSTER

Value: 242

Variant type: [VT_UI1](#)

Description: Indicates that the MSMQ installation is in a group that is part of a cluster.

Used when creating the MSMQ Configuration objects. The value MUST be one of the following.

Constant	Value
MSMQ_GROUP_NOT_IN_CLUSTER	0x00
MSMQ_GROUP_IN_CLUSTER	0x01

Note This property identifier was introduced in MSMQ 2.0.

2.3.2.36 PROPID_QM_SECURITY

Value: 1201

Variant type: [VT_BLOB](#)

Description: Contains the security descriptor of the machine object. The layout of the **BLOB** is specified in [\[MS-DTYP\]](#) section 2.4.6. [<32>](#)

2.3.2.37 PROPID_QM_SIGN_PK

Value: 1202

Variant type: [VT_BLOB](#)

Description: The computer's public key certificates used for signing, formatted as an [MQDSPUBLICKEYS \(section 2.2.2\)](#) structure. This property can be specified only at object creation time.

2.3.2.38 PROPID_QM_ENCRYPT_PK

Value: 1203

Variant type: [VT_BLOB](#)

Description: The computer's public key certificates used for encryption, formatted as an [MQDSPUBLICKEYS \(section 2.2.2\)](#) structure. This property can be specified only at object creation time.

2.3.2.39 PROPID_QM_UPGRADE_DACL

Value: 1205

Variant type: [VT_BLOB](#)

Description: A dummy [PROPID](#). It is used only in a set property operation to request that the PEC update the DACL of the calling computer. The **BLOB** MAY be empty. The server MUST ignore the value.

2.3.3 Site Property Identifiers

Site property identifiers pertain to the site object.

2.3.3.1 PROPID_S_PATHNAME

Value: 301

Variant type: [VT_LPWSTR](#)

Description: Contains the name of the site.

2.3.3.2 PROPID_S_SITEID

Value: 302

Variant type: [VT_CLSID](#)

Description: Contains the identifier of the site.

2.3.3.3 PROPID_S_GATES

Value: 303

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: Contains the GUIDs of the MSMQ Configuration objects of the **MSMQ queue managers** that are the gates for this site.

2.3.3.4 PROPID_S_PSC

Value: 304

Variant type: [VT_LPWSTR](#)

Description: Contains the computer name of the PSC for the site.

2.3.3.5 PROPID_S_INTERVAL1

Value: 305

Variant type: [VT_UI2](#)

Description: In **MSMQ mixed-mode**, the default replication time (in seconds) within an MSMQ Site. The default is 2 seconds.

2.3.3.6 PROPID_S_INTERVAL2

Value: 306

Variant type: [VT_UI2](#)

Description: In MSMQ mixed-mode, the default replication time (in seconds) between MSMQ sites. The default is 10 seconds.

2.3.3.7 PROPID_S_PARTITIONID

Value: 307

Variant type: [VT_CLSID](#)

Description: This property MAY [<33>](#) be used to group MSMQ directory objects.

2.3.3.8 PROPID_S_SEQNUM

Value: 308

Variant type: [VT_BLOB](#)

Description: Contains the sequence number of the site object.

2.3.3.9 PROPID_S_FULL_NAME

Value: 309

Variant type: [VT_LPWSTR](#)

Description: Contains the DN of the site in Active Directory. (The name format is specified in [\[MS-ADTS\]](#).)

Note Not valid for MSMQ 1.0.

2.3.3.10 PROPID_S_NT4_STUB

Value: 310

Variant type: [VT_UI2](#)

Description: Specifies whether the site was migrated from an **MQIS** database. The value MUST be one of the following.

Value	Description
0x01	Site was migrated from MQIS.
0x00	Site was not migrated.

Note Not valid for MSMQ 1.0.

2.3.3.11 PROPID_S_FOREIGN

Value: 311

Variant type: [VT_UI1](#)

Description: Specifies whether the site is used as a definition of an external messaging system. The value MUST be one of the following.

Value	Description
0x01	Site is an external system.
0x00	Site is not external.

Note Not valid for MSMQ 1.0.

2.3.3.12 PROPID_S_DONOTHING

Value: 312

Variant type: [VT_UI1](#)

Description: When operating in MSMQ mixed-mode, the MSMQ replication service uses this property when replicating objects from MQIS to AD. Certain properties that are no longer used in MSMQ 2.0 and later are mapped to this property during replication, prior to creating the object in AD. The value stored in this property is not used by MSMQ.

Note Not valid for MSMQ 1.0.

2.3.3.13 PROPID_S_SECURITY

Value: 1301

Variant type: [VT_BLOB](#)

Description: Contains the security descriptor of the site object. The [BLOB](#) layout is that of **SECURITY_DESCRIPTOR**, as specified in [\[MS-DTYP\]](#) section 2.4.6. [<34>](#)

2.3.3.14 PROPID_S_PSC_SIGNPK

Value: 1302

Variant type: [VT_BLOB](#)

Description: Contains the signing key of the PSC formatted as an [MQDSPUBLICKEYS \(section 2.2.2\)](#) structure.

2.3.3.15 PROPID_S_SECURITY_INFORMATION

Value: 1303

Variant type: [VT_UI4](#)

Description: The [SECURITY_INFORMATION \(section 2.2.3\)](#) associated with setting or retrieving a security descriptor.

Note Not valid for MSMQ 1.0 or MSMQ 2.0.

2.3.4 Connected Network Property Identifiers

Connected Network object properties contain attributes of a connected network.

2.3.4.1 PROPID_CN_PROTOCOLID

Value: 501

Variant type: [VT_UI1](#)

Description: Indicates what network protocol is used on the connected network. This property MUST have one of the values listed in the following table.

Value	Meaning
IP_ADDRESS_TYPE 0x01	The connected network uses IP.
IPX_ADDRESS_TYPE 0x03	The connected network uses IPX.
FOREIGN_ADDRESS_TYPE 0x05	The connected network uses any other network protocol.

2.3.4.2 PROPID_CN_NAME

Value: 502

Variant type: [VT_LPWSTR](#)

Description: User-defined name for the connected network, formatted as a null-terminated Unicode string.

2.3.4.3 PROPID_CN_GUID

Value: 503

Variant type: [VT_CLSID](#)

Description: A GUID that uniquely identifies the connected network.

2.3.4.4 PROPID_CN_PARTITIONID

Value: 504

Variant type: [VT_CLSID](#)

Description: This property MAY [<35>](#) be used to group MSMQ directory objects.

2.3.4.5 PROPID_CN_SEQNUM

Value: 505

Variant type: [VT_BLOB](#)

Description: Contains the sequence number of the connected network object.

2.3.4.6 PROPID_CN_SECURITY

Value: 1501

Variant type: [VT_BLOB](#)

Description: Contains the security descriptor of the connected network object. The [BLOB](#) layout is that of **SECURITY_DESCRIPTOR**, as specified in [\[MS-DTYP\]](#) section 2.4.6. [<36>](#)

2.3.5 Enterprise Object Property Identifiers

Enterprise object properties pertain to enterprise-wide settings.

2.3.5.1 PROPID_E_NAME

Value: 601

Variant type: [VT_LPWSTR](#)

Description: User-defined name for the enterprise, formatted as a null-terminated Unicode string.

2.3.5.2 PROPID_E_NAMESTYLE

Value: 602

Variant type: [VT_UI1](#)

Description: In MSMQ 1.0, this property is not used. In MSMQ 2.0 and up, this property indicates whether weakened security is enabled. Value MUST be one of the following.

Value	Description
0x00	Weakened security is not enabled.
0x01	Weakened security is enabled.

Value	Description
0x02	Use internal default. <37>

2.3.5.3 PROPID_E_CSP_NAME

Value: 603

Variant type: [VT_LPWSTR](#)

Description: The type of cryptographic provider used by MSMQ. The default value is "Microsoft Enhanced RSA and AES Cryptographic Provider".

2.3.5.4 PROPID_E_PECNAME

Value: 604

Variant type: [VT_LPWSTR](#)

Description: Contains the machine name of the Primary Enterprise Controller, formatted as a null-terminated Unicode string.

2.3.5.5 PROPID_E_S_INTERVAL1

Value: 605

Variant type: [VT_UI2](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.5.6 PROPID_E_S_INTERVAL2

Value: 606

Variant type: [VT_UI2](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.5.7 PROPID_E_PARTITIONID

Value: 607

Variant type: [VT_CLSID](#)

Description: This property MAY [<38>](#) be used to group MSMQ directory objects.

2.3.5.8 PROPID_E_SEQNUM

Value: 608

Variant type: [VT_BLOB](#)

Description: Contains the sequence number of the enterprise object.

2.3.5.9 PROPID_E_ID

Value: 609

Variant type: [VT_CLSID](#)

Description: The GUID identifier for the directory object instance.

2.3.5.10 PROPID_E_CRL

Value: 610

Variant type: [VT_BLOB](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.5.11 PROPID_E_CSP_TYPE

Value: 611

Variant type: [VT_UI4](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.5.12 PROPID_E_ENCRYPT_ALG

Value: 612

Variant type: [VT_UI4](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.5.13 PROPID_E_SIGN_ALG

Value: 613

Variant type: [VT_UI4](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.5.14 PROPID_E_HASH_ALG

Value: 614

Variant type: [VT_UI4](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.5.15 PROPID_E_LONG_LIVE

Value: 616

Variant type: [VT_UI4](#)

Description: The default value for the time, in seconds, that a message has to reach a queue when sending MSMQ messages.

2.3.5.16 PROPID_E_VERSION

Value: 617

Variant type: [VT_UI2](#)

Description: The version number of MSMQ Directory Service (MQDS) information.

2.3.5.17 PROPID_E_SECURITY

Value: 1601

Variant type: [VT_BLOB](#)

Description: Contains the security descriptor of the enterprise object. The [BLOB](#) layout is that of **SECURITY_DESCRIPTOR**, as specified in [\[MS-DTYP\]](#) section 2.4.6. [<39>](#)

2.3.5.18 PROPID_E_CIPHER_MODE

Value: 615

Variant type: [VT_UI4](#)

Description: Reserved. The property value associated with this property identifier is undefined and MUST NOT be interpreted by any protocol implementation.

2.3.6 User Object Property Identifiers

User object properties are used by MSMQ during management of user certificates that are stored in the MSMQ Directory Service.

2.3.6.1 PROPID_U_SID

Value: 701

Variant type: [VT_BLOB](#)

Description: Contains the user's SID. The **SID** layout is specified in [\[MS-DTYP\]](#) section 2.4.2.2. The **SubAuthority** field of the **SID** packet is a variable-length array of unsigned 32-bit little-endian integers.

2.3.6.2 PROPID_U_PARTITIONID

Value: 703

Variant type: [VT_CLSID](#)

Description: This property MAY [<40>](#) be used to group MSMQ directory objects.

2.3.6.3 PROPID_U_SEQNUM

Value: 704

Variant type: [VT_BLOB](#)

Description: Contains the sequence number of the user object.

2.3.6.4 PROPID_U_SIGN_CERT

Value: 702

Variant type: [VT_BLOB](#)

Description: Contains an [MOUSERSIGNCERTS](#) structure that packs multiple X.509 encoded certificates for the user object.

2.3.6.5 PROPID_U_DIGEST

Value: 705

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: Contains an array of certificate digests. Each digest is computed as the MD5 hash of the encoded certificate. Each array element MUST contain the 16-byte output of the MD5 algorithm, as specified in [\[RFC1321\]](#).

2.3.6.6 PROPID_U_ID

Value: 706

Variant type: [VT_CLSID](#)

Description: The GUID identifying the user object.

2.3.7 Routinglink Property Identifiers

Routinglink properties define the cost of routing a message from one site to another.

2.3.7.1 PROPID_L_NEIGHBOR1

Value: 801

Variant type: [VT_CLSID](#)

Description: Contains the GUID of one of the routing sites.

2.3.7.2 PROPID_L_NEIGHBOR2

Value: 802

Variant type: [VT_CLSID](#)

Description: Contains the GUID of the other routing site.

2.3.7.3 PROPID_L_COST

Value: 803

Variant type: [VT_UI4](#)

Description: Contains the cost of the link. Each routing link is assigned a relative cost, which may reflect the speed or the monetary cost of the underlying physical communication link. The default value is 1; and costs can range from 1 to 999999, inclusive.

2.3.7.4 PROPID_L_PARTITIONID

Value: 804

Variant type: [VT_CLSID](#)

Description: This property MAY [<41>](#) be used to group MSMQ directory objects.

2.3.7.5 PROPID_L_SEQNUM

Value: 805

Variant type: [VT_BLOB](#)

Description: Contains the sequence number of the **routing link** object.

2.3.7.6 PROPID_L_ID

Value: 806

Variant type: [VT_CLSID](#)

Description: Contains the GUID of the routing link object.

2.3.7.7 PROPID_L_GATES_DN

Value: 807

Variant type: [VT_LPWSTR](#) | [VT_VECTOR](#)

Description: Contains the distinguished names of the MSMQ Configuration object of the computers that are site gates on the link. Each name MUST conform to ABNF: distinguishedName, as specified in [\[RFC4514\]](#).

Note Not valid for MSMQ 1.0 or MSMQ 2.0.

2.3.7.8 PROPID_L_NEIGHBOR1_DN

Value: 808

Variant type: [VT_LPWSTR](#)

Description: Contains the distinguished name of one site on the link. The name MUST conform to ABNF: distinguishedName, as specified in [\[RFC4514\]](#).

Note Not valid for MSMQ 1.0.

2.3.7.9 PROPID_L_NEIGHBOR2_DN

Value: 809

Variant type: [VT_LPWSTR](#)

Description: Contains the distinguished name of the other site on the link. The name MUST conform to ABNF: distinguishedName, as specified in [\[RFC4514\]](#).

Note Not valid for MSMQ 1.0.

2.3.7.10 PROPID_L_DESCRIPTION

Value: 810

Variant type: [VT_LPWSTR](#)

Description: Contains the description of the routing link.

Note Not valid for MSMQ 1.0.

2.3.7.11 PROPID_L_FULL_PATH

Value: 811

Variant type: [VT_LPWSTR](#)

Description: Contains the distinguished name of the routing link object in the Active Directory. The name MUST conform to ABNF: distinguishedName, as described in [\[RFC4514\]](#).

Note Not valid for MSMQ 1.0.

2.3.7.12 PROPID_L_ACTUAL_COST

Value: 812

Variant type: [VT_UI4](#)

Description: Contains the untranslated link cost. The value MUST be in the range from 1 to 999999, inclusive.

Note Not valid for MSMQ 1.0.

2.3.7.13 PROPID_L_GATES

Value: 813

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: Contains the GUIDs of the MSMQ Configuration objects of the computers that are site gates on the link.

Note Not valid for MSMQ 1.0.

2.3.8 Settings Property Identifiers

Setting objects represent MSMQ Routing Servers or **MSMQ Directory Service Servers**.

Note All Settings properties are not valid for MSMQ 1.0.

2.3.8.1 PROPID_SET_NAME

Value: 5101

Variant type: [VT_LPWSTR](#)

Description: Contains the **Common-Name** attribute, which MUST always be set to the string "MSMQ Settings".

2.3.8.2 PROPID_SET_SERVICE

Value: 5102

Variant type: [VT_UI4](#)

Description: Contains a value that identifies the type of service. The value MUST be one of the following.

Value	Description
0x00000000	None
0x00000001	Routing server (SRV)
0x00000002	Backup Site Controller (BSC)
0x00000004	Primary Site Controller (PSC)
0x00000008	Primary Enterprise Controller (PEC)

2.3.8.3 PROPID_SET_QM_ID

Value: 5103

Variant type: [VT_CLSID](#)

Description: Contains the GUID of the computer's MSMQ Configuration object.

2.3.8.4 PROPID_SET_FULL_PATH

Value: 5105

Variant type: [VT_LPWSTR](#)

Description: Contains the distinguished name of the MSMQ Settings object in the Active Directory. The name MUST conform to ABNF: distinguishedName, as specified in [\[RFC4514\]](#).

2.3.8.5 PROPID_SET_NT4

Value: 5106

Variant type: [VT_UI1](#)

Description: Specifies whether the server is MSMQ 1.0.

The value MUST be one of the following.

Value	Description
0x01	Server is MSMQ 1.0.
0x00	Server is not MSMQ 1.0.

2.3.8.6 PROPID_SET_PARTITIONID

Value: 5107

Variant type: [VT_CLSID](#)

Description: This property MAY [<42>](#) be used to group MSMQ directory objects.

2.3.8.7 PROPID_SET_SITENAME

Value: 5108

Variant type: [VT_LPWSTR](#)

Description: Contains the site name.

2.3.8.8 PROPID_SET_SERVICE_ROUTING

Value: 5109

Variant type: [VT_UI1](#)

Description: Specifies whether the server is a routing server. The value MUST be one of the following.

Value	Description
0x01	Server is a routing server.
0x00	Server is not a routing server.

2.3.8.9 PROPID_SET_SERVICE_DSSERVER

Value: 5110

Variant type: [VT_UI1](#)

Description: Specifies whether the queue manager provides access to the Active Directory for MSMQ 2.0 **directory service** clients. The value MUST be set to one of the following.

Value	Description
0x01	Server provides access to Active Directory.
0x00	Server does not provide access to Active Directory.

2.3.8.10 PROPID_SET_SERVICE_DEPCLIENTS

Value: 5111

Variant type: [VT_UI1](#)

Description: Specifies whether the server can be a supporting server for **applications**. The value MUST be set to one of the following.

Value	Description
0x01	Server can be a supporting server.
0x00	Server cannot be a supporting server.

2.3.8.11 PROPID_SET_OLDSERVICE

Value: 5112

Variant type: [VT_UI4](#)

Description: Contains a value that identifies the type of service. The value MUST be set to one of the following.

Value	Description
0x00000000	None
0x00000001	Routing server (SRV)
0x00000002	Backup Site Controller (BSC)
0x00000004	Primary Site Controller (PSC)
0x00000008	Primary Enterprise Controller (PEC)

2.3.9 MQUser Property Identifiers

These properties represent attributes of users who migrated to Active Directory from the Microsoft MQIS.

Note These values are not valid for MSMQ 1.0.

2.3.9.1 PROPID_MQU_SID

Value: 5401

Variant type: [VT_BLOB](#)

Description: The migrated user's SID. The **SID** layout is specified in [\[MS-DTYP\]](#) section 2.4.2.2. The **SubAuthority** field of the **SID** packet is a variable-length array of unsigned 32-bit little-endian integers.

2.3.9.2 PROPID_MQU_SIGN_CERT

Value: 5402

Variant type: [VT_BLOB](#)

Description: Contains an X.509 encoded certificate for the migrated user object as specified in [\[RFC3280\]](#).

2.3.9.3 PROPID_MQU_DIGEST

Value: 5405

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: Contains an array of certificate digests. Each digest is computed as the MD5 hash of the encoded certificate. Each array element MUST contain the 16-byte output of the MD5 algorithm, as specified in [\[RFC1321\]](#).

2.3.9.4 PROPID_MQU_ID

Value: 5406

Variant type: [VT_CLSID](#)

Description: Contains the GUID of the MQUser object.

2.3.9.5 PROPID_MQU_SECURITY

Value: 5407

Variant type: [VT_BLOB](#)

Description: Contains the security descriptor of the MQUser object. The [BLOB](#) layout is that of **SECURITY_DESCRIPTOR**, as specified in [\[MS-DTYP\]](#) section 2.4.6. [<43>](#)

2.3.10 Computer Property Identifiers

Computer properties contain attributes of the computer object.

Note These values are not valid for MSMQ 1.0.

2.3.10.1 PROPID_COM_FULL_PATH

Value: 5201

Variant type: [VT_LPWSTR](#)

Description: Contains the distinguished name of the computer. The name MUST conform to ABNF: distinguishedName, as specified in [\[RFC4514\]](#).

2.3.10.2 PROPID_COM_SAM_ACCOUNT

Value: 5202

Variant type: [VT_LPWSTR](#)

Description: Identifies a property that contains the name of the computer account in Active Directory. Contains the name of the computer object. The value is represented as the computer name (truncated to 19 characters) followed by a dollar sign "\$" character. For example, the property value for a computer with the name "MyComputer" is "MyComputer\$".

2.3.10.3 PROPID_COM_ACCOUNT_CONTROL

Value: 5204

Variant type: [VT_UI4](#)

Description: Contains user account control attributes, as specified in [\[MS-SAMR\]](#). The value MUST be a bitmask computed as a logical OR of a set of UF_FLAG codes, as specified in [\[MS-SAMR\]](#) section 2.2.1.13.

2.3.10.4 PROPID_COM_DNS_HOSTNAME

Value: 5205

Variant type: [VT_LPWSTR](#)

Description: Contains the DNS host name attribute of the computer object. The value MUST contain the FQDN of the computer.

2.3.10.5 PROPID_COM_SID

Value: 5206

Variant type: [VT_BLOB](#)

Description: Contains the SID of the computer object. This property is read from Active Directory during creation of an MSMQ service Configuration object, and is used to add the computer SID to the MSMQ service configuration DACL. The **SID** layout is specified in [\[MS-DTYP\]](#) section 2.4.2.2. The **SubAuthority** field of the **SID** packet is a variable-length array of unsigned 32-bit little-endian integers.

2.3.10.6 PROPID_COM_SIGN_CERT

Value: 5207

Variant type: [VT_BLOB](#)

Description: Contains an X.509 encoded certificate for the computer object. The X.509 encoded certificate is specified in [\[RFC3280\]](#).

2.3.10.7 PROPID_COM_DIGEST

Value: 5208

Variant type: [VT_CLSID](#) | [VT_VECTOR](#)

Description: Contains an array of certificate digests. The digest is computed as the MD5 hash of the encoded certificate. Each value MUST contain the 16-byte output of the MD5 algorithm, as specified in [\[RFC1321\]](#).

2.3.10.8 PROPID_COM_ID

Value: 5209

Variant type: [VT_CLSID](#)

Description: Contains the **GUID** (as specified in [\[MS-DTYP\]](#) section 2.3.2) of the computer object.

2.3.11 Management Machine Property Identifiers

Management machine property identifiers provide values that identify properties that describe local administration of MSMQ machines.

2.3.11.1 PROPID_MGMT_MSMQ_ACTIVEQUEUES

Value: 1

Variant type: [VT_LPWSTR](#) | [VT_VECTOR](#)

Description: A list of all the **active queue** names on the computer. Each name MUST conform to the ABNF for a format name, as specified in sections [2.1.2](#), [2.1.3](#), [2.1.4](#), and [2.1.6](#).

2.3.11.2 PROPID_MGMT_MSMQ_PRIVATEQ

Value: 2

Variant type: [VT_LPWSTR](#) | [VT_VECTOR](#)

Description: A list of the path names of all the private queues registered on the computer.

2.3.11.3 PROPID_MGMT_MSMQ_DSSERVER

Value: 3

Variant type: [VT_LPWSTR](#)

Description: The name of the current MSMQ Directory Service server for the computer. The pointer to a null-terminated Unicode string that specifies the computer name of the discovered server. The returned computer name is prefixed with "\\".

The format in ABNF notation is as follows.

```
DS = "\\\" 1*NameChar EndList

R1 = %x01-2b ; Range 1
R2 = %x2c-2c ; Range 2 is x2c only
R3 = %x00-ff ; Range 3
R4 = %x01-ff ; Range 4
R5 = %x2d-ff ; Range 5
R6 = %x00-00 ; Range 6 is x00 only
X1 = R1 R3 ; Two hex digit range 1
X2 = R2 R4 ; Two hex digit range 2
X3 = R5 R3 ; Two hex digit range 3
X4 = R6 R4 ; Two hex digit range 4
NameChar = X1 / X2 / X3 / X4 ; Name character: no commas or nulls
EndList = %x00.00 ; Use null for end of string
```

2.3.11.4 PROPID_MGMT_MSMQ_CONNECTED

Value: 4

Variant type: [VT_LPWSTR](#)

Description: The value that indicates whether the queue manager on the computer has been disconnected from the network. The value MUST be one of the following strings.

Value	Constant
"CONNECTED"	MSMQ_CONNECTED
"DISCONNECTED"	MSMQ_DISCONNECTED

2.3.11.5 PROPID_MGMT_MSMQ_TYPE

Value: 5

Variant type: [VT_LPWSTR](#)

Description: The version and build information for the computer operating system and MSMQ installation.

2.3.11.6 PROPID_MGMT_MSMQ_BYTES_IN_ALL_QUEUES

Value: 6

Variant type: [VT_I8](#)

Description: The number of message bytes stored in all the queues on the computer.

Note Not valid for MSMQ 1.0 and MSMQ 2.0.

2.3.12 Management Queue Property Identifiers

Management **queue property** identifiers provide values that identify properties for monitoring the MSMQ installation and the queues on a computer, which allows applications to manage these resources programmatically.

2.3.12.1 PROPID_MGMT_QUEUE_PATHNAME

Value: 1

Variant type: [VT_LPWSTR](#)

Description: The path name of the queue. The path name format is specified in section [2.1.1](#).

2.3.12.2 PROPID_MGMT_QUEUE_FORMATNAME

Value: 2

Variant type: [VT_LPWSTR](#)

Description: The format name of the queue, as specified in section [2.1](#).

2.3.12.3 PROPID_MGMT_QUEUE_TYPE

Value: 3

Variant type: [VT_LPWSTR](#)

Description: The type of the queue. The value MUST be one of the following strings.

Value	Constant
"PUBLIC"	MGMT_QUEUE_TYPE_PUBLIC
"PRIVATE"	MGMT_QUEUE_TYPE_PRIVATE
"MACHINE"	MGMT_QUEUE_TYPE_MACHINE
"CONNECTOR"	MGMT_QUEUE_TYPE_CONNECTOR
"MULTICAST"	MGMT_QUEUE_TYPE_MULTICAST

2.3.12.4 PROPID_MGMT_QUEUE_LOCATION

Value: 4

Variant type: [VT_LPWSTR](#)

Description: The value that indicates whether the queue is located on the computer. The value MUST be one of the following strings.

Value	Constant
"LOCAL"	MGMT_QUEUE_LOCAL_LOCATION
"REMOTE"	MGMT_QUEUE_REMOTE_LOCATION

2.3.12.5 PROPID_MGMT_QUEUE_XACT

Value: 5

Variant type: [VT_LPWSTR](#)

Description: The value that indicates whether the queue is transactional. The value MUST be one of the following strings.

Value	Constant
"UNKNOWN"	MGMT_QUEUE_UNKNOWN_TYPE
"YES"	MGMT_QUEUE_TRANSACTIONAL_TYPE
"NO"	MGMT_QUEUE_NOT_TRANSACTIONAL_TYPE

2.3.12.6 PROPID_MGMT_QUEUE_FOREIGN

Value: 6

Variant type: [VT_LPWSTR](#)

Description: The string that indicates whether the queue is a foreign queue. The value MUST be one of the following strings.

Value	Constant
"UNKNOWN"	MGMT_QUEUE_UNKNOWN_TYPE
"YES"	MGMT_QUEUE_FOREIGN_TYPE
"NO"	MGMT_QUEUE_NOT_FOREIGN_TYPE

2.3.12.7 PROPID_MGMT_QUEUE_MESSAGE_COUNT

Value: 7

Variant type: [VT_UI4](#)

Description: The number of messages in the queue.

2.3.12.8 PROPID_MGMT_QUEUE_BYTES_IN_QUEUE

Value: 8

Variant type: [VT_UI4](#)

Description: The number of message bytes for all messages in the queue.

Note This property identifier is available only in MSMQ 3.0 and later versions. It replaces PROPID_MGMT_QUEUE_JOURNAL_USED_QUOTA from MSMQ 1.0 and MSMQ 2.0.

2.3.12.9 PROPID_MGMT_QUEUE_JOURNAL_MESSAGE_COUNT

Value: 9

Variant type: [VT_UI4](#)

Description: The number of messages in the queue journal.

2.3.12.10 PROPID_MGMT_QUEUE_BYTES_IN_JOURNAL

Value: 10

Variant type: [VT_UI4](#)

Description: The number of message bytes for all messages in the queue journal.

Note This property identifier is available only in MSMQ 3.0 and later versions. It replaces PROPID_MGMT_QUEUE_JOURNAL_USED_QUOTA from MSMQ 1.0 and MSMQ 2.0.

2.3.12.11 PROPID_MGMT_QUEUE_STATE

Value: 11

Variant type: [VT_LPWSTR](#)

Description: The connection state of the **outgoing queue**. The value MUST be one of the following strings.

Value	Constant
"LOCAL CONNECTION"	MGMT_QUEUE_STATE_LOCAL
"INACTIVE"	MGMT_QUEUE_STATE_NONACTIVE
"WAITING"	MGMT_QUEUE_STATE_WAITING
"NEED VALIDATION"	MGMT_QUEUE_STATE_NEED_VALIDATE
"ONHOLD"	MGMT_QUEUE_STATE_ONHOLD
"CONNECTED"	MGMT_QUEUE_STATE_CONNECTED
"DISCONNECTING"	MGMT_QUEUE_STATE_DISCONNECTING
"DISCONNECTED"	MGMT_QUEUE_STATE_DISCONNECTED

2.3.12.12 PROPID_MGMT_QUEUE_NEXTHOPS

Value: 12

Variant type: [VT_LPWSTR](#) | [VT_VECTOR](#)

Description: The address, or a list of possible addresses, for routing messages to the destination queue in the next hop. If the queue is in the process of being connected, a list of possible addresses is returned. Each element conforms to the following ABNF.

```

Address = IPAddr/ForeignAddress/IPv6Addr

IPAddr   = "IP=" IPv4address

ForeignAddress = "FOREIGN=" Guid

IPv6Addr  = "IPv6=" IPv6address

Guid = 8HexDig %x2D 3(4HexDig %x2D) 12HexDig

HexDig = Digit / "A" / "B" / "C" / "D" / "E" / "F"

Digit = %x30-39

```

ABNF rules IPv4address and IPv6address are defined in [\[RFC3986\]](#) appendix A.

2.3.12.13 PROPID_MGMT_QUEUE_EOD_LAST_ACK

Value: 13

Variant type: [VT_BLOB](#)

Description: The sequence information about the last message sent from the computer to the queue for which an **order acknowledgment** was received. The [BLOB](#) layout of the **SEQUENCE_INFO** structure is specified in section [2.2.5](#).

2.3.12.14 PROPID_MGMT_QUEUE_EOD_LAST_ACK_TIME

Value: 14

Variant type: [VT_I4](#)

Description: The date and time when the last order acknowledgment for a message sent from the computer to the queue was received. Time is represented as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 UTC.

2.3.12.15 PROPID_MGMT_QUEUE_EOD_LAST_ACK_COUNT

Value: 15

Variant type: [VT_UI4](#)

Description: The number of times that the last order acknowledgment for a message sent from the computer to the queue was received.

2.3.12.16 PROPID_MGMT_QUEUE_EOD_FIRST_NON_ACK

Value: 16

Variant type: [VT_BLOB](#)

Description: The sequence information about the first message sent from the computer to the queue for which no order acknowledgment was received. The [BLOB](#) layout of the **SEQUENCE_INFO** structure is specified in section [2.2.5](#).

2.3.12.17 PROPID_MGMT_QUEUE_EOD_LAST_NON_ACK

Value: 17

Variant type: [VT_BLOB](#)

Description: The sequence information about the last message that was sent from the computer to the queue for which no order acknowledgment was received. The [BLOB](#) layout of the **SEQUENCE_INFO** structure is specified in section [2.2.5](#).

2.3.12.18 PROPID_MGMT_QUEUE_EOD_NEXT_SEQ

Value: 18

Variant type: [VT_BLOB](#)

Description: The sequence information about the next message to be sent from the computer to the queue. The [BLOB](#) layout of the **SEQUENCE_INFO** structure is specified in section [2.2.5](#).

2.3.12.19 PROPID_MGMT_QUEUE_EOD_NO_READ_COUNT

Value: 19

Variant type: [VT_UI4](#)

Description: The number of messages sent from the computer to the queue for which an order acknowledgment was received but for which a receive acknowledgment message was not received.

2.3.12.20 PROPID_MGMT_QUEUE_EOD_NO_ACK_COUNT

Value: 20

Variant type: [VT_UI4](#)

Description: The number of messages sent from the computer to the queue for which no order acknowledgment was received.

2.3.12.21 PROPID_MGMT_QUEUE_EOD_RESEND_TIME

Value: 21

Variant type: [VT_I4](#)

Description: The time at which MSMQ will attempt to send a message from the computer to the queue again. Time is represented as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 UTC.

2.3.12.22 PROPID_MGMT_QUEUE_EOD_RESEND_INTERVAL

Value: 22

Variant type: [VT_UI4](#)

Description: The resend interval (in seconds) for the messages in the outgoing queue for which no order acknowledgment was received.

2.3.12.23 PROPID_MGMT_QUEUE_EOD_RESEND_COUNT

Value: 23

Variant type: [VT_UI4](#)

Description: The number of times that the last message in the corresponding outgoing queue on the computer was sent.

2.3.12.24 PROPID_MGMT_QUEUE_EOD_SOURCE_INFO

Value: 24

Variant type: [VT_VARIANT](#) | [VT_VECTOR](#)

Description: The array of information about the transactional messages sent from all source computers to the queue on the target computer.

The array contains the following six items. Each item is an array; there is one entry in each array for each message.

- **Format name**

Variant type: [VT_LPWSTR](#) | [VT_VECTOR](#)

Description: Each entry is a format name of a queue, as specified in section [2.1](#).

- **Sender ID**

Variant type: [VT_CLSID](#) | **VT_VECTOR**

Description: Each entry is a GUID of the sender of the message.

- **Sequence ID**

Variant type: [VT_UI8](#) | **VT_VECTOR**

Description: Each entry is a number to distinguish a sequence from other sequences.

- **Sequence number**

Variant type: [VT_UI4](#) | **VT_VECTOR**

Description: Each entry is a sequence number.

- **Last access time**

Variant type: [VT_I4](#) | **VT_VECTOR**

Description: Each entry was the time when the queue was accessed. Time is represented as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 UTC.

- **Message reject count**

Variant type: **VT_UI4** | **VT_VECTOR**

Description: Each entry is the number of times that a message was rejected.

2.3.12.25 PROPID_MGMT_QUEUE_CONNECTION_HISTORY

Value: 25

Variant type: 12 | 0x1000 - [VT_VARIANT](#) | [VT_VECTOR](#)

Description: The array representing the queue connection state history information. The array consists of the following four items, and each item is an array.

- **Status**

Variant type: [VT_UI4](#) | [VT_VECTOR](#)

Description: Each entry is the connection status and cause of the failure. The contents MUST be one of the following values.

Value	Description
0x00000000	Connection is in the process of establishment; no failures have occurred.
0x00000001	Connection establishment packet has been received.
0x00000002	Connection has been successfully established and is ready to send messages.
0x80000000	Exact reason for failure cannot be determined.
0x80000001	Ping failure.
0x80000002	Create socket failure.

Value	Description
0x80000003	Bind socket failure.
0x80000004	Connect socket failure.
0x80000005	TCP is not enabled.
0x80000006	Send operation on a socket failed.
0x80000007	Send operation failed because connection is not ready.
0x80000008	DNS failure.
0x80000009	Could not validate server certificate in HTTPS scenario.
0x8000000A	Connection limit reached, cannot establish new session to a specific destination.
0x8000000B	Connection refused by other side due to any reason (quota, invalid packet, connection limit reached).
0x8000000C	Absence of MSMQ Directory Service server connectivity prevents getting routing data.
0x8000000D	Failure due to low memory.

- **Time at which the failure occurred**

Variant type: **VT_I4** | [VT_VECTOR](#)

Description: Each entry is the time is represented as the number of seconds elapsed since midnight (00:00:00), January 1, 1970 UTC.

- **Error indicator**

Variant type: **VT_I4** | [VT_VECTOR](#)

Description: Each entry is a value; a non-zero value indicates an error.

- **List of addresses**

Variant type: [VT_LPWSTR](#) | **VT_VECTOR** | [VT_VECTOR](#)

Description: Each entry is an address or a list of possible addresses for routing messages to the destination queue in the next hop. Each element MUST conform to the following ABNF.

```

Address = Name / IPAddress

Name = "\\\" 1*Alpha

Alpha = %x41-5A / %x61-7A

IPAddress = AddDigits 3("." AddDigits)

Digit = %x30-39

AddDigits = 1*3Digit

```

2.3.12.26 PROPID_MGMT_QUEUE_SUBQUEUE_COUNT

Value: 26

Variant type: [VT_UI4](#)

Description: The count of the number of subqueues for a given queue.

2.3.12.27 PROPID_MGMT_QUEUE_SUBQUEUE_NAMES

Value: 27

Variant type: [VT_LPWSTR](#) | [VT_VECTOR](#)

Description: The list of subqueue names (as specified in section [2.1](#)) for a given queue.

2.3.13 Deletion Notification Property Identifiers

Deletion notification property identifiers provide values that identify properties in a directory service object deletion notification.

2.3.13.1 PROPID_D_SEQNUM

Value: 1401

Variant type: [VT_BLOB](#)

Description: Contains the sequence number of the deleted object.

2.3.13.2 PROPID_D_PARTITIONID

Value: 1402

Variant type: [VT_CLSID](#)

Description: This property MAY [<44>](#) be used to group MSMQ directory objects.

2.3.13.3 PROPID_D_SCOPE

Value: 1403.

Variant type: [VT_UI1](#).

Description: A value that specifies the scope of a deletion notification. The value MUST be one of the following.

Value	Constant	Description
0	MQDS_SITESCOPE	Indicates a site scope.
1	MQDS_ENTERPRISESCOPE	Indicates an enterprise scope.

2.3.13.4 PROPID_D_OBJTYPE

Value: 1404.

Variant type: [VT_UI1](#).

Description: A value that specifies the type of a deleted object. The value MUST be one of the following.

Value	Constant	Description
1	MQDS_QUEUE	Object represents a message queue .
2	MQDS_MACHINE	Object represents a queue manager.
3	MQDS_SITE	Object represents a site.
4	MQDS_DELETEDOBJECT	Object has been deleted.
5	MQDS_CN	Object represents a connected network.
6	MQDS_ENTERPRISE	Object represents an enterprise.
7	MQDS_USER	Object represents a user.
8	MQDS_ROUTINGLINK	Object represents a routing link.

2.3.13.5 PROPID_D_IDENTIFIER

Value: 1405

Variant type: [VT_CLSID](#)

Description: Contains the GUID of the deleted object.

2.4 Error Codes

The following table specifies MSMQ-specific [HRESULT](#) values. Not all methods of all protocols return these error codes. Common HRESULT values are specified in [\[MS-ERREF\]](#) section 2.1.<45>

Return value/code	Description
0x400E0001 MQ_INFORMATION_PROPERTY	One or more of the properties passed resulted in a warning, but the function completed.
0x400E0002 MQ_INFORMATION_ILLEGAL_PROPERTY	The property ID is invalid.
0x400E0003 MQ_INFORMATION_PROPERTY_IGNORED	The property specified was ignored for this operation.
0x400E0004 MQ_INFORMATION_UNSUPPORTED_PROPERTY	The property specified is not supported and was ignored for this operation.
0x400E0005 MQ_INFORMATION_DUPLICATE_PROPERTY	The property specified is already in the property identifier array. The duplicate was ignored for this operation.
0x400E0006	An asynchronous operation is

Return value/code	Description
MQ_INFORMATION_OPERATION_PENDING	currently pending.
0x400E0009 MQ_INFORMATION_FORMATNAME_BUFFER_TOO_SMALL	The format name buffer supplied was too small to hold the format name; however, the queue was created successfully.
0x400E000A MQ_INFORMATION_INTERNAL_USER_CERT_EXIST	An internal Message Queuing certificate already exists for this user.
0x400E000B MQ_INFORMATION_OWNER_IGNORED	The queue owner was not set during the processing of this call.
0xC00E0001 MQ_ERROR	Generic error code.
0xC00E0002 MQ_ERROR_PROPERTY	One or more of the properties passed are invalid.
0xC00E0003 MQ_ERROR_QUEUE_NOT_FOUND	The queue does not exist or you do not have sufficient permissions to perform the operation.
0xC00E0004 MQ_ERROR_QUEUE_NOT_ACTIVE	The queue is not open or may not exist.
0xC00E0005 MQ_ERROR_QUEUE_EXISTS	A queue with the same path name already exists.
0xC00E0006 MQ_ERROR_INVALID_PARAMETER	An invalid parameter was passed to a function.
0xC00E0007 MQ_ERROR_INVALID_HANDLE	An invalid handle was passed to a function.
0xC00E0008 MQ_ERROR_OPERATION_CANCELLED	The operation was canceled before it could be completed.
0xC00E0009 MQ_ERROR_SHARING_VIOLATION	There is a sharing violation. The queue is already open for exclusive retrieval.
0xC00E000B MQ_ERROR_SERVICE_NOT_AVAILABLE	The Message Queuing service is not available.
0xC00E000D MQ_ERROR_MACHINE_NOT_FOUND	The computer specified cannot be found.
0xC00E0010 MQ_ERROR_ILLEGAL_SORT	The sort operation specified is invalid; for example, there are duplicate columns.
0xC00E0011 MQ_ERROR_ILLEGAL_USER	The user specified is not a valid user.
0xC00E0013	A connection with Active Directory

Return value/code	Description
MQ_ERROR_NO_DS	cannot be established. Verify that there are sufficient permissions to perform this operation.
0xC00E0014 MQ_ERROR_ILLEGAL_QUEUE_PATHNAME	The queue path name specified is invalid.
0xC00E0018 MQ_ERROR_ILLEGAL_PROPERTY_VALUE	The property value specified is invalid.
0xC00E0019 MQ_ERROR_ILLEGAL_PROPERTY_VT	The VARTYPE value specified is invalid.
0xC00E001A MQ_ERROR_BUFFER_OVERFLOW	The buffer supplied for message property retrieval is too small. The message was not removed from the queue, but the part of the message property that was in the buffer was copied.
0xC00E001B MQ_ERROR_IO_TIMEOUT	The time specified to wait for the message elapsed.
0xC00E001C MQ_ERROR_ILLEGAL_CURSOR_ACTION	The MQ_ACTION_PEEK_NEXT value specified cannot be used with the current cursor position.
0xC00E001D MQ_ERROR_MESSAGE_ALREADY_RECEIVED	The message to which the cursor is currently pointing was removed from the queue by another process or by another call without the use of this cursor.
0xC00E001E MQ_ERROR_ILLEGAL_FORMATNAME	The format name specified is invalid.
0xC00E001F MQ_ERROR_FORMATNAME_BUFFER_TOO_SMALL	The format name buffer supplied to the API was too small to hold the format name.
0xC00E0020 MQ_ERROR_UNSUPPORTED_FORMATNAME_OPERATION	Operations of the type requested (for example, deleting a queue using a direct format name) are not supported for the format name specified.
0xC00E0021 MQ_ERROR_ILLEGAL_SECURITY_DESCRIPTOR	The specified security descriptor is invalid.
0xC00E0022 MQ_ERROR_SENDERID_BUFFER_TOO_SMALL	The size of the buffer for the user ID property is too small.
0xC00E0023 MQ_ERROR_SECURITY_DESCRIPTOR_TOO_SMALL	The size of the buffer passed is too small.
0xC00E0024 MQ_ERROR_CANNOT_IMPERSONATE_CLIENT	The security credentials cannot be verified because the RPC server

Return value/code	Description
	cannot impersonate the client application.
0xC00E0025 MQ_ERROR_ACCESS_DENIED	Access is denied.
0xC00E0026 MQ_ERROR_PRIVILEGE_NOT_HELD	The client does not have sufficient security privileges to perform the operation.
0xC00E0027 MQ_ERROR_INSUFFICIENT_RESOURCES	There are insufficient resources to perform this operation.
0xC00E0028 MQ_ERROR_USER_BUFFER_TOO_SMALL	The request failed because the user buffer is too small to hold the information returned.
0xC00E002A MQ_ERROR_MESSAGE_STORAGE_FAILED	A recoverable or journal message could not be stored. The message was not sent.
0xC00E002B MQ_ERROR_SENDER_CERT_BUFFER_TOO_SMALL	The buffer for the user certificate property is too small.
0xC00E002C MQ_ERROR_INVALID_CERTIFICATE	The user certificate is invalid.
0xC00E002D MQ_ERROR_CORRUPTED_INTERNAL_CERTIFICATE	The internal Message Queuing certificate is corrupted.
0xC00E002E MQ_ERROR_INTERNAL_USER_CERT_EXIST	An internal Message Queuing certificate already exists for this user.
0xC00E002F MQ_ERROR_NO_INTERNAL_USER_CERT	No internal Message Queuing certificate exists for the user.
0xC00E0030 MQ_ERROR_CORRUPTED_SECURITY_DATA	A cryptographic function failed.
0xC00E0031 MQ_ERROR_CORRUPTED_PERSONAL_CERT_STORE	The personal certificate store is corrupted.
0xC00E0033 MQ_ERROR_COMPUTER_DOES_NOT_SUPPORT_ENCRYPTION	The computer does not support encryption operations.
0xC00E0035 MQ_ERROR_BAD_SECURITY_CONTEXT	The security context is invalid.
0xC00E0036 MQ_ERROR_COULD_NOT_GET_USER_SID	The SID cannot be obtained from the thread token.
0xC00E0037 MQ_ERROR_COULD_NOT_GET_ACCOUNT_INFO	The account information for the user cannot be obtained.
0xC00E0038 MQ_ERROR_ILLEGAL_MQCOLUMNS	The MQCOLUMNS parameter is invalid.

Return value/code	Description
0xC00E0039 MQ_ERROR_ILLEGAL_PROPID	A property identifier is invalid.
0xC00E003A MQ_ERROR_ILLEGAL_RELATION	A relationship parameter is invalid.
0xC00E003B MQ_ERROR_ILLEGAL_PROPERTY_SIZE	The size of the buffer for the message identifier or correlation identifier is invalid.
0xC00E003C MQ_ERROR_ILLEGAL_RESTRICTION_PROPID	A property identifier specified in MQRESTRICTION is invalid.
0xC00E003D MQ_ERROR_ILLEGAL_MQQUEUEPROPS	Either the pointer to the MQQUEUEPROPS structure has a null value or no properties are specified in it.
0xC00E003E MQ_ERROR_PROPERTY_NOTALLOWED	The property identifier specified is invalid for the operation requested.
0xC00E003F MQ_ERROR_INSUFFICIENT_PROPERTIES	Not all the properties required for the operation were specified for the input parameters.
0xC00E0040 MQ_ERROR_MACHINE_EXISTS	The MSMQ Configuration (msmq) object already exists in Active Directory.
0xC00E0041 MQ_ERROR_ILLEGAL_MQQMPPROPS	Either the pointer to the MQQMPPROPS structure has a null value, or no properties are specified in it.
0xC00E0042 MQ_ERROR_DS_IS_FULL	Valid for MSMQ 1.0 and MSMQ 2.0. Distinguished name (DS) is full.
0xC00E0043 MQ_ERROR_DS_ERROR	There is an internal Active Directory error.
0xC00E0044 MQ_ERROR_INVALID_OWNER	The object owner is invalid.
0xC00E0045 MQ_ERROR_UNSUPPORTED_ACCESS_MODE	The access mode specified is unsupported.
0xC00E0046 MQ_ERROR_RESULT_BUFFER_TOO_SMALL	The result buffer specified is too small.
0xC00E0048 MQ_ERROR_DELETE_CN_IN_USE	Valid for MSMQ 1.0 and MSMQ 2.0. The connected network cannot be deleted; it is in use.
0xC00E0049 MQ_ERROR_NO_RESPONSE_FROM_OBJECT_SERVER	There was no response from the object owner.

Return value/code	Description
0xC00E004A MQ_ERROR_OBJECT_SERVER_NOT_AVAILABLE	The object owner is not available.
0xC00E004B MQ_ERROR_QUEUE_NOT_AVAILABLE	An error occurred while reading from a queue located on a remote computer.
0xC00E004C MQ_ERROR_DTC_CONNECT	A connection cannot be established with the Distributed Transaction Coordinator.
0xC00E004E MQ_ERROR_TRANSACTION_IMPORT	The transaction specified cannot be imported.
0xC00E0050 MQ_ERROR_TRANSACTION_USAGE	An attempted action cannot be performed within a transaction.
0xC00E0051 MQ_ERROR_TRANSACTION_SEQUENCE	The transaction's operation sequence is incorrect.
0xC00E0055 MQ_ERROR_MISSING_CONNECTOR_TYPE	The connector type message property is not specified. This property is required for sending an acknowledgment message or a secure message.
0xC00E0056 MQ_ERROR_STALE_HANDLE	The Message Queuing service was restarted. Any open queue handles should be closed.
0xC00E0058 MQ_ERROR_TRANSACTION_ENLIST	The transaction specified cannot be enlisted.
0xC00E005A MQ_ERROR_QUEUE_DELETED	The queue was deleted. Messages cannot be received anymore using this queue handle. The handle should be closed.
0xC00E005B MQ_ERROR_ILLEGAL_CONTEXT	The context parameter is invalid.
0xC00E005C MQ_ERROR_ILLEGAL_SORT_PROPID	An invalid property identifier is specified in MQSORTSET.
0xC00E005D MQ_ERROR_LABEL_TOO_LONG	The message label is too long. Its length should be less than or equal to MQ_MAX_MSG_LABEL_LEN.
0xC00E005E MQ_ERROR_LABEL_BUFFER_TOO_SMALL	The label buffer supplied to the API is too small.
0xC00E005F MQ_ERROR_MQIS_SERVER_EMPTY	Valid for MSMQ 1.0 and MSMQ 2.0. The list of MQIS servers (in the registry) is empty.
0xC00E0060	Valid for MSMQ 1.0 and MSMQ

Return value/code	Description
MQ_ERROR_MQIS_READONLY_MODE	2.0. The MQIS database is in read-only mode.
0xC00E0061 MQ_ERROR_SYMM_KEY_BUFFER_TOO_SMALL	The buffer passed for the symmetric key is too small.
0xC00E0062 MQ_ERROR_SIGNATURE_BUFFER_TOO_SMALL	The buffer passed for the signature property is too small.
0xC00E0063 MQ_ERROR_PROV_NAME_BUFFER_TOO_SMALL	The buffer passed for the provider name property is too small.
0xC00E0064 MQ_ERROR_ILLEGAL_OPERATION	The operation is invalid for a foreign Message Queuing system.
0xC00E0065 MQ_ERROR_WRITE_NOT_ALLOWED	Another MQIS server is being installed. Write operations to the database are not allowed at this stage.
0xC00E0066 MQ_ERROR_WKS_CANT_SERVE_CLIENT	The MSMQ service cannot be a supporting server. A Message Queuing supporting server is required.
0xC00E0067 MQ_ERROR_DEPEND_WKS_LICENSE_OVERFLOW	The supporting server has reached its limit for accepting application connections.
0xC00E0068 MQ_CORRUPTED_QUEUE_WAS_DELETED	The corresponding file for the designated queue in the Lqs folder was deleted because it was corrupted.
0xC00E0069 MQ_ERROR_REMOTE_MACHINE_NOT_AVAILABLE	The remote computer is not available.
0xC00E006A MQ_ERROR_UNSUPPORTED_OPERATION	This operation is not supported for Message Queuing installed in workgroup mode.
0xC00E006B MQ_ERROR_ENCRYPTION_PROVIDER_NOT_SUPPORTED	The requested cryptographic service provider is not supported by Message Queuing.
0xC00E006C MQ_ERROR_CANNOT_SET_CRYPTO_SEC_DESCR	The security descriptors for the cryptographic keys cannot be set.
0xC00E006D MQ_ERROR_CERTIFICATE_NOT_PROVIDED	A user attempted to send an authenticated message without a certificate.
0xC00E006E MQ_ERROR_Q_DNS_PROPERTY_NOT_SUPPORTED	The column PROPID_Q_PATHNAME_DNS is not supported for the API.
0xC00E006F	A certificate store cannot be

Return value/code	Description
MQ_ERROR_CANNOT_CREATE_CERT_STORE	created for the internal certificate.
0xC00E0070 MQ_ERROR_CANNOT_OPEN_CERT_STORE	The certificate store for the internal certificate cannot be opened.
0xC00E0071 MQ_ERROR_ILLEGAL_ENTERPRISE_OPERATION	This operation is invalid for an MsmqServices object.
0xC00E0072 MQ_ERROR_CANNOT_GRANT_ADD_GUID	The Add GUID permission cannot be granted to the current user.
0xC00E0073 MQ_ERROR_CANNOT_LOAD MSMQOCM	Valid for MSMQ 1.0 and MSMQ 2.0. The dynamic-link library Msmqocm.dll cannot be loaded.
0xC00E0074 MQ_ERROR_NO_ENTRY_POINT_MSMQOCM	An entry point cannot be located in Msmqocm.dll.
0xC00E0075 MQ_ERROR_NO_MSMQ_SERVERS_ON_DC	Message Queuing servers cannot be found on domain controllers.
0xC00E0076 MQ_ERROR_CANNOT_JOIN_DOMAIN	The computer joined the domain, but Message Queuing will continue to run in workgroup mode because it failed to register itself in Active Directory.
0xC00E0077 MQ_ERROR_CANNOT_CREATE_ON_GC	The object was not created on the Global Catalog server specified.
0xC00E0078 MQ_ERROR_GUID_NOT_MATCHING	Valid for MSMQ 1.0 and MSMQ 2.0. Failed to create an msmqConfiguration object with a GUID that matches the computer installation. MSMQ must be uninstalled and then reinstalled.
0xC00E0079 MQ_ERROR_PUBLIC_KEY_NOT_FOUND	The public key for the designated computer cannot be found.
0xC00E007A MQ_ERROR_PUBLIC_KEY_DOES_NOT_EXIST	The public key for the designated computer does not exist.
0xC00E007B MQ_ERROR_ILLEGAL_MQPRIVATEPROPS	The parameters in MQPRIVATEPROPS are invalid. Either the pointer to the MQPRIVATEPROPS structure has a null value or no properties are specified in it.
0xC00E007C MQ_ERROR_NO_GC_IN_DOMAIN	Global Catalog servers cannot be found in the domain specified.
0xC00E007D MQ_ERROR_NO_MSMQ_SERVERS_ON_GC	No Message Queuing servers were found on Global Catalog servers.

Return value/code	Description
0xC00E007E MQ_ERROR_CANNOT_GET_DN	Valid for MSMQ 1.0 and MSMQ 2.0. Failed to retrieve the distinguished name of the local computer.
0xC00E007F MQ_ERROR_CANNOT_HASH_DATA_EX	Data for an authenticated message cannot be hashed.
0xC00E0080 MQ_ERROR_CANNOT_SIGN_DATA_EX	Data cannot be signed before sending an authenticated message.
0xC00E0081 MQ_ERROR_CANNOT_CREATE_HASH_EX	A hash object cannot be created for an authenticated message.
0xC00E0082 MQ_ERROR_FAIL_VERIFY_SIGNATURE_EX	The signature of the message received is not valid.
0xC00E0083 MQ_ERROR_CANNOT_DELETE_PSC_OBJECTS	The delete operation against the designated object failed because the object is owned by a PSC. The operation cannot be performed.
0xC00E0084 MQ_ERROR_NO_MQUSER_OU	There is no MSMQ Users organizational unit object in Active Directory for the domain. Please create one manually.
0xC00E0085 MQ_ERROR_CANNOT_LOAD_MQAD	The dynamic-link library Mqad.dll cannot be loaded.
0xC00E0086 MQ_ERROR_CANNOT_LOAD_MQDSSRV	Obsolete: not used in any version of MSMQ.
0xC00E0087 MQ_ERROR_PROPERTIES_CONFLICT	Two or more of the properties passed cannot coexist.
0xC00E0088 MQ_ERROR_MESSAGE_NOT_FOUND	The message does not exist or was removed from the queue.
0xC00E0089 MQ_ERROR_CANT_RESOLVE_SITES	The sites in which the computer resides cannot be resolved. Verify that the subnets in the network are configured correctly in Active Directory and that each site is configured with the appropriate subnet.
0xC00E008A MQ_ERROR_NOT_SUPPORTED_BY_DEPENDENT_CLIENTS	This operation is not supported for communicating with a supporting server.
0xC00E008B MQ_ERROR_OPERATION_NOT_SUPPORTED_BY_REMOTE_COMPUTER	This operation is not supported by the remote Message Queuing service.
0xC00E008C	The object for which properties

Return value/code	Description
MQ_ERROR_NOT_A_CORRECT_OBJECT_CLASS	were requested from Active Directory does not belong to the class requested.
0xC00E008D MQ_ERROR_MULTI_SORT_KEYS	The value of cCol in MQSORTSET cannot be greater than 1. Active Directory supports only a single sort key.
0xC00E008E MQ_ERROR_GC_NEEDED	An MSMQ Configuration (msmq) object with the GUID supplied cannot be created.
0xC00E008F MQ_ERROR_DS_BIND_ROOT_FOREST	Binding to the forest root failed. This error usually indicates a problem in the DNS configuration.
0xC00E0090 MQ_ERROR_DS_LOCAL_USER	A local user is authenticated as an anonymous user and cannot access Active Directory. The local user must log on as a domain user to access Active Directory.
0xC00E0091 MQ_ERROR_Q_ADS_PROPERTY_NOT_SUPPORTED	The column PROPID_Q_ADS_PATH is not supported for the API.
0xC00E0092 MQ_ERROR_BAD_XML_FORMAT	The given property is not a valid XML document.
0xC00E0093 MQ_ERROR_UNSUPPORTED_CLASS	The Active Directory object specified is not an instance of a supported class.
0xC00E0094 MQ_ERROR_UNINITIALIZED_OBJECT	The MSMQManagement object must be initialized before it is used.
0xC00E0095 MQ_ERROR_CANNOT_CREATE_PSC_OBJECTS	The create object operation cannot be performed because the object must be owned by a PSC.
0xC00E0096 MQ_ERROR_CANNOT_UPDATE_PSC_OBJECTS	The update operation cannot be performed because the designated object is owned by a PSC.
0xC00E0099 MQ_ERROR_RESOLVE_ADDRESS	Message Queuing is not able to resolve the address specified by the user. The address may be wrong or DNS look-up for the address failed.
0xC00E009A MQ_ERROR_TOO_MANY_PROPERTIES	Too many properties passed to the function. Message Queuing can process up to 128 properties in one call.
0xC00E009B	The queue only accepts

Return value/code	Description
MQ_ERROR_MESSAGE_NOT_AUTHENTICATED	authenticated messages.
0xC00E009C MQ_ERROR_MESSAGE_LOCKED_UNDER_TRANSACTION	The message is currently being processed under a transaction. Until the transaction outcome is determined, the message cannot be processed in any other transaction.
0xC00E0504 MQDS_UNKNOWN_SOURCE	The specified MSMQ Directory Service server in the directory change is unknown.

2.5 Message Properties for Digital Signatures

2.5.1 MSMQ 1.0 Digital Signature Properties

The MSMQ 1.0 digital signature MUST be calculated using the values of the following fields in the specified order:

- **MessagePropertiesHeader.CorrelationID**
- **MessagePropertiesHeader.ApplicationTag**
- **MessagePropertiesHeader.MessageBody**
- **MessagePropertiesHeader.Label**
- **UserHeader.ResponseQueue**
- **UserHeader.AdminQueue**

2.5.2 MSMQ 2.0 Digital Signature Properties

The MSMQ 2.0 digital signature MUST be calculated using the values of the following fields in the specified order:

- **MessagePropertiesHeader.CorrelationID**
- **MessagePropertiesHeader.ApplicationTag**
- **MessagePropertiesHeader.MessageBody**
- **MessagePropertiesHeader.Label**
- **UserHeader.ResponseQueue**
- **UserHeader.AdminQueue**
- **UserHeader.SourceQueueManager**
- **([BYTE](#))UserHeader.Flags.DM**
- **([BYTE](#))BaseHeader.Flags.PR**
- **(([BYTE](#))UserHeader.Flags.JP) << 1 | (([BYTE](#))UserHeader.Flags.JN)**

- ((**BYTE**)**MessagePropertiesHeader.Flags**) & 0x0F
- (**USHORT**)**MessagePropertiesHeader.MessageClass**
- (**ULONG**)**MessagePropertiesHeader.BodyType**
- **UserHeader.ConnectorType**
- **UserHeader.DestinationQueue**

2.5.3 MSMQ 3.0 Digital Signature Properties

The MSMQ 3.0 digital signature MUST be calculated using the values of the following fields in the specified order:

- **MessagePropertiesHeader.CorrelationID**
- **MessagePropertiesHeader.ApplicationTag**
- **MessagePropertiesHeader.MessageBody**
- **MessagePropertiesHeader.Label**
- **UserHeader.ResponseQueue**
- **UserHeader.AdminQueue**
- **MessagePropertiesHeader.ExtensionData**
- **MultiQueueFormatHeader.FormatNameList**
- **UserHeader.SourceQueueManager**
- (**BYTE**)**UserHeader.Flags.DM**
- (**BYTE**)**BaseHeader.Flags.PR**
- ((**BYTE**)**UserHeader.Flags.JP**) << 1 | ((**BYTE**)**UserHeader.Flags.JN**)
- ((**BYTE**)**MessagePropertiesHeader.Flags**) & 0x0F
- (**USHORT**)**MessagePropertiesHeader.MessageClass**
- (**ULONG**)**MessagePropertiesHeader.BodyType**
- **UserHeader.ConnectorType**

3 Appendix A: PROPVARIANT IDL

```
import "ms-dtyp.idl";

// forward declaration
typedef tag_inner_PROPVARIANT PROPVARIANT;

// basic type aliases
typedef unsigned long    PROPID;
typedef short           VARIANT_BOOL;

typedef struct {
    unsigned char rgb[16];
} XACTUOW;

typedef struct tagBLOB {
    unsigned long cbSize;
    [size_is(cbSize)]
    unsigned char *pBlobData;
} BLOB;

typedef struct tagCAUB
{
    unsigned long    cElems;
    [size_is( cElems )]
    unsigned char *  pElems;
} CAUB;

typedef struct tagCAUI
{
    unsigned long    cElems;
    [size_is( cElems )]
    unsigned short * pElems;
} CAUI;

typedef struct tagCAL
{
    unsigned long    cElems;
    [size_is( cElems )]
    long *          pElems;
} CAL;

typedef struct tagCAUL
{
    unsigned long    cElems;
    [size_is( cElems )]
    unsigned long *  pElems;
} CAUL;

typedef struct tagCAUH
{
    unsigned long    cElems;
    [size_is( cElems )]
    ULARGE_INTEGER * pElems;
} CAUH;

typedef struct tagCACLSID
```

```

{
    unsigned long    cElems;
    [size_is( cElems )]
    GUID *    pElems;
} CACLSID;

typedef struct tagCALPWSTR
{
    unsigned long    cElems;
    [size_is( cElems )]
    LPWSTR *    pElems;
} CALPWSTR;

typedef struct tagCAPROPVARIANT
{
    unsigned long cElems;
    [size_is( cElems )]
    PROPVARIANT * pElems;
} CAPROPVARIANT;

typedef enum
{
    VT_EMPTY            = 0,
    VT_NULL             = 1,
    VT_I2               = 2,
    VT_I4               = 3,
    VT_BOOL             = 11,
    VT_VARIANT          = 12,
    VT_I1               = 16,
    VT_UI1              = 17,
    VT_UI2              = 18,
    VT_UI4              = 19,
    VT_I8               = 20,
    VT_UI8              = 21,
    VT_LPWSTR           = 31,
    VT_BLOB              = 65,
    VT_CLSID            = 72,

    VT_VECTOR           = 0x1000,
} VARENUM;

typedef unsigned short VARTYPE;

typedef struct _tag_inner_PROPVARIANT
{
    VARTYPE vt;
    UCHAR    wReserved1;
    UCHAR    wReserved2;
    ULONG    wReserved3;
    [switch_is(vt)] union
    {
        [case (VT_EMPTY, VT_NULL)];
        [case (VT_I1)]                CHAR            cVal;
        [case (VT_UI1)]               UCHAR            bVal;
        [case (VT_I2)]                SHORT            iVal;
        [case (VT_UI2)]               USHORT           uiVal;
        [case (VT_I4)]                LONG             lVal;
        [case (VT_UI4)]               ULONG            ulVal;
        [case (VT_I8)]                LARGE_INTEGER    hVal;
    }

```

```

[case (VT_UI8)]           ULARGE_INTEGER  uhVal;
[case (VT_BOOL)]          VARIANT_BOOL    boolVal;
[case (VT_CLSID)]          GUID *          puuid;
[case (VT_BLOB)]           BLOB             blob;
[case (VT_LPWSTR)]         LPWSTR          pwszVal;
[case (VT_VECTOR|VT_UI1)]  CAUB             caub;
[case (VT_VECTOR|VT_UI2)]  CAUI             caui;
[case (VT_VECTOR|VT_I4)]   CAL             cal;
[case (VT_VECTOR|VT_UI4)]  CAUL            caul;
[case (VT_VECTOR|VT_UI8)]  CAUH            cauh;
[case (VT_VECTOR|VT_CLSID)] CACLSID         cauuid;
[case (VT_VECTOR|VT_LPWSTR)] CALPWSTR       calpwstr;
[case (VT_VECTOR|VT_VARIANT)] CAPROPVARIANT capropvar;
    } _varUnion;
} tag_inner_PROPVARIANT;

```

4 Appendix B: Product Behavior

The information in this specification is applicable to the following Microsoft products or supplemental software. References to product versions include released service packs:

- Microsoft Windows NT® operating system
- Microsoft Windows® 2000 operating system
- Windows® XP operating system
- Windows Server® 2003 operating system
- Windows Server® 2008 operating system
- Windows® 7 operating system
- Windows Server® 2008 R2 operating system

Exceptions, if any, are noted below. If a service pack or Quick Fix Engineering (QFE) number appears with the product version, behavior changed in that service pack or QFE. The new behavior also applies to subsequent service packs of the product unless otherwise specified. If a product edition appears with the product version, behavior is different in that product edition.

Unless otherwise specified, any statement of optional behavior in this specification that is prescribed using the terms SHOULD or SHOULD NOT implies product behavior in accordance with the SHOULD or SHOULD NOT prescription. Unless otherwise specified, the term MAY implies that the product does not follow the prescription.

[<1> Section 1.1:](#) The SHA-1 algorithm is not supported by Windows NT and Windows 2000. The SHA-256 and SHA-512 algorithms are not supported by Windows NT, Windows 2000, Windows XP, and Windows Server 2003.

[<2> Section 2.2.18.1.4:](#) Padding bytes contain uninitialized values.

[<3> Section 2.2.18.1.5.2:](#) Padding bytes contain uninitialized values.

[<4> Section 2.2.19.2:](#) Negative source journaling is not supported by Windows NT. Windows Server 2008, Windows 7, and Windows Server 2008 R2 do not perform source journaling for messages sent to administration queues, notification queues, and **order queues**.

[<5> Section 2.2.19.2:](#) Windows stores a copy of the message in the local dead-letter queue on failure to deliver. Transactional messages are copied to the local transactional dead-letter queue. The dead-letter queue is a system-generated queue and is implementation-dependent. Windows Server 2008, Windows 7, and Windows Server 2008 R2 do not perform source journaling for messages sent to administration queues, notification queues, and order queues.

[<6> Section 2.2.19.2:](#) Windows copies the message to the system journal queue. The journal queue is a system-generated queue and is implementation-dependent. Windows Server 2008, Windows 7, and Windows Server 2008 R2 do not perform source journaling for messages sent to administration queues, notification queues, and order queues.

[<7> Section 2.2.19.3:](#) 40-bit and 128-bit encryption is not supported by Windows NT. AES encryption is not supported by Windows XP, Windows Server 2003, Windows 2000, or Windows NT.

<8> [Section 2.2.19.3](#): The SHA-1 hash algorithm is not supported by Windows NT and Windows 2000. The SHA-256 and SHA-512 hash algorithms are not supported by Windows NT, Windows 2000, Windows XP, and Windows Server 2003. As a security enhancement, the default hash algorithm has been set to a stronger one, as described in the following list:

- Windows NT and Windows 2000 default to MD5 (0x00008003).
- Windows XP, Windows Server 2003, Windows Vista, and Windows Server 2008 default to SHA-1 (0x00008004).
- Windows 7 and Windows Server 2008 R2 default to SHA-512 (0x0000800E).

<9> [Section 2.2.19.3](#): Windows pads the [MessagePropertiesHeader](#) packet with uninitialized data.

<10> [Section 2.2.20.1](#): The [MultiQueueFormatHeader](#) is not supported by Windows 2000 or Windows NT.

<11> [Section 2.2.20.1](#): Padding bytes contain uninitialized values.

<12> [Section 2.2.20.1](#): Padding bytes contain uninitialized values.

<13> [Section 2.2.20.1](#): Padding bytes contain uninitialized values.

<14> [Section 2.2.20.2](#): Padding bytes contain uninitialized values.

<15> [Section 2.2.20.4](#): Coding errors present in Windows can prevent the **UserMsgSequenceNumber** from being set to the count of [UserMessage Packets](#) sent on a session.

<16> [Section 2.2.20.4](#): If a destination queue manager encounters a memory allocation error while processing a message, it sets the window size to 1 in the outgoing [SessionHeader](#) header, which causes the destination queue manager to reduce its window to the same size. The source queue manager doubles the window size every 30 seconds until the window size returns to the default value of 64.

<17> [Section 2.2.20.4](#): The maximum allowed value of this field can be configured by setting a value in the registry key HKEY_LOCAL_MACHINE\software\microsoft\msmq\parameters\MaxUnackedPacket. When this key is absent, the default maximum is 64.

<18> [Section 2.2.20.4](#): The maximum allowed value of this field can be configured by setting a value in the registry key HKEY_LOCAL_MACHINE\software\microsoft\msmq\parameters\MaxUnackedPacket. When this key is absent, the default maximum is 64.

<19> [Section 2.2.20.5](#): The **TransactionHeader.Flags.FM** and **TransactionHeader.Flags.LM** fields are not supported by Windows NT.

<20> [Section 2.2.20.6](#): The default cryptographic provider for MSMQ on Windows XP and Windows Server 2003 is "Microsoft Base Cryptographic Provider v1.0" as described in [\[MSDN-BCP\]](#). The default cryptographic provider for MSMQ on Windows Vista, Windows Server 2008, Windows 7, and Windows Server 2008 R2 is "Microsoft AES Cryptographic Provider" as described in [\[MSDN-ACP\]](#).

<21> [Section 2.2.20.6](#): Windows stores the queue manager public key in the MSMQ-Encrypt-Key attribute of the **queue manager's** MSMQ-Configuration object in Active Directory (AD). During the **queue manager** startup, this value is queried once using the **Lightweight Directory Access Protocol (LDAP)**.

<22> [Section 2.2.20.6](#): The application may choose any of the currently available Microsoft cryptographic service providers (CSPs). The list of available Microsoft CSPs as well as the type and the name of each CSP are described in [\[MSDN-CSP\]](#).

<23> [Section 2.2.20.6](#): The application may choose any of the currently available Microsoft cryptographic service providers (CSPs) listed in [\[MSDN-CSP\]](#).

<24> [Section 2.2.20.8](#): To enable report messages, ensure that there is a registry key of type **DWORD** called HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\MSMQ\Parameters\Security\EnableReportMessages and that its value is set to 1.

<25> [Section 2.3.1.5](#): When the property is not set, the storage size of a queue is limited only by the available disk space on the local computer or the computer quota. For Windows XP Professional, there is no default computer quota. For Windows 2000, the default computer quota is 2 gigabytes. For the Windows Server 2003 family, the default computer quota is 8 gigabytes. For Windows Vista, Windows Server 2008, Windows 7, and Windows Server 2008 R2, the default computer quota is 4 gigabytes.

<26> [Section 2.3.1.7](#): When the property is not set, the storage size of a queue is limited only by the available disk space on the local computer or by the journal quota. For Windows 2000, the default journal quota is 2 gigabytes. For Windows XP Professional, there is no default journal quota. For the Windows Server 2003 family, the default journal quota is 8 gigabytes. For Windows Vista, Windows Server 2008, Windows 7, and Windows Server 2008 R2, the default journal quota is 4 gigabytes.

<27> [Section 2.3.1.16](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) and the collocated Message Queuing (MSMQ): Directory Service Protocol [\[MS-MQDS\]](#) server for directory service replication among MSMQ Directory Service servers.

<28> [Section 2.3.1.25](#): The security descriptor ACE **AceType** fields are limited to those supported by Windows NT 4.0 ([\[MS-DTYP\]](#) section 2.4.4.1).

<29> [Section 2.3.2.11](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) and the collocated Message Queuing (MSMQ): Directory Service Protocol [\[MS-MQDS\]](#) server for directory service replication among MSMQ Directory Service servers.

<30> [Section 2.3.2.15](#): Windows Server 2003, Windows Vista, Windows Server 2008, Windows 7, and Windows Server 2008 R2 accept an empty string.

<31> [Section 2.3.2.15](#): Windows NT, Windows 95, Windows 98, and Windows 2000 require the following format in ABNF notation.

```
MachineType = WindowsLiteral Space OStype Space UInt "."
              UInt Space "(" BuildLiteral Space UInt "," Space Platform ")"
              Space "-" Space MSMQLiteral Space UInt "." UInt Space
              "(" BuildLiteral Space UInt ")"
WindowsLiteral = %x57 %x69 %x6e %x64 %x6f %x77 %x73
BuildLiteral = %x42 %x75 %x69 %x6c %x64
MSMQLiteral = %x4d %x53 %x4d %x51
OStype = *(%x20-7E)
Platform = *(%x20-7E)
UInt = *(%x30-39)
Space = %x20
```

<32> [Section 2.3.2.36](#): The security descriptor ACE **AceType** fields are limited to those supported by Windows NT 4.0 ([\[MS-DTYP\]](#) section 2.4.4.1).

<33> [Section 2.3.3.7](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) for directory service replication among MSMQ Directory Service servers.

<34> [Section 2.3.3.13](#): The security descriptor ACE **AceType** fields are limited to those supported by Windows NT 4.0 ([\[MS-DTYP\]](#) section 2.4.4.1).

<35> [Section 2.3.4.4](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) for directory service replication among MSMQ Directory Service servers.

<36> [Section 2.3.4.6](#): The security descriptor ACE **AceType** fields are limited to those supported by Windows NT 4.0 ([\[MS-DTYP\]](#) section 2.4.4.1).

<37> [Section 2.3.5.2](#): Windows 2000, Windows XP, Windows Server 2003, Windows Vista, Windows Server 2008, Windows 7, and Windows Server 2008 R2 use an internal default equivalent to setting this value to 0x00.

<38> [Section 2.3.5.7](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) for directory service replication among MSMQ Directory Service servers.

<39> [Section 2.3.5.17](#): The security descriptor ACE **AceType** fields are limited to those supported by Windows NT 4.0 ([\[MS-DTYP\]](#) section 2.4.4.1).

<40> [Section 2.3.6.2](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) for directory service replication among MSMQ Directory Service servers.

<41> [Section 2.3.7.4](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) for directory service replication among MSMQ Directory Service servers.

<42> [Section 2.3.8.6](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) for directory service replication among MSMQ Directory Service servers.

<43> [Section 2.3.9.5](#): The security descriptor ACE **AceType** fields are limited to those supported by Windows NT 4.0 ([\[MS-DTYP\]](#) section 2.4.4.1).

<44> [Section 2.3.13.2](#): This property is used only by Windows NT and Windows 2000 operating in MSMQ mixed-mode in the Message Queuing (MSMQ): Directory Service Replication Protocol [\[MC-MQDSRP\]](#) for directory service replication among MSMQ Directory Service servers.

<45> [Section 2.4](#): For more information about MSMQ-specific HRESULT values, see [\[MSDN-MQEIC\]](#).

5 Change Tracking

This section identifies changes that were made to the [MS-MQMQ] protocol document between the May 2011 and June 2011 releases. Changes are classified as New, Major, Minor, Editorial, or No change.

The revision class **New** means that a new document is being released.

The revision class **Major** means that the technical content in the document was significantly revised. Major changes affect protocol interoperability or implementation. Examples of major changes are:

- A document revision that incorporates changes to interoperability requirements or functionality.
- An extensive rewrite, addition, or deletion of major portions of content.
- The removal of a document from the documentation set.
- Changes made for template compliance.

The revision class **Minor** means that the meaning of the technical content was clarified. Minor changes do not affect protocol interoperability or implementation. Examples of minor changes are updates to clarify ambiguity at the sentence, paragraph, or table level.

The revision class **Editorial** means that the language and formatting in the technical content was changed. Editorial changes apply to grammatical, formatting, and style issues.

The revision class **No change** means that no new technical or language changes were introduced. The technical content of the document is identical to the last released version, but minor editorial and formatting changes, as well as updates to the header and footer information, and to the revision summary, may have been made.

Major and minor changes can be described further using the following change types:

- New content added.
- Content updated.
- Content removed.
- New product behavior note added.
- Product behavior note updated.
- Product behavior note removed.
- New protocol syntax added.
- Protocol syntax updated.
- Protocol syntax removed.
- New content added due to protocol revision.
- Content updated due to protocol revision.
- Content removed due to protocol revision.
- New protocol syntax added due to protocol revision.

- Protocol syntax updated due to protocol revision.
- Protocol syntax removed due to protocol revision.
- New content added for template compliance.
- Content updated for template compliance.
- Content removed for template compliance.
- Obsolete document removed.

Editorial changes are always classified with the change type **Editorially updated**.

Some important terms used in the change type descriptions are defined as follows:

- **Protocol syntax** refers to data elements (such as packets, structures, enumerations, and methods) as well as interfaces.
- **Protocol revision** refers to changes made to a protocol that affect the bits that are sent over the wire.

The changes made to this document are listed in the following table. For more information, please contact protocol@microsoft.com.

Section	Tracking number (if applicable) and description	Major change (Y or N)	Change type
1.2 References	Added explanatory statement regarding the removal of the publishing year from Microsoft Open Specification document references.	N	Content updated.
2.1.1 Path Names	64778 Replaced all vertical line characters (" ") with forward slashes ("/") in the ABNF production rules for the QueuePathName, QueueName, and Subqueue tokens.	N	Content updated.
2.1.2 Direct Format Names	64778 Replaced all vertical line characters (" ") with forward slashes ("/") in the ABNF production rules for the DirectName, MachineQueuePath, Subqueue, and Protocol tokens.	N	Content updated.
2.1.3 Public Format Names	64778 Replaced all vertical line characters (" ") with forward slashes ("/") in the ABNF production rule for the HexDig token.	N	Content updated.
2.1.7 Multiple-Element Format Names	64778 Replaced all vertical line characters (" ") with forward slashes ("/") in the ABNF production rule for the FormatName token.	N	Content updated.

6 Index

A

[Applicability](#) 18

B

[BaseHeader packet](#) 45

[BLOB structure](#) 35

C

[CACLSID structure](#) 37

[CAL structure](#) 36

[CALPWSTR structure](#) 37

[CAPROPVARIANT structure](#) 37

[CAUB structure](#) 36

[CAUH structure](#) 37

[CAUI structure](#) 36

[CAUL structure](#) 36

[Change tracking](#) 136

[Computer property identifiers](#) 105

[Connected network property identifiers](#) 94

[Connector format names](#) 22

[COUNTEDARRAY](#) 35

D

[DebugHeader packet](#) 68

[Definitions](#) 19

[Direct format names](#) 20

[DirectQueueFormatName packet](#) 41

[Distribution list format names](#) 22

[DL ID structure](#) 31

E

[Enterprise object property identifiers](#) 95

[Error codes](#) 117

F

[Fields - vendor-extensible](#) 18

[Full IDL](#) 129

G

[Glossary](#) 10

I

[IDL](#) 129

[Informative references](#) 17

[Introduction](#) 10

[IP Address packet](#) 26

[IPX Address packet](#) 26

L

[Localization](#) 18

M

[Machine format names](#) 22

[Machine property identifiers](#) 84

[Management machine property identifiers](#) 107

[Management queue property identifiers](#) 108

[MESSAGE_CLASS_VALUES enumeration](#) 41

[MessageIdentifier packet](#) 39

[MessagePropertiesHeader packet](#) 51

[MQCNACCESSMASK enumeration](#) 77

[MQDSPUBLICKEY packet](#) 24

[MQDSPUBLICKEYS packet](#) 24

[MQENTACCESSMASK enumeration](#) 75

[MQFAddressHeader packet](#) 58

[MQFDirectQueueFormatName packet](#) 40

[MQFDistributionQueueFormatName packet](#) 40

[MQFFormatNameElement packet](#) 39

[MQFSignatureHeader packet](#) 59

[MQQMACCESSMASK enumeration](#) 71

[MQQUEUEFACCESSMASK enumeration](#) 73

[MQSITEACCESSMASK enumeration](#) 74

[MQUser property identifiers](#) 104

[MOUSERSIGNCERT packet](#) 70

[MOUSERSIGNCERTS packet](#) 70

[Multicast format names](#) 22

[MULTICAST ID structure](#) 31

[Multiple-element format names](#) 23

[MultiQueueFormatHeader packet](#) 57

N

[Normative references](#) 16

O

[OBJECTID structure](#) 31

P

[Path names](#) 19

[Private format names](#) 21

[PrivateQueueFormatName packet](#) 44

[PrivateQueueFormatNameId packet](#) 41

[Product behavior](#) 132

Property identifiers

[computer](#) 105

[connected network](#) 94

[enterprise object](#) 95

[machine](#) 84

[management machine](#) 107

[management queue](#) 108

[MQUser](#) 104

[queue](#) 78

[settings](#) 101

[site](#) 91

[sitelink](#) 99

[user object](#) 98
[PROPID_CN_SECURITY](#) 95
[PROPID_MQU_ID](#) 105
[PROPID_CN_GUID](#) 94
[PROPID_CN_NAME](#) 94
[PROPID_CN_PARTITIONID](#) 95
[PROPID_CN_PROTOCOLID](#) 94
[PROPID_CN_SEQNUM](#) 95
[PROPID_COM_ACCOUNT_CONTROL](#) 106
[PROPID_COM_DIGEST](#) 106
[PROPID_COM_DNS_HOSTNAME](#) 106
[PROPID_COM_FULL_PATH](#) 105
[PROPID_COM_ID](#) 106
[PROPID_COM_SAM_ACCOUNT](#) 105
[PROPID_COM_SID](#) 106
[PROPID_COM_SIGN_CERT](#) 106
[PROPID_D_IDENTIFIER](#) 117
[PROPID_D_PARTITIONID](#) 116
[PROPID_D_SEQNUM](#) 116
[PROPID_E_ID](#) 97
[PROPID_E_CIPHER_MODE](#) 98
[PROPID_E_CRL](#) 97
[PROPID_E_CSP_NAME](#) 96
[PROPID_E_CSP_TYPE](#) 97
[PROPID_E_ENCRYPT_ALG](#) 97
[PROPID_E_HASH_ALG](#) 97
[PROPID_E_LONG_LIVE](#) 97
[PROPID_E_NAME](#) 95
[PROPID_E_NAMESTYLE](#) 95
[PROPID_E_PARTITIONID](#) 96
[PROPID_E_PECNAME](#) 96
[PROPID_E_S_INTERVAL1](#) 96
[PROPID_E_S_INTERVAL2](#) 96
[PROPID_E_SECURITY](#) 98
[PROPID_E_SEQNUM](#) 96
[PROPID_E_SIGN_ALG](#) 97
[PROPID_E_VERSION](#) 98
[PROPID_L_ACTUAL_COST](#) 101
[PROPID_L_COST](#) 100
[PROPID_L_DESCRIPTION](#) 101
[PROPID_L_FULL_PATH](#) 101
[PROPID_L_GATES](#) 101
[PROPID_L_GATES_DN](#) 100
[PROPID_L_ID](#) 100
[PROPID_L_NEIGHBOR1](#) 99
[PROPID_L_NEIGHBOR1_DN](#) 100
[PROPID_L_NEIGHBOR2](#) 99
[PROPID_L_NEIGHBOR2_DN](#) 101
[PROPID_L_PARTITIONID](#) 100
[PROPID_L_SEQNUM](#) 100
[PROPID_MGMT_MSMQ_ACTIVEQUEUES](#) 107
[PROPID_MGMT_MSMQ_BYTES_IN_ALL_QUEUES](#) 108
[PROPID_MGMT_MSMQ_CONNECTED](#) 107
[PROPID_MGMT_MSMQ_DSSERVER](#) 107
[PROPID_MGMT_MSMQ_PRIVATEQ](#) 107
[PROPID_MGMT_MSMQ_TYPE](#) 108
[PROPID_MGMT_QUEUE_SUBQUEUE_COUNT](#) 116
[PROPID_MGMT_QUEUE_SUBQUEUE_NAMES](#) 116
[PROPID_MGMT_QUEUE_BYTES_IN_JOURNAL](#) 110
[PROPID_MGMT_QUEUE_BYTES_IN_QUEUE](#) 110

[PROPID_MGMT_QUEUE_CONNECTION_HISTORY](#) 114
[PROPID_MGMT_QUEUE_EOD_FIRST_NON_ACK](#) 112
[PROPID_MGMT_QUEUE_EOD_LAST_ACK](#) 111
[PROPID_MGMT_QUEUE_EOD_LAST_ACK_COUNT](#) 112
[PROPID_MGMT_QUEUE_EOD_LAST_ACK_TIME](#) 112
[PROPID_MGMT_QUEUE_EOD_LAST_NON_ACK](#) 112
[PROPID_MGMT_QUEUE_EOD_NEXT_SEQ](#) 112
[PROPID_MGMT_QUEUE_EOD_NO_ACK_COUNT](#) 113
[PROPID_MGMT_QUEUE_EOD_NO_READ_COUNT](#) 112
[PROPID_MGMT_QUEUE_EOD_RESEND_COUNT](#) 113
[PROPID_MGMT_QUEUE_EOD_RESEND_INTERVAL](#) 113
[PROPID_MGMT_QUEUE_EOD_RESEND_TIME](#) 113
[PROPID_MGMT_QUEUE_EOD_SOURCE_INFO](#) 113
[PROPID_MGMT_QUEUE_FOREIGN](#) 109
[PROPID_MGMT_QUEUE_FORMATNAME](#) 108
[PROPID_MGMT_QUEUE_JOURNAL_MESSAGE_COUNT](#) 110
[PROPID_MGMT_QUEUE_LOCATION](#) 109
[PROPID_MGMT_QUEUE_MESSAGE_COUNT](#) 110
[PROPID_MGMT_QUEUE_NEXTHOPS](#) 111
[PROPID_MGMT_QUEUE_PATHNAME](#) 108
[PROPID_MGMT_QUEUE_STATE](#) 110
[PROPID_MGMT_QUEUE_TYPE](#) 108
[PROPID_MGMT_QUEUE_XACT](#) 109
[PROPID_MQU_DIGEST](#) 105
[PROPID_MQU_SECURITY](#) 105
[PROPID_MQU_SID](#) 104
[PROPID_MQU_SIGN_CERT](#) 104
[PROPID_Q_ADS_PATH](#) 83
[PROPID_Q_AUTHENTICATE](#) 80
[PROPID_Q_BASEPRIORITY](#) 79
[PROPID_Q_CREATE_TIME](#) 80
[PROPID_Q_FULL_PATH](#) 82
[PROPID_Q_HASHKEY](#) 82
[PROPID_Q_INSTANCE](#) 78
[PROPID_Q_JOURNAL](#) 79
[PROPID_Q_JOURNAL_QUOTA](#) 79
[PROPID_Q_LABEL](#) 79
[PROPID_Q_LABEL_HASHKEY](#) 82
[PROPID_Q_MODIFY_TIME](#) 80
[PROPID_Q_MULTICAST_ADDRESS](#) 82
[PROPID_Q_NAME_SUFFIX](#) 82
[PROPID_Q_OBJ_SECURITY](#) 83
[PROPID_Q_PARTITIONID](#) 81
[PROPID_Q_PATHNAME](#) 78
[PROPID_Q_PATHNAME_DNS](#) 82
[PROPID_Q_PRIV_LEVEL](#) 80
[PROPID_Q_QMID](#) 81
[PROPID_Q_QUOTA](#) 79
[PROPID_Q_SCOPE](#) 81
[PROPID_Q_SECURITY](#) 83
[PROPID_Q_SECURITY_INFORMATION](#) 83
[PROPID_Q_SEQNUM](#) 81
[PROPID_Q_TRANSACTION](#) 81
[PROPID_Q_TYPE](#) 78
[PROPID_QM_CNS](#) 84
[PROPID_QM_CREATE_TIME](#) 86

[PROPID_QM_FOREIGN](#) 86
[PROPID_QM_FULL_PATH](#) 87
[PROPID_QM_INFRS_DN](#) 88
[PROPID_QM_JOURNAL_QUOTA](#) 86
[PROPID_QM_MODIFY_TIME](#) 86
[PROPID_QM_OS](#) 87
[PROPID_QM_OUTFRS_DN](#) 88
[PROPID_QM_QUOTA](#) 85
[PROPID_QM_SERVICE_ROUTING](#) 88
[PROPID_QM_SITE_IDS](#) 87
[PROPID_QM_ADDRESS](#) 84
[PROPID_QM_ENCRYPT_PK](#) 91
[PROPID_QM_ENCRYPT_PKS](#) 89
[PROPID_QM_ENCRYPTION_PK](#) 84
[PROPID_QM_ENCRYPTION_PK_BASE](#) 89
[PROPID_QM_ENCRYPTION_PK_ENHANCED](#) 89
[PROPID_QM_GROUP_IN_CLUSTER](#) 90
[PROPID_QM_HASHKEY](#) 86
[PROPID_QM_INFRS](#) 85
[PROPID_QM_MACHINE_ID](#) 84
[PROPID_QM_MACHINE_TYPE](#) 86
[PROPID_QM_OBJ_SECURITY](#) 89
[PROPID_QM_OUTFRS](#) 85
[PROPID_QM_OWNER_SID](#) 90
[PROPID_QM_PARTITIONID](#) 85
[PROPID_QM_PATHNAME](#) 84
[PROPID_QM_PATHNAME_DNS](#) 89
[PROPID_QM_SECURITY](#) 90
[PROPID_QM_SECURITY_INFORMATION](#) 89
[PROPID_QM_SEQNUM](#) 86
[PROPID_QM_SERVICE](#) 85
[PROPID_QM_SERVICE_DEPCLIENTS](#) 88
[PROPID_QM_SERVICE_DSSERVER](#) 88
[PROPID_QM_SIGN_PK](#) 91
[PROPID_QM_SIGN_PKS](#) 90
[PROPID_QM_SITE_ID](#) 84
[PROPID_QM_UPGRADE_DACL](#) 91
[PROPID_S_SECURITY_INFORMATION](#) 94
[PROPID_S_DONOTHING](#) 93
[PROPID_S_FOREIGN](#) 93
[PROPID_S_FULL_NAME](#) 92
[PROPID_S_GATES](#) 91
[PROPID_S_INTERVAL1](#) 92
[PROPID_S_INTERVAL2](#) 92
[PROPID_S_NT4_STUB](#) 93
[PROPID_S_PARTITIONID](#) 92
[PROPID_S_PATHNAME](#) 91
[PROPID_S_PSC](#) 92
[PROPID_S_PSC_SIGNPK](#) 94
[PROPID_S_SECURITY](#) 93
[PROPID_S_SEQNUM](#) 92
[PROPID_S_SITEID](#) 91
[PROPID_SET_FULL_PATH](#) 102
[PROPID_SET_NAME](#) 102
[PROPID_SET_NT4](#) 102
[PROPID_SET_OLDSERVICE](#) 104
[PROPID_SET_PARTITIONID](#) 103
[PROPID_SET_QM_ID](#) 102
[PROPID_SET_SERVICE](#) 102
[PROPID_SET_SERVICE_DEPCLIENTS](#) 104
[PROPID_SET_SERVICE_DSSERVER](#) 103

[PROPID_SET_SERVICE_ROUTING](#) 103
[PROPID_SET_SITENAME](#) 103
[PROPID_U_DIGEST](#) 99
[PROPID_U_ID](#) 99
[PROPID_U_PARTITIONID](#) 98
[PROPID_U_SEQNUM](#) 99
[PROPID_U_SID](#) 98
[PROPID_U_SIGN_CERT](#) 99
[PROPVARIANT](#) 33
[PTA_ADDRESS](#) 25
[Public format names](#) 21
[PublicQueueFormatName packet](#) 43

Q

[Queue names](#) 19
[Queue property identifiers](#) 78
[QUEUE_FORMAT structure](#) 28
[QUEUE_FORMAT_TYPE enumeration](#) 28
[QUEUE_SUFFIX_TYPE enumeration](#) 31

R

References
 [informative](#) 17
 [normative](#) 16
[Relationship to other protocols](#) 18

S

[SecurityHeader packet](#) 63
[SEQUENCE_INFO packet](#) 27
[SEQUENCE_INFO structure](#) 27
[SessionHeader packet](#) 60
[Settings property identifiers](#) 101
[Site property identifiers](#) 91
[Sitelink property identifiers](#) 99
[SoapHeader packet](#) 67

Structures

[discussed](#) 24
 [overview](#) 19

T

[TA_ADDRESS structure](#) 25
[tag_inner_PROPVARIANT structure](#) 34
[Tracking changes](#) 136
[TransactionHeader packet](#) 61
[TxSequenceID packet](#) 38

U

[ULARGE_INTEGER structure](#) 38
[User object property identifiers](#) 98
[UserHeader packet](#) 47
[UserMessage packet](#) 55

V

[VARENUM enumeration](#) 32
[Vendor-extensible fields](#) 18
[Versioning](#) 18

X

[XACTUOW structure](#) 44