

[MS-POP3]: NT LAN Manager (NTLM) Authentication: Post Office Protocol - Version 3 (POP3) Extension

Intellectual Property Rights Notice for Protocol Documentation

- This protocol documentation is covered by Microsoft copyrights. Regardless of any other terms that are contained in the terms of use for the Microsoft website that hosts this documentation, you may make copies of it in order to develop implementations of the protocols, and may distribute portions of it in your implementations of the protocols or your documentation as necessary to properly document the implementation. This permission also applies to any documents that are referenced in the protocol documentation.
- Microsoft does not claim any trade secret rights in this documentation.
- Microsoft has patents that may cover your implementations of the protocols. Neither this notice nor Microsoft's delivery of the documentation grants any licenses under those or any other Microsoft patents. If you are interested in obtaining a patent license, please contact protocol@microsoft.com.
- The names of companies and products contained in this documentation may be covered by trademarks or similar intellectual property rights. This notice does not grant any licenses under those rights.
- All other rights are reserved, and this notice does not grant any rights other than specifically described above, whether by implication, estoppel, or otherwise.

This protocol documentation is intended for use in conjunction with publicly available standard specifications, network programming art, and Microsoft Windows distributed systems concepts, and assumes that the reader either is familiar with the aforementioned material or has immediate access to it.

A protocol specification does not require the use of Microsoft programming tools or programming environments in order for you to develop an implementation. If you have access to Microsoft programming tools and environments you are free to take advantage of them.

Revision Summary

Date	Revision History	Revision Class	Comments
07/20/2007	0.1	Major	MCPPE Milestone 5 Initial Availability
09/28/2007	1.0	Major	Updated and revised the technical content.
10/23/2007	1.0.1	Editorial	Revised and edited the technical content.

Date	Revision History	Revision Class	Comments
11/30/2007	1.0.2	Editorial	Revised and edited the technical content.
01/25/2008	1.0.3	Editorial	Revised and edited the technical content.

Table of Contents

1	Introduction	5
1.1	Glossary	5
1.2	References	6
1.2.1	Normative References	6
1.2.2	Informative References.....	7
1.3	Protocol Overview (Synopsis).....	7
1.4	Relationship to Other Protocols.....	8
1.5	Prerequisites/Preconditions	9
1.6	Applicability Statement	9
1.7	Versioning and Capability Negotiation.....	9
1.8	Vendor-Extensible Fields	9
1.9	Standards Assignments.....	9
2	Messages	10
2.1	Transport	10
2.2	Message Syntax	10
2.2.1	AUTH Extensions	10
2.2.2	POP3 Server Messages	12
2.2.3	POP3 Client Messages.....	12
3	Protocol Details	14
3.1	Client Details	14
3.1.1	Abstract Data Model	14
3.1.1.1	POP3 State Model.....	14
3.1.1.2	NTLM Subsystem Interaction.....	15
3.1.2	Timers	16
3.1.3	Initialization	16
3.1.4	Higher-Layer Triggered Events.....	16
3.1.5	Message Processing Events and Sequencing Rules	16
3.1.5.1	Receiving a POP3_NTLM_Supported_Response Message.....	16
3.1.5.2	Receiving a POP3_AUTH_NTLM_Fail_Response Message.....	16
3.1.5.3	Receiving a POP3_NTLM_Blob_Response.....	16
3.1.5.3.1	Error from NTLM	16
3.1.5.3.2	NTLM Reports Success and Returns an NTLM Message.....	17
3.1.5.4	Receiving a POP3_AUTH_Succeeded_Response Message	17
3.1.5.5	Receiving a POP3_AUTH_NTLM_Fail_Response	17
3.1.6	Timer Events.....	17
3.1.7	Other Local Events	17
3.2	Server Details.....	18
3.2.1	Abstract Data Model	18
3.2.1.1	POP3 State Model.....	18
3.2.1.2	NTLM Subsystem Interaction.....	19
3.2.2	Timers	20
3.2.3	Initialization	20
3.2.4	Higher-Layer Triggered Events.....	20
3.2.5	Message Processing Events and Sequencing Rules	20
3.2.5.1	Receiving a POP3_AUTH_NTLM_Initiation_Command Message	20
3.2.5.2	Receiving a POP3_AUTH_NTLM_Blob_Command Message.....	20
3.2.5.2.1	NTLM Returns Success, Returning an NTLM Message.....	20
3.2.5.2.2	NTLM Returns Success, Indicating Authentication Completed Successfully	21
3.2.5.2.3	NTLM Returns Status, Indicating User Name or Password Was Incorrect	21
3.2.5.2.4	NTLM Returns a Failure Status, Indicating Any Other Error.....	21

3.2.5.2.5	NTLM Reports Success, Returning an NTLM Message	21
3.2.6	Timer Events.....	21
3.2.7	Other Local Events.....	21
4	Protocol Examples	22
4.1	POP3 Client Successfully Authenticating to a POP3 Server	22
4.2	POP3 Client Unsuccessfully Authenticating to a POP3 Server	23
5	Security	26
5.1	Security Considerations for Implementers	26
5.2	Index of Security Parameters	26
6	Appendix A: Windows Behavior	27
7	Index.....	28

1 Introduction

The NT LAN Manager (NTLM) Authentication: Post Office Protocol–Version 3 (POP3) Extension specifies the use of **NTLM** authentication (see [\[MS-NLMP\]](#)) by the Post Office Protocol 3 (POP3) to facilitate client authentication to a Windows POP3 server. POP3 specifies a protocol for the inquiry and retrieval of electronic mail. For a detailed definition of POP3, see [\[RFC1939\]](#).

Note For the purposes of this document, "NT LAN Manager (NTLM) Authentication: Post Office Protocol–Version 3 (POP3) Extension" will be referred to in subsequent sections as "NTLM POP3 Extension".

The NTLM POP3 Extension uses the POP3 **AUTH command** (see [\[RFC1734\]](#)) to negotiate NTLM authentication and to send authentication data.

1.1 Glossary

The following terms are defined in [\[MS-GLOS\]](#):

NT LAN Manager Protocol (NTLM)

The following terms are specific to this document:

AUTH Command: A Post Office Protocol 3 (POP3) optional command that is used to send authentication information as specified in [\[RFC1734\]](#). The "mechanism" name defined in the RFC is **NTLM**. The structure of the **AUTH command** as used in [\[MS-POP3\]](#) is as follows:

```
AUTH NTLM<CR><LF>
```

Connection-Oriented NTLM: One of the two variants of the [Windows NT LAN Manager \(NTLM\) Authentication Protocol](#).

NTLM AUTHENTICATE_MESSAGE: A packet that defines an **NTLM** Authenticate message that is sent from the client to the server after the CHALLENGE_MESSAGE is processed by the client. Message structure and other details of this packet are specified in [\[MS-NLMP\]](#) section 2.2.1.3.

NTLM CHALLENGE_MESSAGE: A packet that defines an **NTLM** Challenge message that is sent from the server to the client. The CHALLENGE_MESSAGE is generated by the local **NTLM software** and passed to the application that supports embedded **NTLM** authentication. This message is used by the server to challenge the client to prove its identity. Message structure and other details of this packet are specified in [\[MS-NLMP\]](#) section 2.2.1.2.

NTLM Message: A message that carries authentication information. Its payload data is passed to the application that supports embedded **NTLM** authentication by the **NTLM software** installed on the local computer. **NTLM messages** are transmitted between the client and server embedded within the application protocol that is using **NTLM** authentication. There are three types of **NTLM messages**:

- **NTLM NEGOTIATE_MESSAGE**
- **NTLM CHALLENGE_MESSAGE**
- **NTLM AUTHENTICATE_MESSAGE**

NTLM NEGOTIATE_MESSAGE: A packet that defines an **NTLM** Negotiate message that is sent from the client to the server. The NEGOTIATE_MESSAGE is generated by the local **NTLM**

software and passed to the application that supports embedded **NTLM** authentication. This message allows the client to specify its supported **NTLM** options to the server. Message structure and other details are specified in [\[MS-NLMP\]](#) section 2.2.1.1.

NTLM Software: Software that implements the Windows NT LAN Manager (NTLM) Authentication Protocol.

POP3 Response: A message sent by a POP3 server in response to a message from a POP3 client. The structure of this message, as specified in [\[RFC1939\]](#), is as follows:

```
<+OK> <response text><CR><LF>
```

Or:

```
<-ERR><response text><CR><LF>
```

MAY, SHOULD, MUST, SHOULD NOT, MUST NOT: These terms (in all caps) are used as described in [\[RFC2119\]](#). All statements of optional behavior use either MAY, SHOULD, or SHOULD NOT.

1.2 References

1.2.1 Normative References

We conduct frequent surveys of the normative references to assure their continued availability. If you have any issue with finding a normative reference, please contact dochelp@microsoft.com. We will assist you in finding the relevant information. Please check the archive site, <http://msdn2.microsoft.com/en-us/library/E4BD6494-06AD-4aed-9823-445E921C9624>, as an additional source.

[MS-NLMP] Microsoft Corporation, "[NT LAN Manager \(NTLM\) Authentication Protocol Specification](#)", June 2007.

[RFC1521] Borenstein, N., and Freed, N., "MIME (Multipurpose Internet Mail Extensions) Part One: Mechanisms for Specifying and Describing the Format of Internet Message Bodies", RFC 1521, September, 1993, <http://www.ietf.org/rfc/rfc1521.txt>

[RFC1734] Myers, J., "POP3 AUTHentication Command", RFC 1734, December 1994, <http://www.ietf.org/rfc/rfc1734.txt>

[RFC1939] Myers, J. and Rose, M., "Post Office Protocol—Version 3", RFC 1939, May 1996, <http://www.ietf.org/rfc/rfc1939.txt>

[RFC2045] Freed, N., et al., "Multipurpose Internet Mail Extensions (MIME) Part One: Format of Internet Message Bodies", RFC 2045, November 1996, <http://ietf.org/rfc/rfc2045.txt>

[RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997, <http://www.ietf.org/rfc/rfc2119.txt>

[RFC4234] Crocker, D., Ed. and Overell, P., "Augmented BNF for Syntax Specifications: ABNF", RFC 4234, October 2005, <http://www.ietf.org/rfc/rfc4234.txt>

1.2.2 Informative References

[SSPI] Microsoft Corporation, "SSPI", <http://msdn2.microsoft.com/en-us/library/aa380493.aspx>

1.3 Protocol Overview (Synopsis)

Client applications that connect to the Post Office Protocol 3 (POP3) service included in Windows Server 2003 can use either standard plaintext authentication, as specified in [RFC1939], or Windows NT LAN Manager (NTLM) authentication.

The NTLM POP3 Extension specifies how a POP3 client and POP3 server can use the Windows NT LAN Manager (NTLM) Authentication Protocol, as specified in [MS-NLMP], so that the POP3 server can authenticate the POP3 client. NTLM is a challenge/response authentication protocol that depends on the application layer protocols to transport NTLM packets from client to server, and from server to client.

This specification defines how the POP3 Authentication command [RFC1734] is used to perform authentication using the NTLM authentication protocol. The POP3 Authentication command standard defines an extensibility mechanism for arbitrary authentication protocols to be plugged into the core protocol.

This specification describes an embedded protocol in which NTLM authentication data is first transformed into a base64 representation, and then formatted by padding with POP3 keywords as defined by the AUTH mechanism. The base64 encoding and the formatting is very rudimentary, and solely intended to make the NTLM data fit the framework specified in [RFC1734]. The following diagram illustrates the sequence of transformations performed on an **NTLM message** to produce a message that can be sent over POP3.




Figure 1: Relationship between NTLM message and POP3: NTLM Authentication Protocol message

This specification describes a pass-through protocol that does not specify the structure of NTLM information. Instead, the protocol relies on the software that implements the NTLM Authentication Protocol (as specified in [MS-NLMP]) to process each NTLM message to be sent or received.

This specification defines a server and a client role.

When POP3 performs an NTLM authentication, it needs to interact with the NTLM subsystem appropriately. Below is an overview of this interaction.

If acting as a POP3 client:

1. The NTLM subsystem returns the first NTLM message to the client, to be sent to the server.
2. The client should apply the base64-encoding and POP3-padding transformations mentioned earlier and described in detail later in this document to produce a POP3 message and send this message to the server.

3. The client should wait for a response from the server. When the response is received, it checks to see whether it indicates the end of authentication (success or failure), or that authentication is continuing.
4. If the authentication is continuing, the response message is stripped of the POP3 padding, base64 decoded, and passed into the NTLM subsystem, upon which the NTLM subsystem may return another NTLM message that needs to be sent to the server. Steps 3 through 5 are repeated until authentication succeeds or fails.

If acting as a POP3 server:

1. The server then waits to receive the first POP3 authentication message from the client.
2. When a POP3 message is received from the client, the POP3 padding is removed, the message is base64 decoded, and the resulting NTLM message is passed into the NTLM subsystem.
3. The NTLM subsystem will return a status indicating whether authentication completed successfully, failed, or whether more NTLM messages need to be exchanged to complete the authentication.
4. If the authentication is continuing, the NTLM subsystem will return an NTLM message that needs to be sent to the server. This message is base64-encoded, the POP3 padding is applied and sent to the client. Steps 2 through 4 are repeated until authentication succeeds or fails.

The sequence that follows shows the typical flow of packets between client and server once NTLM authentication has been selected.

1. The POP3 client sends an **NTLM NEGOTIATE_MESSAGE** embedded in a [POP3 AUTH NTLM Blob Command](#) packet to the server.
2. On receiving the POP3 packet with an NTLM NEGOTIATE_MESSAGE, the POP3 server sends an **NTLM CHALLENGE_MESSAGE** embedded in a POP3 packet to the client.
3. In response, the POP3 client sends an **NTLM AUTHENTICATE_MESSAGE** embedded in a POP3 packet.
4. The server then sends a **POP3 Response** to the client to successfully complete the authentication process.

The NTLM NEGOTIATE_MESSAGE, NTLM CHALLENGE_MESSAGE, and NTLM AUTHENTICATE_MESSAGE packets contain NTLM authentication data that must be processed by the **NTLM software** installed on the local computer. How to retrieve and process NTLM messages is specified in [MS-NLMP].

Implementers of this specification must possess a working knowledge of the following:

- POP3, as specified in [RFC1734](#) and [RFC1939](#).
- The Multipurpose Internet Mail Extensions (MIME) base64 encoding method, as specified in [RFC1521](#).
- The NTLM Authentication Protocol, as specified in [MS-NLMP].

1.4 Relationship to Other Protocols

The NTLM POP3 Extension uses the POP3 AUTH extension mechanism, as specified in [RFC1734](#), and is an embedded protocol. Unlike standalone application protocols, such as Telnet or Hypertext

Transfer Protocol (HTTP), packets for this specification are embedded in POP3 commands and server responses.

POP3 specifies only the sequence in which a POP3 server and POP3 client must exchange NTLM messages to successfully authenticate the client to the server. It does not specify how the client obtains NTLM messages from the local NTLM software, or how the POP3 server should process NTLM messages. The POP3 client and POP3 server implementations depend on the availability of an implementation of the NTLM Authentication Protocol (as specified in [MS-NLMP]) to obtain and process NTLM messages and on the availability of the base64 encoding and decoding mechanisms (as specified in [RFC1521]) to encode and decode the NTLM messages embedded in POP3 packets.

1.5 Prerequisites/Preconditions

Because POP3 depends on NTLM to authenticate the client to the server, both server and client must have access to an implementation of the NTLM Authentication Protocol (as specified in [MS-NLMP]) that is capable of supporting **connection-oriented NTLM**.<1>

1.6 Applicability Statement

The NTLM POP3 Extension must be used only when implementing a POP3 client that needs to authenticate to a POP3 server by using NTLM authentication.

1.7 Versioning and Capability Negotiation

This document covers versioning issues in the following areas:

- Security and Authentication Methods: The NTLM POP3 Extension supports the NTLMv1 and NTLMv2 authentication methods, as specified in [MS-NLMP].
- Capability Negotiation: POP3 does not support negotiation of which version of the NTLM Authentication Protocol to use. Instead, the NTLM Authentication Protocol version must be configured on both the client and the server prior to authentication. NTLM Authentication Protocol version mismatches are handled by the NTLM Authentication Protocol implementation, not by POP3.

The client discovers whether the server supports NTLM AUTH through the AUTH command, issued without any arguments (through a mechanism described in [AUTH Extensions \(section 2.2.1\)](#)), upon which the server responds with a list of supported authentication mechanisms followed by a line containing only a period (.). If NTLM is supported, the server will list the word "NTLM" in the list. The messages involved are formally described in other sections of this document in section [2.2](#).

1.8 Vendor-Extensible Fields

The NTLM POP3 Extension does not have any vendor-extensible fields.

1.9 Standards Assignments

The NTLM POP3 Extension does not use any standards assignments.

2 Messages

The following sections specify how the NTLM POP3 Extension messages are transported and NTLM POP3 Extension message syntax.

2.1 Transport

The NTLM POP3 Extension does not establish transport connections. Instead, NTLM POP3 Extension messages are encapsulated in POP3 commands and responses. How NTLM POP3 Extension messages must be encapsulated in POP3 commands is specified in section [2.2](#).

2.2 Message Syntax

The NTLM POP3 Extension messages are divided into the three categories, depending on whether the message was sent by the server or the client:

- AUTH extensions
- POP3 server messages
- POP3 client messages

2.2.1 AUTH Extensions

The first category of POP3 messages is messages that fall within the AUTH extensibility framework. These messages are specified in [\[RFC1734\]](#). Some messages have parameters that must be customized by the extensibility mechanism (such as NTLM). The following customizations are introduced by this document:

- A client can query the server to see if NTLM is supported. This is accomplished by issuing the AUTH command without any parameters. This is shown in ABNF (for more information on ABNF, see [\[RFC4234\]](#)) in the following example:

```
AUTH<CR><LF>
```

- The server responds to this message with a message followed by a list of supported authentication mechanisms, followed by a list termination message. This sequence is shown in ABNF format in the example below:

```
+OK<CR><LF>  
NTLM<CR><LF>  
.<CR><LF>
```

- [\[RFC1734\]](#) section 2 defines the syntax of the AUTH command to initiate authentication. The parameter "mechanism" is defined to be the string "NTLM" for NTLM POP3 Extension. The command to initiate an NTLM conversation by a client in ABNF is shown in the following example. This is referred to as POP3_AUTH_NTLM_Initiation_Command in this document.

```
AUTH NTLM<CR><LF>
```

- If NTLM is supported, the POP3 server will respond with a POP3 message to indicate that NTLM is supported. The syntax of this command in ABNF form is shown in the following example. This is referred to as POP3_NTLM_Supported_Response in this document.

```
+OK<CR><LF>
```

- If NTLM is not supported, the POP3 server returns a failure status code as defined by [\[RFC1734\]](#). The only data in this message that is useful is the -ERR. The remaining data is human-readable data and has no bearing on the authentication. The syntax of this command in ABNF form is shown in the following example. This is referred to as POP3_AUTH_NTLM_Fail_Response in this document.

```
-ERR <human_readable_string> <CR><LF>
```

- At every point of time during the authentication exchange, the client must parse the responses in the messages sent by the server and interpret them as defined by [\[RFC1734\]](#). The responses define various states such as success in authenticating, failure to authenticate, and any other arbitrary failures that the software may encounter.

The client may receive any one of the following responses during authentication. Note that the syntax and meaning of all these messages are completely defined by [\[RFC1734\]](#).

- POP3_AUTH_NTLM_Blob_Response: This message is partially defined in [\[RFC1734\]](#). The '+' status code indicates ongoing authentication, and indicates that the <base64-encoded-NTLM-message> is to be processed by the authentication subsystem. In this case, the client must de-encapsulate the data, and pass it to the NTLM subsystem.

```
+ < base64-encoded-NTLM-message><CR><LF>
```

- POP3_AUTH_NTLM_Fail_Response: This message is defined in [\[RFC1734\]](#) and indicates that the authentication has terminated unsuccessfully, either because the username or password was incorrect, or due to some other arbitrary error such as a software or data corruption error.

```
-ERR <human-readable-string><CR><LF>
```

- POP3_AUTH_NTLM_Succeeded_Response: This message is defined in [\[RFC1734\]](#) and indicates that the authentication negotiation has completed with the client successfully authenticating to the server.

```
+OK <human-readable-string><CR><LF>
```

- POP3_AUTH_NTLM_Cancelled_Response: This message is defined in [\[RFC1734\]](#) and indicates that the authentication negotiation has been canceled with the client.

```
+ERR <human-readable-string><CR><LF>
```

- NTLM messages encapsulated by the client and sent to the server, are referred to as POP3_AUTH_NTLM_Blob_Command in this document. They have the following syntax defined in ABNF, and conform to the prescription of [\[RFC1734\]](#).

```
< base64-encoded-NTLM-message><CR><LF>
```

- The client is able to cancel the authentication request by issuing a POP3_AUTH_Cancellation_Command. This has the following syntax defined in ABNF.

```
*<CR><LF>
```

2.2.2 POP3 Server Messages

This section defines the creation of POP3_AUTH_NTLM_Blob_Response messages. These are NTLM messages sent by the server and must be encapsulated as follows to conform to syntax specified by the AUTH mechanism.

1. Base64-encode the NTLM message data. This is needed because NTLM messages contain data outside the ASCII character range, whereas POP3 only supports ASCII characters.
2. To the base64-encoded string, prefix the POP3 response code with a plus sign (+).
3. Suffix the <CR> and <LF> character (ASCII values 0x0D and 0x0A) as required by POP3.

The ABNF definition of a server message is as follows:

```
+ <base64-encoded-NTLM-message><CR><LF>
```

De-encapsulation of these messages by the client follows the reverse logic:

1. Remove the <CR> and <LF> character (ASCII values 0x0D and 0x0A).
2. Remove the POP3 response code (+).
3. Decode the base64-encoded POP3 data to produce the original NTLM message data.

2.2.3 POP3 Client Messages

This section defines the processing of POP3_AUTH_NTLM_Blob_Command messages. These NTLM messages sent by the client are encapsulated as follows to conform to the AUTH mechanism:

1. base64-encode the NTLM message data. This is needed because NTLM messages contain data outside the ASCII character range whereas POP3 only supports ASCII characters.
2. Send the base64-encoded string.
3. Suffix the <CR> and <LF> character (ASCII values 0x0D and 0x0A) as required by POP3.

The ABNF definition of a client message is as follows:

```
<base64-encoded-NTLM-message><CR><LF>
```

De-encapsulation of these messages by the client follows the reverse logic:

1. Remove the <CR> and <LF> character (ASCII values 0x0D and 0x0A).
2. Base64-decode the POP3 data to produce the original NTLM message data.

3 Protocol Details

3.1 Client Details

3.1.1 Abstract Data Model

3.1.1.1 POP3 State Model




Figure 2: Client POP3 state model

The abstract data model for NTLM POP3 Extension has the following states:

1. Start:
This is the state of the client before the POP3_AUTH_Initiation_Command has been sent.
2. State 2: sent_authentication_request.
This is the state of the client after the POP3_AUTH_Initiation_Command has been sent.
3. State 1: inside_authentication.
This is the state entered by a client after it has received a POP3_NTLM_Supported_Command. In this state, the client initializes the NTLM subsystem and repeats the following steps:

- Encapsulates the NTLM message, returned by the NTLM subsystem, into a POP3 message.
- Waits for a response from the server.
- De-encapsulates received POP3 message data (if any) from the other party and converts it to NTLM message data.
- Passes it to the NTLM subsystem.
- Sends the POP3 message to the other party.

This state terminates when:

- For the server: The NTLM subsystem reports completion with either a success or failed authentication status, upon which it sends the client and POP3_AUTH_NTLM_Succeeded_Response or POP3_AUTH_NTLM_Fail_Response as specified in [\[RFC1734\]](#).
- For the client: a POP3_AUTH_NTLM_Succeeded_Response or POP3_AUTH_NTLM_Fail_Response is received.
- For either client or server: when any failure is reported by the NTLM subsystem.

4. Stop: completed_authentication.

This is the state of the client on exiting the inside_authentication state. The rules for how the inside_authentication state are exited are defined in section [3.1.5](#). The behavior of POP3 in this state is not in the scope of this document—it represents the end state of the authentication protocol.

3.1.1.2 NTLM Subsystem Interaction

During inside_authentication phase, the POP3 client invokes the NTLM subsystem as described in [\[MS-NLMP\]](#) section 3.1. The NTLM protocol is used with these options:

1. The negotiation is a connection-oriented NTLM negotiation.
2. None of the flags specified in [\[MS-NLMP\]](#) section 3.1.1 are specific to NTLM.

The following is a description of how POP3 uses NTLM. All NTLM messages are encapsulated as specified in section [2.1](#). [\[MS-NLMP\]](#) section 3.1.1 describes the data model, internal states, and sequencing of NTLM messages in greater detail:

1. The client initiates the authentication by invoking NTLM, upon which NTLM will return the NTLM NEGOTIATE_MESSAGE to be sent to the server.
2. Subsequently, the exchange of NTLM messages goes on as defined by the NTLM protocol, with the POP3 client encapsulating the NTLM messages before sending them to the server, and de-encapsulating POP3 messages to obtain the NTLM message before giving it to NTLM.
3. The NTLM protocol completes authentication, either successfully or unsuccessfully, as follows:
 - The server sends the POP3_AUTH_NTLM_Succeeded_Response to the client. On receiving this message, the client transitions to the completed_authentication state and should treat the authentication attempt as successful.

- The server sends the POP3_AUTH_NTLM_Fail_Response to the client. On receiving this message, the client transitions to the completed_authentication state and should treat the authentication attempt as failed.
- Failures reported from the NTLM package (which can occur for any reason, including incorrect data being passed in, or implementation-specific errors), may be reported to the client by NTLM and cause the client to transition to the completed_authentication state.

3.1.2 Timers

None.

3.1.3 Initialization

None.

3.1.4 Higher-Layer Triggered Events

None.

3.1.5 Message Processing Events and Sequencing Rules

The NTLM POP3 Extension is driven by a series of message exchanges between a POP3 server and a POP3 client. The rules governing the sequencing of commands and the internal states of the client and server are defined by a combination of [\[RFC1734\]](#) and [\[MS-NLMP\]](#). Section [3.1.1](#) completely defines how the rules specified in [\[RFC1734\]](#) and [\[MS-NLMP\]](#) govern POP3 authentication.

3.1.5.1 Receiving a POP3_NTLM_Supported_Response Message

The expected state is sent_authentication_request.

On receiving this message, a client MUST generate the first NTLM message by calling the NTLM subsystem. The NTLM subsystem then generates NTLM NEGOTIATE_MESSAGE as specified in [\[MS-NLMP\]](#). The NTLM message is then encapsulated as defined previously and sent to the server.

The state of the client is changed to "inside_authentication".

3.1.5.2 Receiving a POP3_AUTH_NTLM_Fail_Response Message

The expected state is sent_authentication_request.

On receiving this message, a client MUST abort the NTLM authentication attempt.

3.1.5.3 Receiving a POP3_NTLM_Blob_Response

The expected state is inside_authentication.

On receiving this message, a client must de-encapsulate it to obtain the embedded NTLM message, and pass it to the NTLM subsystem for processing. The NTLM subsystem may then either report an error, or report success and return an NTLM message to be sent to the server.

3.1.5.3.1 Error from NTLM

If the NTLM subsystem reports an error, the client must change its internal state to "completed_authentication" and consider that the authentication has failed. The client may then

take any action it considers appropriate; this document does not mandate any specific course of action.

Typical actions are to attempt other (non-authentication-related) POP3 commands, or to disconnect the connection.

3.1.5.3.2 NTLM Reports Success and Returns an NTLM Message

The NTLM message should be encapsulated and sent to the server. No change occurs in the state of the client.

3.1.5.4 Receiving a POP3_AUTH_Succeeded_Response Message

Expected state: inside_authentication

The POP3 client must change its internal state to completed_authentication and consider that the authentication has succeeded. The client may then take any action it considers appropriate. This document does not mandate any specific course of action.

3.1.5.5 Receiving a POP3_AUTH_NTLM_Fail_Response

Expected state: inside_authentication.

The POP3 client must change its internal state to completed_authentication and consider that the authentication has failed. The client may then take any action it considers appropriate; this document does not mandate any specific course of action.

3.1.6 Timer Events

None.

3.1.7 Other Local Events

None.

3.2 Server Details

3.2.1 Abstract Data Model

3.2.1.1 POP3 State Model




Figure 3: Server POP3 state model

The abstract data model for NTLM POP3 Extension has the following states:

1. Start

This is the state of the server before the `POP3_AUTH_NTLM_Initiation_Command` has been received.

2. State 2: `received_authentication_request`.

This is the state of the client after the `POP3_AUTH_NTLM_Initiation_Command` has been received.

3. State 1: `inside_authentication`.

This is the state entered by a server after it has sent a POP3_NTLM_Supported_Response. In this state, the server initializes the NTLM subsystem and repeats the following steps:

- Waits for a message from the client.
- De-encapsulates received POP3 message-data party and obtains the embedded NTLM message data.
- Passes it to the NTLM subsystem.
- Encapsulates the NTLM message returned by the NTLM subsystem into a POP3 message.
- Sends the POP3 message to the other party.

This state terminates when:

- The NTLM subsystem reports completion with either a success or failed authentication status, upon which it sends the client and POP3_AUTH_NTLM_Succeeded_Response or POP3_AUTH_NTLM_Fail_Response, as specified in [\[RFC1734\]](#).
- Any failure is reported by the NTLM subsystem.

4. Stop: completed_authentication.

This is the state of the server on exiting the inside_authentication state. The rules for how the inside_authentication state are exited are defined in section [3.2.5](#). The behavior of POP3 in this state is defined in [\[RFC1734\]](#)—it represents the end_state of the authentication protocol.

3.2.1.2 NTLM Subsystem Interaction

During inside_authentication state, the POP3 server invokes the NTLM subsystem as specified in [\[MS-NLMP\]](#) section 3.1.1. The NTLM protocol is used with the following options:

1. The negotiation is a connection-oriented NTLM negotiation.
2. None of the flags specified in [\[MS-NLMP\]](#) section 3.1.1 are specific to NTLM.

What follows is a description of how POP3 uses NTLM. For further details, see [\[MS-NLMP\]](#) section 3.1.1, which describes the data-model and sequencing of NTLM packets in greater detail:

1. The server on receiving the NTLM NEGOTIATE_MESSAGE passes it to the NTLM subsystem and is returned the NTLM CHALLENGE_MESSAGE, if the NTLM NEGOTIATE_MESSAGE was valid.
2. Subsequently, the exchange of NTLM messages goes on as defined by the NTLM protocol, with the POP3 server encapsulating the NTLM messages returned by NTLM before sending them to the client.
3. When the NTLM protocol completes authentication, either successfully or unsuccessfully, the NTLM subsystem notifies POP3.
 - On successful completion the server MUST exit the inside_authentication state and enter the completed_authentication state and send the POP3_AUTH_NTLM_Succeeded_Response to the client. On receiving this message, the client MUST also transition to the completed_authentication state.
 - If a failure occurs due to an incorrect password error, as described in [\[MS-NLMP\]](#) section 3.3.1 and [3.3.2](#), the server should enter the completed_authentication state and send the client a POP3_AUTH_NTLM_Fail_Response message.

- If a failure occurs on the server due to any other reason than the incorrect password error the server enters the completed_authentication state and sends the client a POP3_AUTH_NTLM_Fail_Response message. On receiving this message the client must enter the completed_authentication state.

3.2.2 Timers

None.

3.2.3 Initialization

None.

3.2.4 Higher-Layer Triggered Events

None.

3.2.5 Message Processing Events and Sequencing Rules

The NTLM POP3 Extension is driven by a series of message exchanges between a POP3 server and a POP3 client. The rules governing the sequencing of commands and the internal states of the client and server are defined by a combination of [\[RFC1734\]](#) and [\[MS-NLMP\]](#). Section [3.1.1](#) completely defines how the rules specified in [\[RFC1734\]](#) and [\[MS-NLMP\]](#) govern POP3 authentication.

3.2.5.1 Receiving a POP3_AUTH_NTLM_Initiation_Command Message

The expected state is start.

On receiving this message, the server must reply with the POP3_NTLM_Supported_Response, if it supports NTLM, and change its state to the inside_authentication state.

If the server does not support NTLM, it must respond with the POP3_AUTH_NTLM_Fail_Response, and the internal state remains unchanged.

3.2.5.2 Receiving a POP3_AUTH_NTLM_Blob_Command Message

The expected state is inside_authentication.

On receiving this message, a server must de-encapsulate the message, obtain the embedded NTLM message, and pass it to the NTLM subsystem. The NTLM subsystem may:

1. Report success in processing the message and return an NTLM message to continue authentication.
2. Report that authentication completed successfully.
3. Report that authentication failed due to a bad user name or password, as specified in [\[MS-NLMP\]](#).
4. Report that the authentication failed due to some other software error or message corruption.

3.2.5.2.1 NTLM Returns Success, Returning an NTLM Message

The NTLM message must be encapsulated and sent to the client. The internal state of the POP3 server remains unchanged.

3.2.5.2.2 NTLM Returns Success, Indicating Authentication Completed Successfully

The server must return the POP3_AUTH_NTLM_Succeeded_Response and change its internal state to completed_authentication.

3.2.5.2.3 NTLM Returns Status, Indicating User Name or Password Was Incorrect

The server must return the POP3_AUTH_NTLM_Fail_Response and change its internal state to completed_authentication.

3.2.5.2.4 NTLM Returns a Failure Status, Indicating Any Other Error

The server must return the POP3_AUTH_NTLM_Fail_Response and change its internal state to completed_authentication.

3.2.5.2.5 NTLM Reports Success, Returning an NTLM Message

The NTLM message should be encapsulated and sent to the server. No change occurs in the state of the client.

3.2.6 Timer Events

None.

3.2.7 Other Local Events

None.

4 Protocol Examples

The following section describes operations used in a common scenario to illustrate the function of the Post Office Protocol 3 (POP3).

4.1 POP3 Client Successfully Authenticating to a POP3 Server

This section illustrates the NTLM POP3 Extension with a scenario in which a POP3 client successfully authenticates to a POP3 server using NTLM.




Figure 4: POP3 client successfully authenticating to POP3 server

1. The client sends a `POP3_AUTH_NTLM_Initiation_Command` to the server. This command is specified in [\[RFC1734\]](#) and does not carry any POP3-specific data. It is included in this example to provide a better understanding of the POP3 NTLM initiation command.

AUTH NTLM

2. The server sends the `POP3_NTLM_Supported_Response` message, indicating that it can perform NTLM authentication.

+OK

3. The client sends a `POP3_AUTH_NTLM_Blob_Command` message containing a base64-encoded NTLM `NEGOTIATE_MESSAGE`.

```
TlRMTVNTUAAABAAA4IIogAAAAAAAAAAAAAAAAAFASgKAAADw==
```

```
00000000:4e 54 4c 4d 53 53 50 00 01 00 00 00 07 82 08 a2    NTLMSSP....., .ç
00000010:00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00    .....
00000020:05 01 28 0a 00 00 00 0f                                ..(.....
```

4. The server sends a POP3_AUTH_NTLM_Blob_Response message containing a base64-encoded NTLM CHALLENGE_MESSAGE.

```
+ TlRMTVNTUAAACAAAFAAUADgAAAAFgoqinziKqGYjdlEAAAAAAAAAGQAZABMAAABQ
LODgAAAA9UAEUUAwBUAFMARQBSAFYARQBSAAIAFABUAEUUAwBUAFMARQBSAFYARQBSAA
EAFABUAEUUAwBUAFMARQBSAFYARQBSAAQAFABUAGUAcwB0AFMAZQByAHYAZQByAAMAFA
BUAGUAcwB0AFMAZQByAHYAZQByAAAAA=
00000000:4e 54 4c 4d 53 53 50 00 02 00 00 00 14 00 14 00    NTLMSSP.....
00000010:38 00 00 00 05 82 8a a2 9f 38 8a a8 66 23 76 51    8.....,ŠçY8Š`f#vQ
00000020:00 00 00 00 00 00 00 00 64 00 64 00 4c 00 00 00    .....d.d.L...
00000030:05 02 ce 0e 00 00 00 0f 54 00 45 00 53 00 54 00    ..Î.....T.E.S.T.
00000040:53 00 45 00 52 00 56 00 45 00 52 00 02 00 14 00    S.E.R.V.E.R.....
00000050:54 00 45 00 53 00 54 00 53 00 45 00 52 00 56 00    T.E.S.T.S.E.R.V.
00000060:45 00 52 00 01 00 14 00 54 00 45 00 53 00 54 00    E.R.....T.E.S.T.
00000070:53 00 45 00 52 00 56 00 45 00 52 00 04 00 14 00    S.E.R.V.E.R.....
00000080:54 00 65 00 73 00 74 00 53 00 65 00 72 00 76 00    T.e.s.t.S.e.r.v.
00000090:65 00 72 00 03 00 14 00 54 00 65 00 73 00 74 00    e.r.....T.e.s.t.
000000a0:53 00 65 00 72 00 76 00 65 00 72 00 00 00 00 00    S.e.r.v.e.r.....
```

5. The client sends a POP3_AUTH_NTLM_Blob_Command message containing a base64-encoded NTLM AUTHENTICATE_MESSAGE.

```
TlRMTVNTUAAADAAAAGAAAYAGIAAAAYABgAegAAAAAAAAABIAAACAAIAEgAAAASABIAUAAA
AAAAAACSAABYKIOgUBKAoAAAAPdQBzAGUAcgBOAEYALQBDAEwASQBFAE4AVABKMiQ4
djhcSgAAAAAAAAAAAAAAAAAAC7zUSgB0Auy98bRi6h3mwHMJfbKNtxmmo=
00000000:4e 54 4c 4d 53 53 50 00 03 00 00 00 18 00 18 00    NTLMSSP.....
00000010:62 00 00 00 18 00 18 00 7a 00 00 00 00 00 00 00    b.....z.....
00000020:48 00 00 00 08 00 08 00 48 00 00 00 12 00 12 00    H.....H.....
00000030:50 00 00 00 00 00 00 00 92 00 00 00 05 82 88 a2    P.....',.....,^ç
00000040:05 01 28 0a 00 00 00 0f 75 00 73 00 65 00 72 00    ..(.....u.s.e.r.
00000050:4e 00 46 00 2d 00 43 00 4c 00 49 00 45 00 4e 00    N.F.-.C.L.I.E.N.
00000060:54 00 4a 32 24 38 76 38 5c 4a 00 00 00 00 00 00    T.J2$8v8\J.....
00000070:00 00 00 00 00 00 00 00 00 00 bb cd 44 a0 07 40    .....»ÍD .@
00000080:2e cb df 1b 46 2e a1 de 6c 07 30 97 db 28 db 71    .Ëß.F.;¡l.0-Û(Ûq
00000090:9a 6a                                                šj
```

6. The server sends a POP3_AUTH_NTLM_Succeeded_Response message.

```
+OK User successfully logged on
```

4.2 POP3 Client Unsuccessfully Authenticating to a POP3 Server

This section illustrates the NTLM POP3 Extension with a scenario in which a POP3 client attempts NTLM authentication to a POP3 server and the authentication fails.




Figure 5: Client unsuccessfully authenticating to POP3 server

The client sends a POP3_AUTH_NTLM_Initiation_Command to the server. This command is defined in [\[RFC1734\]](#) and does not carry any POP3-specific data. It is included in this example to provide a better understanding.

The server sends the POP3_NTLM_Supported_Response message, indicating that it can perform NTLM authentication.

The client sends a POP3_AUTH_NTLM_Blob_Command message.

1. The client sends a POP3_AUTH_NTLM_Blob_Command message containing a base-64-encoded NTLM NEGOTIATE_MESSAGE.

```

TlRMTVNTUAABAAAAB4IIogAAAAAAAAAAAAAAAAAAAAAAAAAFASgKAAADw==

00000000:4e 54 4c 4d 53 53 50 00 01 00 00 00 07 82 08 a2  NTLMSSP....., .c
00000010:00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  ..
00000020:05 01 28 0a 00 00 00 0f  ..(.....
  
```

2. The server sends a POP3_AUTH_NTLM_Blob_Response message containing a base64-encoded NTLM CHALLENGE_MESSAGE.

```

+ TlRMTVNTUAACAAAFAAUADgAAAFgoqieUWd5ES4Bi0AAAAAAAAAGQAZABMAA
AABQLODgAAAA9UAEUAUwBUAFMARQBSAFYARQBSAAIAFABUAEUAUwBUAFMARQBSAF
YARQBSAAEFABUAEUAUwBUAFMARQBSAFYARQBSAAQAFABUAGUAcwB0AFMAZQByAH
YAZQByAAMAFABUAGUAcwB0AFMAZQByAHYAZQByAAAAAA=

00000000:4e 54 4c 4d 53 53 50 00 02 00 00 00 14 00 14 00  NTLMSSP.....
00000010:38 00 00 00 05 82 8a a2 79 45 9d e4 44 b8 06 2d  8....,ŠcyEüäd,.-
  
```



```

00000020:00 00 00 00 00 00 00 00 64 00 64 00 4c 00 00 00 .....d.d.L...
00000030:05 02 ce 0e 00 00 00 0f 54 00 45 00 53 00 54 00 ..î.....T.E.S.T.
00000040:53 00 45 00 52 00 56 00 45 00 52 00 02 00 14 00 S.E.R.V.E.R....
00000050:54 00 45 00 53 00 54 00 53 00 45 00 52 00 56 00 T.E.S.T.S.E.R.V.
00000060:45 00 52 00 01 00 14 00 54 00 45 00 53 00 54 00 E.R.....T.E.S.T.
00000070:53 00 45 00 52 00 56 00 45 00 52 00 04 00 14 00 S.E.R.V.E.R....
00000080:54 00 65 00 73 00 74 00 53 00 65 00 72 00 76 00 T.e.s.t.S.e.r.v.
00000090:65 00 72 00 03 00 14 00 54 00 65 00 73 00 74 00 e.r.....T.e.s.t.
000000a0:53 00 65 00 72 00 76 00 65 00 72 00 00 00 00 00 S.e.r.v.e.r....

```

3. The client sends a POP3_AUTH_NTLM_Blob_Command message containing a base-64-encoded NTLM AUTHENTICATE_MESSAGE.

```

TlRMTVNTUAADAAAAGAAYAGIAAAAYABgAegAAAAAAAAABIAAAACAAIAEgAAAASABIA
UAAAAAAAAACSAAAABYKIogUBKAoAAAAAPdQBzAGUAcgBOAEYALQBDAEwASQBF4E4A
VAAOArJ6lZ5ZNwAAAAAAAAAAAAAAAAACD9mD8jmWs4FkZe59/nNb1cF2HkL0C
GZw=
00000000:4e 54 4c 4d 53 53 50 00 03 00 00 00 18 00 18 00 NTLMSSP.....
00000010:62 00 00 00 18 00 18 00 7a 00 00 00 00 00 00 00 b.....z.....
00000020:48 00 00 00 08 00 08 00 48 00 00 00 12 00 12 00 H.....H.....
00000030:50 00 00 00 00 00 00 00 92 00 00 00 05 82 88 a2 P.....',....,^ç
00000040:05 01 28 0a 00 00 00 0f 75 00 73 00 65 00 72 00 ..(.....u.s.e.r.
00000050:4e 00 46 00 2d 00 43 00 4c 00 49 00 45 00 4e 00 N.F.-.C.L.I.E.N.
00000060:54 00 0e 6a b2 7a 95 9e 59 37 00 00 00 00 00 00 T..j²z•žY7.....
00000070:00 00 00 00 00 00 00 00 83 f6 60 fc 8e 65 .....fö`üŽe
00000080:ac e0 59 19 7b 9f 7f 9c d6 f5 70 5d 87 90 bd 02 -àY.{ÿœÖöp]#□½.
00000090:19 9c .œ

```

4. The server sends a POP3_AUTH_NTLM_Fail_Response message.

```
-ERR, Error: Command not valid
```

5 Security

The following sections specify security considerations for implementers of the NTLM POP3 Extension.

5.1 Security Considerations for Implementers

Implementers should be aware of the security considerations of using NTLM authentication. Information about the security considerations for using NTLM authentication is specified in [\[MS-NLMP\]](#) section 5.

5.2 Index of Security Parameters

Security parameter	Section
NTLM	2 and 3

6 Appendix A: Windows Behavior

The information in this specification is applicable to the following versions of Windows:

- Windows Vista
- Windows Server 2003
- Windows XP

Exceptions, if any, are noted below. Unless otherwise specified, any statement of optional behavior in this specification prescribed using the terms SHOULD or SHOULD NOT implies Windows behavior in accordance with the SHOULD or SHOULD NOT prescription. Unless otherwise specified, the term MAY implies that Windows does not follow the prescription.

[<1> Section 1.5:](#) Windows POP3 server and POP3 client use Security Support Provider Interface (SSPI) to obtain and process NTLM messages. For more information about SSPI, see [\[SSPI\]](#).

7 Index

A

Abstract data model

[client](#)

[server](#)

[Applicability](#)

C

[Capability negotiation](#)

Client

[abstract data model](#)

[higher-layer triggered events](#)

[initialization](#)

[local events](#)

[message processing](#)

[overview](#)

[sequencing rules](#)

[timer events](#)

[timers](#)

D

Data model - abstract

[client](#)

[server](#)

E

[Examples - overview](#)

F

[Fields - vendor-extensible](#)

G

[Glossary](#)

H

Higher-layer triggered events

[client](#)

[server](#)

I

[Implementer - security considerations](#)

[Index of security parameters](#)

[Informative references](#)

Initialization

[client](#)

[server](#)

[Introduction](#)

L

Local events

[client](#)

[server](#)

M

Message processing

[client](#)

[server](#)

Messages

[overview](#)

[syntax](#)

[transport](#)

N

[Normative references](#)

O

[Overview \(synopsis\)](#)

P

[Parameters - security index](#)

[Preconditions](#)

[Prerequisites](#)

R

References

[informative](#)

[normative](#)

[overview](#)

[Relationship to other protocols](#)

S

Security

[implementer considerations](#)

[overview](#)

[parameter index](#)

Sequencing rules

[client](#)

[server](#)

Server

[abstract data model](#)

[higher-layer triggered events](#)

[initialization](#)

[local events](#)

[message processing](#)

[overview](#)

[sequencing rules](#)

[timer events](#)

[timers](#)

[Standards assignments](#)

[Syntax](#)

T

Timer events

[client](#)
[server](#)

Timers

[client](#)
[server](#)
[Transport](#)

Triggered events - higher-layer

[client](#)
[server](#)

V

[Vendor-extensible fields](#)

[Versioning](#)

W

[Windows behavior](#)