

[MS-SMTP]: NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension

Intellectual Property Rights Notice for Protocol Documentation

- This protocol documentation is covered by Microsoft copyrights. Regardless of any other terms that are contained in the terms of use for the Microsoft website that hosts this documentation, you may make copies of it in order to develop implementations of the protocols, and may distribute portions of it in your implementations of the protocols or your documentation as necessary to properly document the implementation. This permission also applies to any documents that are referenced in the protocol documentation.
- Microsoft does not claim any trade secret rights in this documentation.
- Microsoft has patents that may cover your implementations of the protocols. Neither this notice nor Microsoft's delivery of the documentation grants any licenses under those or any other Microsoft patents. If you are interested in obtaining a patent license, please contact protocol@microsoft.com.
- The names of companies and products contained in this documentation may be covered by trademarks or similar intellectual property rights. This notice does not grant any licenses under those rights.
- All other rights are reserved, and this notice does not grant any rights other than specifically described above, whether by implication, estoppel, or otherwise.

This protocol documentation is intended for use in conjunction with publicly available standard specifications, network programming art, and Microsoft Windows distributed systems concepts, and assumes that the reader either is familiar with the aforementioned material or has immediate access to it.

A protocol specification does not require the use of Microsoft programming tools or programming environments in order for you to develop an implementation. If you have access to Microsoft programming tools and environments you are free to take advantage of them.

Revision Summary

Date	Revision History	Revision Class	Comments
07/20/2007	0.1	Major	MCPPE Milestone 5 Initial Availability
09/28/2007	0.1.1	Editorial	Revised and edited the technical content.
10/23/2007	0.2	Minor	Updated to use data types in MS-DTYP.
11/30/2007	0.2.1	Editorial	Revised and edited the technical content.

Date	Revision History	Revision Class	Comments
01/25/2008	0.2.2	Editorial	Revised and edited the technical content.

Table of Contents

1	Introduction	5
1.1	Glossary	5
1.2	References	6
1.2.1	Normative References	6
1.2.2	Informative References.....	7
1.3	Protocol Overview (Synopsis).....	7
1.4	Relationship to Other Protocols.....	9
1.5	Prerequisites/Preconditions	9
1.6	Applicability Statement	9
1.7	Versioning and Capability Negotiation.....	9
1.8	Vendor-Extensible Fields	10
1.9	Standards Assignments.....	10
2	Messages	11
2.1	Transport	11
2.2	Message Syntax	11
2.2.1	SMTP AUTH Extensions	11
2.2.1.1	SMTP_AUTH_NTLM_Initiation_Command Message.....	11
2.2.1.2	SMTP_NTLM_Supported_Response Message	12
2.2.1.3	SMTP_AUTH_NTLM_Blob_Response Message	12
2.2.1.4	SMTP_AUTH_Fail_Response Message	13
2.2.1.5	SMTP_AUTH_Other_Failure_Response Message	13
2.2.1.6	SMTP_AUTH_NTLM_Succeeded_Response Message	13
2.2.1.7	SMTP_AUTH_NTLM_Blob_Command Message	13
2.2.1.8	EHLO Discovery Message.....	13
2.2.2	SMTP Server Messages	14
2.2.3	SMTP Client Messages	14
3	Protocol Details	15
3.1	Client Details	15
3.1.1	Abstract Data Model	15
3.1.1.1	SMTP State Model	15
3.1.1.2	NTLM Software Interaction	16
3.1.2	Timers	17
3.1.3	Initialization	17
3.1.4	Higher-Layer Triggered Events.....	17
3.1.5	Message Processing Events and Sequencing Rules	17
3.1.5.1	Receiving an SMTP_NTLM_Supported_Response Message.....	17
3.1.5.2	Receiving an SMTP_NTLM_Not_Supported_Response Message	17
3.1.5.3	Receiving an SMTP_AUTH_NTLM_Blob_Response Message	17
3.1.5.3.1	Error from NTLM	17
3.1.5.3.2	NTLM Reports Success and Returns an NTLM Message.....	18
3.1.5.4	Receiving an SMTP_AUTH_NTLM_Succeeded_Response Message	18
3.1.5.5	Receiving an SMTP_AUTH_Fail_Response Message	18
3.1.5.6	Receiving an SMTP_AUTH_Other_Failure_Response Message	18
3.1.6	Timer Events.....	18
3.1.7	Other Local Events	18
3.2	Server Details	19
3.2.1	Abstract Data Model	19
3.2.1.1	SMTP State Model	19
3.2.1.2	NTLM Software Interaction	20
3.2.2	Timers	21

3.2.3	Initialization	21
3.2.4	Higher-Layer Triggered Events.....	21
3.2.5	Message Processing Events and Sequencing Rules	21
3.2.5.1	Receiving an SMTP_AUTH_NTLM_Initiation_Command Message	21
3.2.5.2	Receiving an SMTP_AUTH_NTLM_Blob_Command Message.....	22
3.2.5.2.1	NTLM Returns Success, Returning an NTLM Message	22
3.2.5.2.2	NTLM Returns Success, Indicating that the Authentication Completed Successfully	22
3.2.5.2.3	NTLM Returns Status, Indicating that the User Name or Password Was Incorrect	22
3.2.5.2.4	NTLM Returns a Failure Status, Indicating Any Other Error.....	22
3.2.6	Timer Events.....	22
3.2.7	Other Local Events	22
4	Protocol Examples	23
4.1	SMTP Client Successfully Authenticating to an SMTP Server	23
4.2	SMTP Client Not Successfully Authenticating to an SMTP Server	25
5	Security	29
5.1	Security Considerations for Implementers	29
5.2	Index of Security Parameters	29
6	Appendix A: Windows Behavior	30
7	Index.....	31

1 Introduction

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension specifies the use of **NTLM** authentication (as specified in [\[MS-NLMP\]](#)) by the **Simple Mail Transfer Protocol (SMTP)** to facilitate client authentication to a Windows SMTP server. SMTP specifies a protocol for the distribution, inquiry, retrieval, and posting of news articles using a reliable, stream-based transmission of news. A detailed definition of SMTP is specified in [\[RFC2821\]](#).

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension uses the SMTP-AUTH command (as specified in [\[RFC2554\]](#) section 4) and **SMTP** response codes to negotiate NTLM authentication and send authentication data.

1.1 Glossary

The following terms are defined in [\[MS-GLOS\]](#):

base64
Challenge/Response Authentication
NT LAN Manager Protocol (NTLM)
Simple Mail Transfer Protocol (SMTP)
SMTP

The following terms are specific to this document:

Connection-Oriented NTLM: One of the two variants of the NT LAN Manager (NTLM) Authentication Protocol.

AUTH Command: A **Simple Mail Transfer Protocol (SMTP)** command that is used to send authentication information, as specified in [\[RFC2554\]](#). The structure of the **AUTH command** (as used in the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension) is:

```
AUTH NTLM<CR><LF>
```

... or, optionally, is:

```
AUTH NTLM [initial-response]
```

Both command forms are accepted, as required by the RFC.

NTLM AUTHENTICATE_MESSAGE: The NTLM AUTHENTICATE_MESSAGE packet defines an **NTLM** authenticate message that is sent from the client to the server after the **NTLM CHALLENGE_MESSAGE** is processed by the client. Message structure and other details of this packet are specified in [\[MS-NLMP\]](#).

NTLM CHALLENGE_MESSAGE: The NTLM CHALLENGE_MESSAGE packet defines an NTLM challenge message that is sent from the server to the client. The **NTLM CHALLENGE_MESSAGE** is generated by the local **NTLM software** and passed to the application that supports embedded **NTLM** authentication. This message is used by the server to challenge the client to prove its identity. Message structure and other details of this packet are specified in [\[MS-NLMP\]](#).

NTLM Message: An **NTLM message** carries authentication information. Its payload data is passed to the application that supports embedded **NTLM** authentication by the **NTLM software** installed on the local computer. **NTLM messages** are transmitted between the client and server embedded within the application protocol that is using **NTLM** authentication. There are three types of **NTLM messages**:

- **NTLM NEGOTIATE_MESSAGE**
- **NTLM CHALLENGE_MESSAGE**
- **NTLM AUTHENTICATE_MESSAGE**

NTLM NEGOTIATE_MESSAGE: The NEGOTIATE_MESSAGE packet defines an NTLM negotiate message that is sent from the client to the server. The **NTLM NEGOTIATE_MESSAGE** is generated by the local **NTLM software** and passed to the application that supports embedded **NTLM** authentication. This message allows the client to specify its supported **NTLM** options to the server. Message structure and other details are specified in [MS-NLMP].

NTLM Software: Software that implements the NT LAN Manager (NTLM) Authentication Protocol.

MAY, SHOULD, MUST, SHOULD NOT, MUST NOT: These terms (in all caps) are used as specified in [RFC2119]. All statements of optional behavior use either MAY, SHOULD, or SHOULD NOT.

1.2 References

1.2.1 Normative References

We conduct frequent surveys of the normative references to assure their continued availability. If you have any issue with finding a normative reference, please contact dochelp@microsoft.com. We will assist you in finding the relevant information. Please check the archive site, <http://msdn2.microsoft.com/en-us/library/E4BD6494-06AD-4aed-9823-445E921C9624>, as an additional source.

[MS-GLOS] Microsoft Corporation, "[Windows Protocols Master Glossary](#)", March 2007.

[MS-NLMP] Microsoft Corporation, "[NT LAN Manager \(NTLM\) Authentication Protocol Specification](#)", June 2007.

[RFC1521] Borenstein, N., and Freed, N., "MIME (Multipurpose Internet Mail Extensions) Part One: Mechanisms for Specifying and Describing the Format of Internet Message Bodies", RFC 1521, September, 1993, <http://www.ietf.org/rfc/rfc1521.txt>

[RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997, <http://www.ietf.org/rfc/rfc2119.txt>

[RFC2554] Myers, J., "SMTP Service Extension for Authentication", RFC 2554, March, 1999, <http://www.ietf.org/rfc/rfc2554.txt>

[RFC2821] Klensin, J., "Simple Mail Transfer Protocol", RFC 2821, April 2001, <http://www.ietf.org/rfc/rfc2821.txt>

[RFC4234] Crocker, D., Ed. and Overell, P., "Augmented BNF for Syntax Specifications: ABNF", RFC 4234, October 2005, <http://www.ietf.org/rfc/rfc4234.txt>

1.2.2 Informative References

[SSPI] Microsoft Corporation, "SSPI", <http://msdn2.microsoft.com/en-us/library/aa380493.aspx>

1.3 Protocol Overview (Synopsis)

Client applications that connect to the Simple Mail Transfer Protocol (SMTP) service included in Windows 2000 Server and Windows Server 2003 can use Windows NT LAN Manager Protocol (NTLM) authentication.

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension specifies how an SMTP client and SMTP server can use the NTLM Authentication Protocol, as specified in [MS-NLMP], so that the SMTP server can authenticate the SMTP client. the NTLM Authentication Protocol, as specified in [MS-NLMP], is a **challenge/response authentication** protocol that depends on the application layer protocols to transport NTLM packets from client to server and from server to client.

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension defines how the SMTP is extended to perform authentication using the NTLM Authentication Protocol, as specified in [MS-NLMP]. The SMTP standard defines an extensibility mechanism for arbitrary authentication protocols to be plugged in to the core protocol. This mechanism is the SMTP-AUTH mechanism.

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension is an embedded protocol in which NTLM authentication data is first transformed into a **base64** representation (as specified in [RFC1521]), and then formatted by padding with SMTP status codes and SMTP keywords, as defined by the AUTH mechanism. The base64 encoding and the formatting is very rudimentary and solely intended to make the NTLM data look like other SMTP commands and responses. The following diagram illustrates the sequence of transformations performed on an **NTLM message** to produce a message that can be sent over SMTP.




Figure 1: Relationship between NTLM message and SMTP (NTLM Authentication Protocol message)

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension is a pass-through protocol that does not specify the structure of NTLM information. Instead, the protocol relies on the software that implements the NTLM Authentication Protocol (as specified in [MS-NLMP]) to process each NTLM message to be sent or received.

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension defines both server and client roles.

When SMTP wants to perform an NTLM authentication, it needs to interact with the **NTLM software** appropriately. An overview of this interaction follows.

If acting as an SMTP client:

1. The NTLM software returns the first NTLM message to the client to be sent to the server.

2. The client should apply the base64 encoding and SMTP padding transformations (mentioned earlier and described in detail later in this document) to produce an SMTP message, and then send this message to the server.
3. The client should wait for a response from the server. When the response is received, it checks to see whether it indicates the end of authentication (success or failure) or that authentication is continuing.
4. If the authentication is continuing, the response message is stripped of the SMTP padding, is base64 decoded, and is passed into the NTLM software, on which the NTLM software may return another NTLM message that needs to be sent to the server. Steps 2 through 4 are repeated until authentication succeeds or fails.

If acting as an SMTP server:

1. The server waits to receive the first SMTP authentication message from the client.
2. When an SMTP message is received from the client, the SMTP padding is removed, the message is base64 decoded, and the resulting NTLM message is passed into the NTLM software.
3. The NTLM software will return a status indicating whether authentication completed successfully, failed, or more NTLM messages need to be exchanged to complete the authentication.
4. If the authentication is continuing, the NTLM software will return an NTLM message that needs to be sent to the server. This message is base64 encoded, and the SMTP padding is applied and sent to the client. Steps 2 through 4 are repeated until authentication succeeds or fails.

The sequence that follows shows the typical flow of packets between a client and server once NTLM authentication has been selected.

1. The SMTP client sends an **NTLM NEGOTIATE_MESSAGE** embedded in an [SMTP AUTH NTLM Blob Command](#) packet to the server.
2. On receiving the SMTP packet with an NTLM NEGOTIATE_MESSAGE, the server sends an **NTLM CHALLENGE_MESSAGE** embedded in an SMTP packet to the client.
3. In response, the SMTP client sends an **NTLM AUTHENTICATE_MESSAGE** embedded in an SMTP packet.
4. The server then sends an SMTP response to the client to successfully complete the authentication process.

The NTLM NEGOTIATE_MESSAGE, NTLM CHALLENGE_MESSAGE, and NTLM AUTHENTICATE_MESSAGE packets contain NTLM authentication data that must be processed by the NTLM software installed on the local computer. How to retrieve and process NTLM messages is specified in [MS-NLMP].

Implementers of the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension must possess a working knowledge of the following:

- Simple Mail Transfer Protocol (SMTP), as specified in [\[RFC2821\]](#) and [\[RFC2554\]](#).
- Multipurpose Internet Mail Extensions (MIME) base64 encoding method, as specified in [\[RFC1521\]](#).
- NTLM Authentication Protocol, as specified in [MS-NLMP].

1.4 Relationship to Other Protocols

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension uses the SMTP-AUTH extension mechanism, as specified in [\[RFC2554\]](#), and is an embedded protocol. Unlike standalone application protocols, such as Telnet or Hypertext Transfer Protocol (HTTP), NTLM Authentication: SMTP Extension packets are embedded in Simple Mail Transfer Protocol (SMTP) commands and server responses.

The SMTP specifies only the sequence in which an SMTP server and an SMTP client must exchange NTLM messages to successfully authenticate the client to the server. It does not specify how the client obtains NTLM messages from the local NTLM software, or how the SMTP server should process NTLM messages. The SMTP client and SMTP server implementations depend on the availability of an implementation of the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) to obtain and process NTLM messages and on the availability of the base64 encoding and decoding mechanisms (as specified in [\[RFC1521\]](#)) to encode and decode the NTLM messages embedded in SMTP packets.

1.5 Prerequisites/Preconditions

Because the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension depends on NTLM to authenticate the client to the server, both server and client must have access to an implementation of the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) that is capable of supporting **connection-oriented NTLM**.[<1>](#)

1.6 Applicability Statement

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension must be used only when implementing an SMTP client that needs to authenticate to an SMTP server by using NTLM authentication.

1.7 Versioning and Capability Negotiation

This document covers versioning issues in the following areas:

- Security and Authentication Methods: The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension supports the NTLM version 1 and NTLM version 2 authentication methods, as specified in [\[MS-NLMP\]](#).
- Capability Negotiation: The NTLM Authentication: SMTP Extension does not support negotiation of the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) version to use. Instead, the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) version must be configured on both the client and the server prior to authentication. NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) version mismatches are handled by the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) implementation, and not by SMTP.

The SMTP Service Extension for Authentication (as specified in [\[RFC2554\]](#)) does document the framework within which SMTP clients may discover (and SMTP servers may advertise) the capability to perform any given authentication mechanism, including (in particular) NTLM.

The client discovers if the server supports NTLM AUTH through the SMTP-EHLO, at which time the server responds with a standard EHLO response, as specified in [\[RFC2821\]](#). The EHLO keyword that is advertised if NTLM authentication is supported is "NTLM". Although "NTLM" is not an SASL mechanism (as defined in [\[RFC2554\]](#) section 3 bullet 3), the SMTP server and client behave exactly as if NTLM was an SASL mechanism with the name "NTLM". The messages involved are formally specified in other sections of this document.

1.8 Vendor-Extensible Fields

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension does not have any vendor-extensible fields.

1.9 Standards Assignments

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension does not use any standards assignments.

2 Messages

The following sections specify how NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension messages are transported and NTLM Authentication: SMTP Extension message syntax.

2.1 Transport

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension does not establish transport connections. Instead, its messages are encapsulated in SMTP commands and responses. How NTLM Authentication: SMTP Extension messages MUST be encapsulated in SMTP commands is specified in section [2.2](#).

2.2 Message Syntax

NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension messages are divided into three categories, depending on whether the message was sent by the server or the client.

The formal syntax of messages is provided in Augmented Backus-Naur Form (ABNF), as specified in [\[RFC4234\]](#).

2.2.1 SMTP AUTH Extensions

The first category of SMTP messages are messages that fall within the SMTP-AUTH extensibility framework. These messages are defined in [\[RFC2554\]](#). Some of the messages have parameters that MUST be customized by the extensibility mechanism (such as NTLM). The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension introduces the following customizations, as specified in sections [2.2.1.1](#) through [2.2.1.8](#).

At every point of time during the authentication exchange, the client MUST parse the status codes on the messages sent by the server and interpret them as specified in [\[RFC2554\]](#). The status codes define various states such as success in authenticating, failure to authenticate, and any other arbitrary failures that the software may encounter.

The client may receive any one of the following responses during authentication. Note that the syntax and meaning of these messages are completely defined by [\[RFC2554\]](#) except for the [SMTP AUTH NTLM Blob Response](#) message, for which [\[RFC2554\]](#) does not define the data encapsulated within the SMTP message; and it leaves the definition and processing of that data to the extension mechanism. This specification will focus on precisely defining that data.

- SMTP_AUTH_NTLM_Blob_Response
- [SMTP AUTH Fail Response](#)
- [SMTP AUTH Other Failure Response](#)
- [SMTP AUTH NTLM Succeeded Response](#)

2.2.1.1 SMTP_AUTH_NTLM_Initiation_Command Message

The SMTP_AUTH_NTLM_Initiation_Command message initiates the NTLM authentication process for SMTP.

[\[RFC2554\]](#) section 4 defines the syntax of the SMTP **AUTH command** and related commands (for example, EHLO) to initiate authentication. The mechanism name for NTLM authentication is defined to be the string "NTLM" for the NTLM Authentication: SMTP Extension. The command to initiate an NTLM conversation by a client in ABNF form is shown below. Note that there are two forms of this command. The client may optionally base64 encode (as specified in [\[RFC1521\]](#)) and send the initial NTLM CHALLENGE_MESSAGE message as part of this command as the [initial-response]:

```
AUTH NTLM<CR><LF>
```

... or, optionally:

```
AUTH NTLM [initial-response]<CR><LF>
```

If an [initial-response] string is supplied, the server will invoke the NTLM subsystem, obtain the NTLM CHALLENGE_MESSAGE, base64 encode it, pad it (as defined elsewhere in this specification), and return it to the client as an SMTP message.

If NTLM is not supported, the SMTP server returns a failure status code, as defined in [\[RFC2554\]](#). This message is a standard message defined by the SMTP standard, and is not discussed here.

2.2.1.2 SMTP_NTLM_Supported_Response Message

The SMTP_NTLM_Supported_Response message indicates that the server supports NTLM authentication for SMTP.

If the [initial-response] string is not supplied in the [SMTP AUTH NTLM Initiation Command](#) message, and NTLM is supported, the SMTP server will respond with an SMTP message prefixed with a status code of 334 to indicate that NTLM is supported. The only data in this message that is useful is the status code 334. The remaining data is human-readable data and has no bearing on the authentication. The syntax of this command in ABNF form is shown below.

```
334 <human-readable-string><CR><LF>
```

<human-readable-string> MUST be ignored by the client. Note that status code 334 is also returned by the [SMTP AUTH NTLM Blob Response](#) message.

2.2.1.3 SMTP_AUTH_NTLM_Blob_Response Message

SMTP_AUTH_NTLM_Blob_Response is defined as follows. This message is partially defined in [\[RFC2554\]](#) section 4. The 334 status code indicates ongoing authentication and indicates that the <base64-encoded-NTLM-message> is to be processed by the authentication subsystem. In this case, the client MUST de-encapsulate the data and pass it to the NTLM subsystem.

```
334 <base64-encoded-NTLM-message><CR><LF>
```

Note that status code 334 is also returned by the [SMTP NTLM Supported Response](#) message.

2.2.1.4 SMTP_AUTH_Fail_Response Message

SMTP_AUTH_Fail_Response is defined as follows. This message, identified by the 535 status code, is defined in [\[RFC2554\]](#) section 4, and indicates that the authentication has terminated unsuccessfully because the user name or password was incorrect.

```
535 5.7.3 <human-readable-string><CR><LF>
```

2.2.1.5 SMTP_AUTH_Other_Failure_Response Message

SMTP_AUTH_Other_Failure_Response is defined as follows. This is actually a class of messages whose syntax and interpretation are defined in [\[RFC2821\]](#) and [\[RFC2554\]](#). They indicate an abnormal termination of the NTLM authentication negotiation, which may occur for various reasons such as software errors, lack of system resources, and so on. For the purposes of this document, SMTP_AUTH_Other_Failure_Response is defined as any SMTP message other than [SMTP_AUTH_NTLM_Succeeded_Response](#), [SMTP_AUTH_Fail_Response](#), and [SMTP_AUTH_NTLM_Blob_Response](#). The interpretation of SMTP_AUTH_Other_Failure_Response, and the suggested client action when receiving such a message, is defined in [\[RFC2821\]](#). This message represents an exit from AUTH and is, as such, not really a part of AUTH negotiation.

2.2.1.6 SMTP_AUTH_NTLM_Succeeded_Response Message

SMTP_AUTH_NTLM_Succeeded_Response is defined as follows. This message is defined in [\[RFC2554\]](#) and indicates that the authentication negotiation has completed with the client successfully authenticating to the server.

```
235 <human-readable-string><CR><LF>
```

2.2.1.7 SMTP_AUTH_NTLM_Blob_Command Message

NTLM messages encapsulated by the client and sent to the server are referred to as SMTP_AUTH_NTLM_Blob_Command in this document. They have the following syntax defined in ABNF and conform to the prescription of [\[RFC2554\]](#).

```
<base64-encoded-NTLM-message><CR><LF>
```

2.2.1.8 EHLO Discovery Message

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension also supports the discovery of supported authentication procedures, as defined in [\[RFC2554\]](#) section 4 (last paragraph).

When the EHLO command is sent to the SMTP server without an authenticator or arguments, the SMTP server will list available authentication mechanisms using the syntax defined in [\[RFC2821\]](#). The NTLM mechanism is indicated by using the "NTLM" EHLO advertisement if NTLM authentication is enabled for the SMTP server.

2.2.2 SMTP Server Messages

This section defines the creation of [SMTP AUTH NTLM Blob Response](#) messages. These are NTLM messages that are sent by the server, and MUST be encapsulated as follows to conform to syntax specified by the SMTP-AUTH mechanism:

1. base64 encode (as specified in [RFC1521](#)) the NTLM message data. This is needed because NTLM messages contain data outside the ASCII character range whereas SMTP only supports the sending of ASCII characters within the context of SMTP-AUTH.
2. To the base64 encoded string, prefix the SMTP response code "334 " (that is, the numerals 334 followed by the ASCII space character 0x20).
3. Suffix the <CR> and <LF> characters (ASCII values 0x0D and 0x0A), as required by SMTP.

The ABNF definition of a server message is as follows:

```
334 <base64-encoded-NTLM-message><CR><LF>
```

De-encapsulation of these messages by the client follows the reverse logic:

1. Remove the <CR> and <LF> characters (ASCII values 0x0D and 0x0A).
2. Remove the SMTP response code "334" (that is, the numerals 334 followed by the ASCII space character 0x20).
3. base64 decode the SMTP data to produce the original NTLM message data.

2.2.3 SMTP Client Messages

This section defines the creation of [SMTP AUTH NTLM Blob Command](#) messages. These NTLM messages sent by the client are encapsulated as follows to conform to the SMTP-AUTH mechanism:

1. base64 encode (as specified in [RFC1521](#)) the NTLM message data. This is needed because NTLM messages contain data outside the ASCII character range whereas SMTP only supports ASCII characters to be sent within the context of SMTP-AUTH.
2. Suffix the <CR> and <LF> characters (ASCII values 0x0D and 0x0A), as required by SMTP.

The ABNF definition of a client message is as follows:

```
<base64-encoded-NTLM-message><CR><LF>
```

De-encapsulation of these messages by the client follows the reverse logic:

1. Remove the <CR> and <LF> characters (ASCII values 0x0D and 0x0A).
2. base64 decode the SMTP data to produce the original NTLM message data.

3 Protocol Details

The following sections specify details of the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension, including abstract data models and message processing rules.

3.1 Client Details

3.1.1 Abstract Data Model

3.1.1.1 SMTP State Model




Figure 2: SMTP NTLM authentication client state model

The abstract data model for the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension has the following states:

1. start

This is the state of the client before the [SMTP AUTH NTLM Initiation Command](#) has been sent.

2. sent_authentication_request

This is the state of the client after the SMTP_AUTH_NTLM_Initiation_Command has been sent.

3. inside_authentication

This is the state entered by a client after it has received an [SMTP NTLM Supported Response](#). In this state, the client initializes the NTLM software and repeats the following steps:

- Encapsulates the NTLM message returned by the NTLM software into an SMTP message.
- Waits for a response from the server.
- De-encapsulates received SMTP message-data (if any) from the other party and converts it to NTLM message data.
- Passes it to the NTLM software.
- Sends the SMTP message to the other party.

This state terminates when:

- For the server: The NTLM software reports completion with either a success or failed authentication status, at which time it sends the client an [SMTP AUTH NTLM Succeeded Response](#) or [SMTP AUTH Fail Response](#), as specified in [\[RFC2554\]](#).

- For the client: An SMTP_AUTH_NTLM_Succeeded_Response or SMTP_AUTH_Fail_Response is received.
- For either the client or server: When any failure is reported by the NTLM software.

4. completed_authentication

This is the state of the client on exiting the inside_authentication state. The rules for how the inside_authentication state is exited are defined in section [3.1.5](#). The behavior of SMTP in this state is not addressed in this document; it represents the end state of the authentication protocol.

3.1.1.2 NTLM Software Interaction

During the inside_authentication phase, the SMTP client invokes the NTLM software, as specified in [\[MS-NLMP\]](#) section 3.1. The NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) is used with these options:

1. The negotiation is a connection-oriented NTLM negotiation.
2. None of the flags specified in [\[MS-NLMP\]](#) section 3.1.1 are passed to NTLM.

Following is a description of how SMTP uses NTLM. Remember that all NTLM messages are encapsulated as specified in section [2.1](#). The NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#) section 3.1.1) specifies the data-model, internal states, and sequencing of NTLM messages in greater detail.

1. The client initiates the authentication by invoking NTLM, at which time NTLM will return the NTLM NEGOTIATE_MESSAGE to be sent to the server. The NTLM NEGOTIATE_MESSAGE may either be embedded in the initial [SMTP AUTH NTLM Initiation Command](#) as the [initial-response] field (as specified in [\[RFC2554\]](#)), or it may be sent to the server embedded inside the first [SMTP AUTH NTLM Blob Command](#).
2. Subsequently, the exchange of NTLM messages goes on as defined by the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) with the SMTP client encapsulating the NTLM messages before sending them to the server, and de-encapsulating SMTP messages to obtain the NTLM message before giving it to the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)).
3. The NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) completes authentication, either successfully or unsuccessfully, as follows:
 - The server sends the [SMTP AUTH NTLM Succeeded Response](#) to the client. On receiving this message, the client transitions to the completed_authentication state, and should treat the authentication attempt as successful.
 - The server sends the [SMTP AUTH Fail Response](#) to the client. On receiving this message, the client transitions to the completed_authentication state, and should treat the authentication attempt as failed.
 - The server sends the [SMTP AUTH Other Failure Response](#) to the client. On receiving this message, the client transitions to the completed_authentication state, and should treat the authentication attempt as failed.
 - Failures reported from the NTLM software (which can occur for any reason, including incorrect data being passed in, or implementation-specific errors) may be reported to the client by the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) and cause the client to transition to the completed_authentication state.

3.1.2 Timers

There are no timers specific to authentication.

3.1.3 Initialization

There is no protocol-specific initialization.

3.1.4 Higher-Layer Triggered Events

There are no higher-layer triggered events in common to all parts of this protocol.

3.1.5 Message Processing Events and Sequencing Rules

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension is driven by a series of message exchanges between an SMTP server and an SMTP client. The rules governing the sequencing of commands and the internal states of the client and server are defined by a combination of [\[RFC2554\]](#) and [\[MS-NLMP\]](#). Section [3.1.1](#) completely defines how the rules specified in [\[RFC2554\]](#) and [\[MS-NLMP\]](#) govern SMTP authentication.

3.1.5.1 Receiving an SMTP_NTLM_Supported_Response Message

Expected state is `sent_authentication_request`.

On receiving this message, a client MUST generate the first NTLM message by calling the NTLM software. The NTLM software then generates NTLM NEGOTIATE_MESSAGE, as specified in [\[MS-NLMP\]](#). The client MUST then encapsulate the NTLM message, as defined in section [2.2.3](#), and send it to the server.

Note The server will only receive the [SMTP_NTLM_Supported_Response](#) if the client did not embed the NTLM NEGOTIATE_MESSAGE in the [SMTP_AUTH_NTLM_Initiation_Command](#) [initial-response] optional parameter.

The state of the client is changed to `inside_authentication`.

3.1.5.2 Receiving an SMTP_NTLM_Not_Supported_Response Message

Expected state is `sent_authentication_request`.

On receiving this message, a client MUST abort the NTLM authentication attempt.

3.1.5.3 Receiving an SMTP_AUTH_NTLM_Blob_Response Message

Expected state is `inside_authentication`.

On receiving this message, a client MUST de-encapsulate it to obtain the embedded NTLM message, and then pass it to the NTLM software for processing. The NTLM software either reports an error or reports success, and then returns an NTLM message to be sent to the server.

3.1.5.3.1 Error from NTLM

If the NTLM software reports an error, the client must change its internal state to `completed_authentication` and consider that the authentication has failed. The client may then take any action it considers appropriate. This document does not mandate any specific course of action.

Typical actions are to attempt other (non-authentication related) SMTP commands or to disconnect the connection.

3.1.5.3.2 NTLM Reports Success and Returns an NTLM Message

The NTLM message should be encapsulated and sent to the server. No change occurs in the state of the client.

3.1.5.4 Receiving an SMTP_AUTH_NTLM_Succeeded_Response Message

Expected state: inside_authentication.

The SMTP client MUST change its internal state to completed_authentication and consider that the authentication has succeeded. The client then takes any action it considers appropriate. This document does not mandate any specific course of action.

3.1.5.5 Receiving an SMTP_AUTH_Fail_Response Message

Expected state: inside_authentication.

The SMTP client MUST change its internal state to completed_authentication and consider that the authentication has failed. The client then takes any action it considers appropriate. This document does not mandate any specific course of action.

3.1.5.6 Receiving an SMTP_AUTH_Other_Failure_Response Message

Expected state: inside_authentication.

The SMTP client MUST change its internal state to completed_authentication and consider that the authentication has failed. The client then takes any action it considers appropriate. This document does not mandate any specific course of action.

Note This response MUST be interpreted using the rules specified in [\[RFC2821\]](#). These rules include using the three-digit status code to infer whether the failure is permanent or temporary, whether or not to generate non-delivery notifications for messages queued on the client, and so on.

3.1.6 Timer Events

There are no timer events.

3.1.7 Other Local Events

There are no local events.

3.2 Server Details

3.2.1 Abstract Data Model

3.2.1.1 SMTP State Model




Figure 3: SMTP NTLM authentication server state model

The abstract data model for the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension has these states:

1. start

This is the state of the server before the [SMTP_AUTH_NTLM_Initiation_Command](#) has been received.

2. `received_authentication_request`

This is the state of the client after the `SMTP_AUTH_NTLM_Initiation_Command` has been received.

3. `inside_authentication`

This is the state entered by a server after it has sent an [SMTP_NTLM_Supported_Response](#). In this state, the server initializes the NTLM software and repeats the following steps:

- Waits for a message from the client except on first entering the `inside_authentication` state; if the optional `[initial-response]` parameter defined by [\[RFC2554\]](#) was received from the client, the `[initial-response]` data is used as the message.
- De-encapsulates the received SMTP message data party and obtains the embedded NTLM message data.
- Passes it to the NTLM software.
- Encapsulates the NTLM message returned by the NTLM software into an SMTP message.
- Sends the SMTP message to the other party.

This state terminates when:

- The NTLM software reports completion with either a success or failed authentication status, at which time it sends the client an [SMTP_AUTH_NTLM_Succeeded_Response](#) or [SMTP_AUTH_Fail_Response](#), as specified in [\[RFC2554\]](#).
- Any failure is reported by the NTLM software.

4. `completed_authentication`

This is the state of the server on exiting the `inside_authentication` state. The rules for how the `inside_authentication` state is exited are defined in section [3.2.5](#). The behavior of SMTP in this state is not addressed in this document; it represents the end state of the authentication protocol.

3.2.1.2 NTLM Software Interaction

During `inside_authentication` state, the SMTP server invokes the NTLM software, as specified in [\[MS-NLMP\]](#) section 3.1. The NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) is used with these options:

1. The negotiation is a connection-oriented NTLM negotiation.
2. None of the flags specified in [\[MS-NLMP\]](#) section 3.1.1 are passed to the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)).

Following is a description on how SMTP uses NTLM. See [\[MS-NLMP\]](#) section 3.1.1, which describes the data-model and sequencing of NTLM packets in greater detail.

1. The server, on receiving the NTLM `NEGOTIATE_MESSAGE`, passes it to the NTLM software and is returned the NTLM `CHALLENGE_MESSAGE`, if the NTLM `NEGOTIATE_MESSAGE` message was valid.
2. Subsequently, the exchange of NTLM messages goes on as defined by the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) with the SMTP server encapsulating the NTLM messages returned by the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) before sending them to the client.
3. When the NTLM Authentication Protocol (as specified in [\[MS-NLMP\]](#)) completes authentication, either successfully or unsuccessfully, the NTLM software notifies SMTP.
 - On successful completion, the server must exit the `inside_authentication` state and enter the `completed_authentication` state, and then send the [SMTP_AUTH_NTLM_Succeeded_Response](#)

to the client. On receiving this message, the client must also transition to the completed_authentication state.

- If a failure occurs due to an incorrect password error, as specified in [MS-NLMP] sections [3.3.1](#) and [3.3.2](#), the server should enter the completed_authentication state and send the client an [MTP_AUTH_Fail_Response](#) message.
- If a failure occurs on the server due to any reason other than the incorrect password error, the server enters the completed_authentication state and sends the client an [MTP_AUTH_Fail_Response](#) message. On receiving this message, the client must enter the completed_authentication state.

3.2.2 Timers

There are no timers specific to this protocol extension.

3.2.3 Initialization

There is no protocol-specific initialization.

3.2.4 Higher-Layer Triggered Events

There are no higher-layer triggered events in common to all parts of this protocol.

3.2.5 Message Processing Events and Sequencing Rules

The NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension is driven by a series of message exchanges between an SMTP server and an SMTP client. The rules governing the sequencing of commands and the internal states of the client and server are defined by a combination of [\[RFC2554\]](#) and [\[MS-NLMP\]](#). Section [3.2.1](#) completely defines how the rules specified in [\[RFC2554\]](#) and [\[MS-NLMP\]](#) govern SMTP authentication.

3.2.5.1 Receiving an SMTP_AUTH_NTLM_Initiation_Command Message

Expected state is start.

The server examines the received message to determine if the [initial-response] parameter is present in the message.

There are two actions possible, depending on whether or not the client has included the [initial-response] parameter in this message:

1. If the client has included the [initial-response] parameter: The server MUST de-encapsulate the NTLM NEGOTIATE_MESSAGE embedded within the [initial-response], and pass it to the NTLM software. The NTLM software MUST do one of the following:
 1. Report success in processing the message and return an NTLM message to continue the authentication.
 2. Report that authentication completed successfully.
 3. Report that the authentication failed due to a bad user name or password, as specified in [\[MS-NLMP\]](#).
 4. Report that the authentication failed, which could be due to some other software error or message corruption.

2. If the client has not included the [initial-response] parameter: The server must reply with the [SMTP_NTLM_Supported_Response](#) if it supports NTLM and change its state to the inside_authentication state.

If the server does not support NTLM, it MUST respond with the SMTP_NTLM_Not_Supported_Response, and the internal state remains unchanged.

3.2.5.2 Receiving an SMTP_AUTH_NTLM_Blob_Command Message

Expected state is inside_authentication.

On receiving this message, a server MUST de-encapsulate the message, obtain the embedded NTLM message, and pass it to the NTLM software. The NTLM software MUST do one of the following:

1. Report success in processing the message and return an NTLM message to continue the authentication.
2. Report that authentication completed successfully.
3. Report that the authentication failed due to a bad user name or password, as specified in [\[MS-NLMP\]](#).
4. Report that the authentication failed, which could be due to some other software error or message corruption.

3.2.5.2.1 NTLM Returns Success, Returning an NTLM Message

The server MUST encapsulate the NTLM message and send it to the client. The internal state of the SMTP server remains unchanged.

3.2.5.2.2 NTLM Returns Success, Indicating that the Authentication Completed Successfully

The server MUST return the [SMTP_AUTH_NTLM_Succeeded_Response](#) and change its internal state to completed_authentication.<2>

3.2.5.2.3 NTLM Returns Status, Indicating that the User Name or Password Was Incorrect

The server MUST return the [SMTP_AUTH_Fail_Response](#) and change its internal state to completed_authentication.

3.2.5.2.4 NTLM Returns a Failure Status, Indicating Any Other Error

The server MUST return the [SMTP_AUTH_Other_Failure_Response](#) and change its internal state to completed_authentication.

3.2.6 Timer Events

There are no timer events.

3.2.7 Other Local Events

There are no local events.

4 Protocol Examples

The following sections describe operations used in common scenarios to illustrate the function of the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension.

4.1 SMTP Client Successfully Authenticating to an SMTP Server

This section illustrates the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension with an example scenario in which an SMTP client successfully authenticates to an SMTP server using NTLM.




Figure 4: SMTP client successfully authenticating to SMTP server

1. The client sends an EHLO to the server. This command is specified in [\[RFC2821\]](#).

```
EHLO test.com
```

2. The server responds with an EHLO-Response (including the EHLO-keyword AUTH) to indicate that the authentication is supported. Among the parameters to the AUTH EHLO-response keyword is the keyword "NTLM", indicating that NTLM authentication is available.

```
250-exch-cli-66 Hello [127.0.0.1]
250-AUTH GSSAPI NTLM
```

```

250-TURN
250-SIZE 2097152
250-ETRN
250-PIPELINING
250-DSN
250-ENHANCEDSTATUSCODES
250-8bitmime
250-BINARYMIME
250-CHUNKING
250-VRFY
250 OK

```

- The client then sends the SMTP AUTH command, [SMTP AUTH NTLM Initiation Command](#), initiating auth. In this example, the AUTH command being sent is without the optional [initial-response] data.

```
AUTH NTLM
```

- The server sends the [SMTP NTLM Supported Response](#) message, indicating that it can perform NTLM authentication.

```
334 ntlm supported
```

- The client sends an [SMTP AUTH NTLM Blob Command](#) message containing a base64-encoded NTLM NEGOTIATE_MESSAGE.

```
TlRMTVNTUAABAAAAt4II4gAAAAAAAAAAAAAAAAAAAAAFAs4OAAADw==
```

The content of the NTLM message after base64 decoding is:

```

0x00000000  4E 54 4C 4D 53 53 50 00 01 00 00 00 B7 82 08 E2  NTLMSSP.....7 .b
0x00000010  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  .....
0x00000020  05 02 CE 0E 00 00 00 0F                          ..N.....

```

- The server sends an [SMTP AUTH NTLM Blob Response](#) message containing a base64-encoded NTLM CHALLENGE_MESSAGE.

```

334 TlRMTVNTUAACAAAAGfAWADgAAAA1goriZt7rI6Uq/ccAAAAAAAAAGwAbABOAAA
ABQLODgAAAA9FAFgAQwBIAC0AQwBMAEkALQA2ADYAAgAWAEUAWABDAEgALQBDAEWASQ
AtADYANGABABYARQBYAEMASAAAtAEMATABJAC0ANGA2AAQAFgBlAHgAYwBoAC0AYwBsA
GkALQA2ADYAAwAWAGUAeABjAGgALQBjAGwAaQAtADYANGAAAAAA

```

The content of the NTLM message after base64 decoding is:

```

0x00000000  4E 54 4C 4D 53 53 50 00 02 00 00 00 16 00 16 00  NTLMSSP.....
0x00000010  38 00 00 00 35 82 8A E2 66 DE EB 23 A5 2A FD C7  8...5_bf^k#%*)G
0x00000020  00 00 00 00 00 00 00 00 6C 00 6C 00 4E 00 00 00  .....1.1.N...
0x00000030  05 02 CE 0E 00 00 00 0F 45 00 58 00 43 00 48 00  ..N.....E.X.C.H.

```


0x00000040	2D 00 43 00 4C 00 49 00 2D 00 36 00 36 00 02 00	-.C.L.I.-.6.6...
0x00000050	16 00 45 00 58 00 43 00 48 00 2D 00 43 00 4C 00	..E.X.C.H.-.C.L.
0x00000060	49 00 2D 00 36 00 36 00 01 00 16 00 45 00 58 00	I.-.6.6.....E.X.
0x00000070	43 00 48 00 2D 00 43 00 4C 00 49 00 2D 00 36 00	C.H.-.C.L.I.-.6.
0x00000080	36 00 04 00 16 00 65 00 78 00 63 00 68 00 2D 00	6.....e.x.c.h.-.
0x00000090	63 00 6C 00 69 00 2D 00 36 00 36 00 03 00 16 00	c.l.i.-.6.6.....
0x000000A0	65 00 78 00 63 00 68 00 2D 00 63 00 6C 00 69 00	e.x.c.h.-.c.l.i.
0x000000B0	2D 00 36 00 36 00 00 00 00 00 00 00 00 00 00	-.6.6.....

7. The client sends an SMTP_AUTH_NTLM_Blob_Command message containing a base64-encoded NTLM AUTHENTICATE_MESSAGE.

```
TlRMTVNTUAADAAAAGAAAYAHwAAAYABgAlAAAABYAFgBIAAAACAAIAF4AAAAWABYAZgA
AABAAEACsAAAAANYKI4gUCzg4AAAAPZQB4AGMAaAAtAGMabABpAC0ANgA2AHQAZQBzAH
QARQBYAEMASAAAtAEMATABJAC0ANgA2AAZKkK42dvN2AAAAAAAAAAAAAAAAAAAAABvqC
ZdJZ0NxuuMaNT5PPn5aZ6imuk9cPzkPUjEYNIRezKCGmTwS5G0=
```

The content of the NTLM message after base64 decoding is:

0x00000000	4E 54 4C 4D 53 53 50 00 03 00 00 00 18 00 18 00	NTLMSSP.....
0x00000010	7C 00 00 00 18 00 18 00 94 00 00 00 16 00 16 00_.....
0x00000020	48 00 00 00 08 00 08 00 5E 00 00 00 16 00 16 00	H.....^.....
0x00000030	66 00 00 00 10 00 10 00 AC 00 00 00 35 82 88 E2	f.....,....5 b
0x00000040	05 02 CE 0E 00 00 00 0F 65 00 78 00 63 00 68 00	..N.....e.x.c.h.
0x00000050	2D 00 63 00 6C 00 69 00 2D 00 36 00 36 00 74 00	-.c.l.i.-.6.6.t.
0x00000060	65 00 73 00 74 00 45 00 58 00 43 00 48 00 2D 00	e.s.t.E.X.C.H.-.
0x00000070	43 00 4C 00 49 00 2D 00 36 00 36 00 06 4A 90 AE	C.L.I.-.6.6..J_.
0x00000080	36 76 F3 76 00 00 00 00 00 00 00 00 00 00 00	6vsv.....
0x00000090	00 00 00 00 1B EA 09 97 49 67 43 71 BA E3 1A 35j. IgCq:c.5
0x000000A0	3E 4F 3E 7E 5A 67 A8 A6 BA 4F 5C 3D 99 0F 52 31	>O>~Zg(&:O\= .R1
0x000000B0	18 34 84 5E CE 40 86 99 3C 12 E4 6D	.4_^N@__<.dm

8. The server sends an [SMTP_AUTH_NTLM_Succeeded_Response](#) message.

```
235 2.7.0 Authentication successful
```

4.2 SMTP Client Not Successfully Authenticating to an SMTP Server

This section illustrates the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension with an example scenario in which an SMTP client attempts NTLM authentication to an SMTP server, and the authentication fails.




Figure 5: SMTP client unsuccessfully attempts authentication to SMTP server

1. As described in the previous example for unsuccessful AUTH, the SMTP client determines if the server supports NTLM authentication by sending the EHLO command and parsing the EHLO response.
2. The client sends an [SMTP AUTH NTLM Initiation Command](#) to the server.

AUTH NTLM

3. The server sends the [SMTP NTLM Supported Response](#) message, indicating that it can perform NTLM authentication.

334 ntlm supported

4. The client sends an [SMTP AUTH NTLM Blob Command](#) message.

TlRMTVNTUAABAAAAt4II4gAAAAAAAAAAAAAAAAAAAAAFAs4OAAADw==

The content of the NTLM message after base64 decoding is:

```

0x00000000 4E 54 4C 4D 53 53 50 00 01 00 00 00 B7 82 08 E2 NTLMSSP.....7_.b
0x00000010 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 .....
0x00000020 05 02 CE 0E 00 00 00 0F ..N.....

```

5. The server responds with an [SMTP_AUTH_NTLM_Blob_Response](#) message.

```

334 TlRMTVNTUAAACAAAFgAWADgAAAAIgoriYo7ENUsXagIAAAAAAAAAAGwAbABOAAA
ABQLODgAAAA9FAFgAQwBIAC0AQwBMAEkALQA2ADYAAgAWAEUAWABDAEgALQBDAEWASQ
AtADYANGABABYARQBYAEMASAAAtAEMATABJAC0ANGA2AAQAFgBlAHgAYwBoAC0AYwBsA
GkALQA2ADYAAwAWAGUAeABjAGgALQBjAGwAaQAtADYANGAAAAA

```

The content of the NTLM message after base64 decoding is:

```

0x00000000 4E 54 4C 4D 53 53 50 00 02 00 00 00 16 00 16 00 NTLMSSP.....
0x00000010 38 00 00 00 35 82 8A E2 62 8E C4 35 4B 17 6A 02 8...5 bb D5K.j.
0x00000020 00 00 00 00 00 00 00 00 6C 00 6C 00 4E 00 00 00 .....l.l.N...
0x00000030 05 02 CE 0E 00 00 00 0F 45 00 58 00 43 00 48 00 ..N.....E.X.C.H.
0x00000040 2D 00 43 00 4C 00 49 00 2D 00 36 00 36 00 02 00 -.C.L.I.-.6.6...
0x00000050 16 00 45 00 58 00 43 00 48 00 2D 00 43 00 4C 00 ..E.X.C.H.-.C.L.
0x00000060 49 00 2D 00 36 00 36 00 01 00 16 00 45 00 58 00 I.-.6.6.....E.X.
0x00000070 43 00 48 00 2D 00 43 00 4C 00 49 00 2D 00 36 00 C.H.-.C.L.I.-.6.
0x00000080 36 00 04 00 16 00 65 00 78 00 63 00 68 00 2D 00 6.....e.x.c.h.-.
0x00000090 63 00 6C 00 69 00 2D 00 36 00 36 00 03 00 16 00 c.l.i.-.6.6....
0x000000A0 65 00 78 00 63 00 68 00 2D 00 63 00 6C 00 69 00 e.x.c.h.-.c.l.i.
0x000000B0 2D 00 36 00 36 00 00 00 00 00 -.6.6....

```

6. The client then sends an SMTP_AUTH_NTLM_Blob_Command.

```

TlRMTVNTUAAADAAAAGAAAYAHwAAAAAYABgAlAAABYAFgBIAAAACAAIAF4AAAAWABYAZgAAABAAEACsAAAAANYKI4g
UCzg4AAAAPZQB4AGMAaAAAtAGMAbABpAC0ANGA2AHQAZQBzAHQARQBYAEMASAAAtAEMATABJAC0ANGA2AIqeV65h
hASwAAAAAAAAAAAAAAAAAAAHZHDVfwTU5ci0RY04eRmWy0/VWZfIfjsqdUu2WmxYUKy83PyxzbA8=

```

The content of the NTLM message after base64 decoding is:

```

0x00000000 4E 54 4C 4D 53 53 50 00 03 00 00 00 18 00 18 00 NTLMSSP.....
0x00000010 7C 00 00 00 18 00 18 00 94 00 00 00 16 00 16 00 |.....
0x00000020 48 00 00 00 08 00 08 00 5E 00 00 00 16 00 16 00 H.....^.....
0x00000030 66 00 00 00 10 00 10 00 AC 00 00 00 35 82 88 E2 f.....,...5_.b
0x00000040 05 02 CE 0E 00 00 00 0F 65 00 78 00 63 00 68 00 ..N.....e.x.c.h.
0x00000050 2D 00 63 00 6C 00 69 00 2D 00 36 00 36 00 74 00 -.c.l.i.-.6.6.t.
0x00000060 65 00 73 00 74 00 45 00 58 00 43 00 48 00 2D 00 e.s.t.e.X.C.H.-.
0x00000070 43 00 4C 00 49 00 2D 00 36 00 36 00 8A 9E 57 AE C.L.I.-.6.6. W.
0x00000080 61 84 04 B0 00 00 00 00 00 00 00 00 00 00 00 00 a .0.....
0x00000090 00 00 00 00 76 47 0D 57 F0 4D 4E 5C 8B 44 58 D3 ....vG.WpMN\DXS
0x000000A0 87 91 99 6C B4 FD 55 99 7C 87 E3 B2 A7 54 BB 65 _l4}U_|_c2'T;e
0x000000B0 A6 C5 85 0A CB CD CF CB 2C 73 6C 0F &E_.KMOK,s1.

```

7. The server sends an [SMTP_AUTH_Fail_Response](#) message.

535 5.7.3 Authentication unsuccessful

5 Security

The following sections specify security considerations for implementers of the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension.

5.1 Security Considerations for Implementers

Implementers of the NT LAN Manager (NTLM) Authentication: Simple Mail Transfer Protocol (SMTP) Extension should be aware of the security considerations of using NTLM authentication (see [\[MS-NLMP\]](#) section 5).

5.2 Index of Security Parameters

Security parameter	Section
NTLM	2 and 3

6 Appendix A: Windows Behavior

The information in this specification is applicable to the following versions of Windows:

- Windows Server 2008
- Windows Server 2003
- Windows Vista
- Windows XP
- Windows 2000

Exceptions, if any, are noted below. Unless otherwise specified, any statement of optional behavior in this specification prescribed using the terms SHOULD or SHOULD NOT implies Windows behavior in accordance with the SHOULD or SHOULD NOT prescription. Unless otherwise specified, the term MAY implies that Windows does not follow the prescription.

[<1> Section 1.5:](#) A Windows SMTP server and SMTP client use Security Support Provider Interface (SSPI) to obtain and process NTLM messages. For more information on SSPI, see [\[SSPI\]](#).

[<2> Section 3.2.5.2.2:](#) A Windows SMTP server does not permit a client to authenticate using credentials for the user identified as the "BUILTIN\Administrator" account, for security reasons. Internally, the NTLM subsystem reports to the SMTP server that the authentication succeeded, but Windows SMTP then checks the user credentials and fails the authentication, sending the [SMTP AUTH Fail Response](#) even though NTLM actually succeeded the authentication.

7 Index

A

Abstract data model

[client](#)

[server](#)

[Applicability](#)

C

[Capability negotiation](#)

Client

[abstract data model](#)

[higher-layer triggered events](#)

[initialization](#)

[local events](#)

[message processing](#)

[overview](#)

[sequencing rules](#)

[timer events](#)

[timers](#)

D

Data model - abstract

[client](#)

[server](#)

E

[Examples - overview](#)

F

[Fields - vendor-extensible](#)

G

[Glossary](#)

H

Higher-layer triggered events

[client](#)

[server](#)

I

[Implementer - security considerations](#)

[Index of security parameters](#)

[Informative references](#)

Initialization

[client](#)

[server](#)

[Introduction](#)

L

Local events

[client](#)

[server](#)

M

Message processing

[client](#)

[server](#)

Messages

[overview](#)

[syntax](#)

[transport](#)

N

[Normative references](#)

[NTLM error](#)

[NTLM reports success - returns NTLM message](#)

NTLM software interaction ([section 3.1.1.2](#), [section 3.2.1.2](#))

O

[Overview](#)

P

[Parameters - security index](#)

[Preconditions](#)

[Prerequisites](#)

R

References

[informative](#)

[normative](#)

[overview](#)

[Relationship to other protocols](#)

S

Security

[implementer considerations](#)

[overview](#)

[parameter index](#)

Sequencing rules

[client](#)

[server](#)

Server

[abstract data model](#)

[higher-layer triggered events](#)

[initialization](#)

[local events](#)

[message processing](#)

[overview](#)

[sequencing rules](#)

[timer events](#)

[timers](#)

[SMTP AUTH extensions](#)
[SMTP client messages](#)
[SMTP server messages](#)
SMTP state model ([section 3.1.1.1](#), [section 3.2.1.1](#))
[SMTP AUTH NTLM Initiation Command message](#)
[SMTP AUTH Success Response](#)
[SMTP Authentication Failed Response](#)
[SMTP Authentication Other Failure Response](#)
[SMTP NTLM Blob Command message](#)
[SMTP NTLM Blob Response](#)
[SMTP NTLM Not Supported Message](#)
[SMTP NTLM Supported Message](#)
[Standards assignments](#)
[Syntax](#)

T

Timer events

[client](#)
[server](#)

Timers

[client](#)
[server](#)
[Transport](#)

Triggered events - higher-layer

[client](#)
[server](#)

V

[Vendor-extensible fields](#)
[Versioning](#)

W

[Windows behavior](#)